www.GetPedia.com

- *More than 150,000 articles in the search database
 - *Learn how almost everything works

Image Processing Toolbox

For Use with MATLAB®

- Computation
- Visualization
- Programming



How to Contact The MathWorks:



www.mathworks.com Web

comp.soft-sys.matlab Newsgroup



support@mathworks.com

suggest@mathworks.com Product enhancement suggestions

bugs@mathworks.com Bug reports

doc@mathworks.com Documentation error reports

service@mathworks.com Order status, license renewals, passcodes info@mathworks.com Sales, pricing, and general information

Technical support



508-647-7000 Phone



508-647-7001 Fax



The MathWorks, Inc. 3 Apple Hill Drive

Natick, MA 01760-2098

Mail

For contact information about worldwide offices, see the MathWorks Web site.

Image Processing Toolbox User's Guide

© COPYRIGHT 1993 - 2004 by The MathWorks, Inc.

The software described in this document is furnished under a license agreement. The software may be used or copied only under the terms of the license agreement. No part of this manual may be photocopied or reproduced in any form without prior written consent from The MathWorks, Inc.

FEDERAL ACQUISITION: This provision applies to all acquisitions of the Program and Documentation by, for, or through the federal government of the United States. By accepting delivery of the Program or Documentation, the government hereby agrees that this software or documentation qualifies as commercial computer software or commercial computer software documentation as such terms are used or defined in FAR 12.212, DFARS Part 227.72, and DFARS 252.227-7014. Accordingly, the terms and conditions of this Agreement and only those rights specified in this Agreement, shall pertain to and govern the use, modification, reproduction, release, performance, display, and disclosure of the Program and Documentation by the federal government (or other entity acquiring for or through the federal government) and shall supersede any conflicting contractual terms or conditions. If this License fails to meet the government's needs or is inconsistent in any respect with federal procurement law, the government agrees to return the Program and Documentation, unused, to The MathWorks, Inc.

MATLAB, Simulink, Stateflow, Handle Graphics, and Real-Time Workshop are registered trademarks, and TargetBox is a trademark of The MathWorks, Inc.

Other product or brand names are trademarks or registered trademarks of their respective holders.

Printing History:	August 1993	First printing	Version 1
	May 1997	Second printing	Version 2
	April 2001	Third printing	Revised for Version 3.0
	June 2001	Online only	Revised for Version 3.1 (Release 12.1)
	July 2002	Online only	Revised for Version 3.2 (Release 13)
	May 2003	Fourth printing	Revised for Version 4.0 (Release 13.0.1)
	September 2003	Online only	Revised for Version 4.1 (Release 13SP1)
	June 2004	Online only	Revised for Version 4.2 (Release 14)
	August 2004	Online only	Revised for Version 5.0 (Release 14+)

Contents

Getting Started

What Is the Image Processing Toolbox? 1-2
Configuration Notes 1-2
Related Products 1-3
Example 1 — Some Basic Concepts 1-4
1. Read and Display an Image 1-4
2. Check How the Image Appears in the Workspace 1-8
3. Improving Image Contrast 1-6
4. Write the Image to a Disk File 1-8
5. Check the Contents of the Newly Written File 1-8
·
Example 2 — Advanced Topics 1-10
1. Read and Display an Image 1-10
2. Estimate the Value of Background Pixels 1-11
3. View the Background Approximation as a Surface 1-12
4. Create an Image with a Uniform Background 1-13
5. Adjust the Contrast in the Processed Image 1-14
6. Create a Binary Version of the Image 1-15
7. Determine the Number of Objects in the Image 1-17
8. Examine the Label Matrix 1-17
9. Display the Label Matrix as a Pseudocolor Indexed Image 1-18
10. Measure Object Properties in the Image 1-19
11. Compute Statistical Properties of Objects in the Image 1-20
Getting Help 1-22
Online Help
Image Processing Demos
MATLAB Newsgroup 1-23
•
1 . 0 14

2

${\bf Images~in~MATLAB~and~the~Image~Processing~Toolbox~.}$. 2-2
Image Types in the Toolbox	. 2-3
Binary Images	
Indexed Images	
Intensity Images	
Truecolor Images	
Converting Between Image Types	2-11
Color Space Conversions	
Converting Between Image Classes	2-13
Losing Information in Conversions	2-13
Converting Indexed Images	2-13
Multiframe Image Arrays	2-14
Reading and Writing Image Data	2-15
Reading a Graphics Image	2-15
Writing a Graphics Image	2-16
Querying a Graphics File	2-19
Converting Graphics File Formats	2-19
Working with DICOM Files	2-21
Reading Image Data from a DICOM File	2-21
Reading Metadata from a DICOM File	2-22
Writing Image Data or Metadata to a DICOM File	2-23
Example: Creating a New Series	2-25
Image Arithmetic	2-28
Image Arithmetic Saturation Rules	
Nesting Calls to Image Arithmetic Functions	
Coordinate Systems	2-30
Pixel Coordinates	
Spatial Coordinates	

Overview	. 3-2
$ \ \textbf{Understanding Handle Graphics Object Property Settings} . \ .$	
Using imshow to Display Images	. 3-4
Specifying the Initial Image Magnification	. 3-5
Controlling the Appearance of the Figure	. 3-6
Using the Image Tool to Explore Images	. 3-8
Opening the Image Tool	3-10
Specifying the Initial Image Magnification	3-11
Specifying the Colormap	
Importing Image Data from the Workspace	3-13
Exporting the Image to the Workspace	3-14
Closing the Image Tool	3-14
Printing the Image in the Image Tool	3-15
Using Image Tool Navigation Aids	3-16
Overview Navigation	
Panning the Image Displayed in the Image Tool	3-19
Zooming In and Out on an Image	
Specifying the Magnification of the Image	3-20
Getting Information about the Pixels in an Image	3-22
Determining the Value of Individual Pixels	3-22
Getting the Display Range of an Image	3-24
Viewing Pixel Values with the Pixel Region Tool	3-25
Getting Information about an Image	3-29
Adjusting the Contrast and Brightness of an Image	3-31
Understanding Contrast Adjustment	3-32
Adjusting Contrast and Brightness	3-34
Using the Window/Level Tool	3-37
Autoscaling	3-39
Viewing Multiple Images	3-41
Displaying Each Image in a Separate Figure	

Discolario e Different Land		
Displaying Different Image	Гурез	3-45
Displaying Indexed Images .		3-45
Displaying Intensity Images		3-46
Displaying Binary Images		3-47
Displaying Truecolor Images		3-49
Special Display Techniques		3-51
Adding a Colorbar		3-51
Displaying All Frames of a M	ultiframe Image at Once :	3-52
Converting a Multiframe Ima	age to a Movie	3-54
Texture Mapping		3-55
Printing Images		3-56
Printing and Handle Graphic	s Object Properties	3-56
Setting Toolbox Display Pref	ferences	3-58
Toolbox Preferences		3-58
Retrieving the Values of Tool	box Preferences	3-59
Setting the Value of Toolbox 1	Preferences	3-59
Building	GUIs with Modular Too	ols
	GUIs with Modular Too	
Overview		4-2
Overview		4-2
Overview Using Modular Tools Displaying the Target Image		4-2 4-6 4-7
Overview Using Modular Tools Displaying the Target Image Specifying the Target Image		4-2 4-6 4-7 4-7
Overview	odular Tool	4-2 4-6 4-7 4-7
Overview	odular Tool	4-2 4-6 4-7 4-11 4-13
Overview Using Modular Tools Displaying the Target Image Specifying the Target Image Specifying the Parent of a Mo Positioning the Modular Tools Example: Building a Pixel Inf	odular Tool	4-2 4-6 4-7 4-11 4-13 4-15
Overview Using Modular Tools Displaying the Target Image Specifying the Target Image Specifying the Parent of a Mo Positioning the Modular Tools Example: Building a Pixel Inf Adding Navigation Aids to a Control of the Modular Tools of the Modula	odular Tool sin a GUI formation GUI	4-2 4-6 4-7 4-7 4-11 4-13 4-15
Overview Using Modular Tools Displaying the Target Image Specifying the Target Image Specifying the Parent of a Mo Positioning the Modular Tools Example: Building a Pixel Inf Adding Navigation Aids to a O	odular Tool	4-2 4-6 4-7 4-7 4-11 4-13 4-15
Overview	odular Tool sin a GUI formation GUI	4-2 4-6 4-7 4-7 4-11 4-13 4-15 4-17 4-22

Spatial Transformations

-
)
-

T-	nterpolation
11	Interpolation Methods
	Image Types
	Image Types
Iı	nage Resizing
	Specifying the Size of the Output Image
	Specifying the Interpolation Method
	Using Filters to Prevent Aliasing
T.	nage Rotation
	Specifying the Interpolation Method
	Specifying the Size of the Output Image
	specifying the size of the output image
Iı	nage Cropping
P	erforming General Spatial Transformations
	Specifying the Transformation Type
	Performing the Transformation
	Advanced Spatial Transformation Techniques
	Image Registrati
Т	erminology
R	egistering an Image
	Point Mapping
	Example: Registering to a Digital Orthophoto

	Using the Control Point Selection Tool
	Using Correlation to Improve Control Points 6-31
7	Linear Filtering and Filter Design
	Terminology 7-2
	Linear Filtering7-4Convolution7-4Correlation7-6Filtering Using imfilter7-7Using Predefined Filter Types7-15Filter Design7-17FIR Filters7-17Frequency Transformation Method7-18Frequency Sampling Method7-19Windowing Method7-20Creating the Desired Frequency Response Matrix7-22Computing the Frequency Response of a Filter7-23
8	Transforms
	Terminology 8-2
	Fourier Transform8-3Definition of Fourier Transform8-3

Discr	ete Cosine Transform 8-1
The	e DCT Transform Matrix 8-1
DC	T and Image Compression
	n Transform
	tting the Radon Transform
	wing the Radon Transform as an Image 8-2
	ng the Radon Transform to Detect Lines 8-2
	erse Radon Transform
Exa	ample: Reconstructing an Image from Parallel Projection Data
Fan-I	Beam Projection Data 8-5
Cor	nputing Fan-Beam Projection Data 8-3
Rec	constructing an Image from Fan-Beam Projection Data 8-8
Wo	rking with Fan-Beam Projection Data8-4
	Morphological Operation
	Morphological Operation
	Morphological Operation
Гегт	Morphological Operation
Dilat i Un	inology
Dilat i Un Str	inology
Dilat i Und Str Dila	inology 9 ion and Erosion 9 derstanding Dilation and Erosion 9 ucturing Elements 9 ating an Image 9-1
Dilat Und Str Dila Ero	inology 9 ion and Erosion 9 derstanding Dilation and Erosion 9 ucturing Elements 9 ating an Image 9-1 ding an Image 9-1
Dilat Und Str Dila Ero Con	inology 9 ion and Erosion 9 derstanding Dilation and Erosion 9 ucturing Elements 9 ating an Image 9-1 ding an Image 9-1 nbining Dilation and Erosion 9-1
Dilat Und Str Dila Ero Con	inology 9 ion and Erosion 9 derstanding Dilation and Erosion 9 ucturing Elements 9 ating an Image 9-1 ding an Image 9-1
Dilati Une Str Dila Erc Cor Dila	inology 9 ion and Erosion 9 derstanding Dilation and Erosion 9 ucturing Elements 9 ating an Image 9-1 ding an Image 9-1 mbining Dilation and Erosion 9-1 ation- and Erosion-Based Functions 9-1 hological Reconstruction 9-1
Dilati Und Str Dila Ero Con Dila Morp Ma	inology 9 ion and Erosion 9 derstanding Dilation and Erosion 9 ucturing Elements 9-1 ating an Image 9-1 ding an Image 9-1 nbining Dilation and Erosion 9-1 ation- and Erosion-Based Functions 9-1 hological Reconstruction 9-1 rker and Mask 9-1
Dilat: Under Strain Dilate Con Dilate Morp Ma	inology 9 ion and Erosion 9 derstanding Dilation and Erosion 9 ucturing Elements 9- ating an Image 9-1 ding an Image 9-1 mbining Dilation and Erosion 9-1 ation- and Erosion-Based Functions 9-1 hological Reconstruction 9-1 rker and Mask 9-1 el Connectivity 9-2
Dilat: Und Str Dilat: Cor Cor Dilat: Morp Ma Pix Flo	inology 9 ion and Erosion 9 derstanding Dilation and Erosion 9 ucturing Elements 9-1 ating an Image 9-1 ding an Image 9-1 nbining Dilation and Erosion 9-1 ation- and Erosion-Based Functions 9-1 hological Reconstruction 9-1 rker and Mask 9-1

Distance Transform	9-37
Objects, Regions, and Feature Measurement	9-40
Connected-Component Labeling	9-40
Selecting Objects in a Binary Image	9-42
Finding the Area of the Foreground of a Binary Image	9-42
Finding the Euler Number of a Binary Image	9-43
Lookup Table Operations	9-44
Analyzing and Enhancing I	mages
Terminology	10-2
Pixel Values and Statistics	10-3
Pixel Selection	10-3
Intensity Profile	10-5
Image Contours	10-9
Image Histogram	
Summary Statistics	
Region Property Measurement	
Image Analysis	10-13
Edge Detection	
Boundary Tracing	
Line Detection Using the Hough Transform	
Quadtree Decomposition	
Texture Analysis	10-26
Texture Filter Functions	10-26
Gray-Level Co-occurrence Matrix (GLCM)	
Intensity Adjustment	10-36
Adjusting Intensity Values to a Specified Range	
Histogram Equalization	
Contract-Limited Adaptive Histogram Equalization	

	Decorrelation Stretching 10-4
	Noise Removal10-4Using Linear Filtering10-4Using Median Filtering10-4Using Adaptive Filtering10-5
I 1 「	Region-Based Processing
· - '	Terminology
	Specifying a Region of Interest11-Selecting a Polygon11-Other Selection Methods11-
	Filtering a Region11-Example: Filtering a Region in an Image11-Specifying the Filtering Operation11-
	Filling a Region
 2	Image Deblurring
	Terminology
	Understanding Deblurring12-Causes of Blurring12-Deblurring Model12-
	Using the Deblurring Functions 12- Deblurring with the Wiener Filter 12- Deblurring with a Regularized Filter 12-

	Colo
Teı	rminology
Ι	rking with Different Screen Bit Depths
Į F	ducing the Number of Colors in an Image 13 Using rgb2ind 13 Reducing Colors in an Indexed Image 13 Dithering 13
(E	Averting Color Data Between Color Spaces 13-Converting Between Device-Independent Color Spaces 13-Converting Profile-Based Conversions
	Neighborhood and Block Operation
Тог	rminology

Linear and Nonlinear Filtering
Overlap
Solumn Processing
Sliding Neighborhoods
Sliding Neighborhoods
Distinct Blocks
Function Reference
unctions – Categorical List
Modular Interactive Tools
Spatial Transformation and Registration
Image Analysis and Statistics15-Image Arithmetic15-
Image Enhancement and Restoration 15-1
Linear Filtering and Transforms 15-1
Morphological Operations
Region-Based, Neighborhood, and Block Processing 15-1
Colormap and Color Space Functions
Wiscenaneous Functions
unctions – Alphabetical List

Getting Started

This chapter contains two examples to get you started doing image processing using MATLAB® and the Image Processing Toolbox. The examples contain cross-references to other sections in the documentation manual that have in-depth discussions on the concepts presented in the examples.

What Is the Image Processing Toolbox? (p. 1-2)	Introduces the Image Processing Toolbox and its capabilities.
Example 1 — Some Basic Concepts (p. 1-4)	Guides you through an example of some of the basic image processing capabilities of the toolbox, including reading, writing, and displaying images
Example 2 — Advanced Topics (p. 1-10)	Guides you through some advanced image processing topics, including components labeling, object property measurement, image arithmetic, morphological image processing, and contrast enhancement
Getting Help (p. 1-22)	Provides pointers to additional sources of information

What Is the Image Processing Toolbox?

The Image Processing Toolbox is a collection of functions that extend the capability of the MATLAB numeric computing environment. The toolbox supports a wide range of image processing operations, including

- Spatial image transformations
- Morphological operations
- Neighborhood and block operations
- Linear filtering and filter design
- Transforms
- Image analysis and enhancement
- Image registration
- Deblurring
- Region of interest operations

Many of the toolbox functions are MATLAB M-files, a series of MATLAB statements that implement specialized image processing algorithms. You can view the MATLAB code for these functions using the statement

```
type function name
```

You can extend the capabilities of the Image Processing Toolbox by writing your own M-files, or by using the toolbox in combination with other toolboxes, such as the Signal Processing Toolbox and the Wavelet Toolbox.

For a list of the new features in this version, see the Release Notes documentation.

Configuration Notes

To determine if the Image Processing Toolbox is installed on your system, type this command at the MATLAB prompt.

ver

When you enter this command, MATLAB displays information about the version of MATLAB you are running, including a list of all toolboxes installed on your system and their version numbers.

For information about installing the toolbox, see the MATLAB Installation Guide for your platform.

For the most up-to-date information about system requirements, see the system requirements page, available in the products area at The MathWorks Web site (www.mathworks.com).

Related Products

The MathWorks provides several products that are especially relevant to the kinds of tasks you can perform with Image Processing Toolbox.

For more information about any of these products, see either

- The online documentation for that product if it is installed or if you are reading the documentation from the CD
- The MathWorks Web site, at http://www.mathworks.com; see the "products" section

The toolboxes listed below all include functions that extend MATLAB. The blocksets all include blocks that extend Simulink[®].

Product	Description		
DSP Blockset	Design and simulate DSP systems		
Image Acquisition Toolbox	Connect to image acquisition hardware and bring frames of image data into the MATLAE workspace		
Mapping Toolbox	Analyze and visualize geographically based information		
MATLAB	The Language of Technical Computing		
Signal Processing Toolbox	Perform signal processing, analysis, and algorithm development		
Wavelet Toolbox	Analyze, compress, and denoise signals and images using wavelet techniques		

Example 1 — Some Basic Concepts

This example introduces some basic image processing concepts, including reading and writing images, performing histogram equalization on an image, and getting information about an image. The example breaks this process into the following steps:

Step 1: Read and display an image

Step 2: Check how the image appears in the workspace

Step 3: Improving image contrast

Step 4: Write the image to a disk file

Step 5: Get information about a graphics file

Before beginning with this example, you should already have installed the Image Processing Toolbox and have started MATLAB. If you are new to MATLAB, read the MATLAB Getting Started documentation to learn about basic MATLAB concepts.

1. Read and Display an Image

Clear the MATLAB workspace of any variables and close open figure windows.

```
clear, close all
```

To read an image, use the imread command. The example reads one of the sample images included with the Image Processing Toolbox, pout.tif, and stores it in an array named I.

```
I = imread('pout.tif');
```

imread infers from the file that the graphics file format is Tagged Image File Format (TIFF). For the list of supported graphics file formats, see the imread function reference documentation.

Now display the image. The toolbox includes two image display functions: imshow and imtool. imshow is the toolbox's fundamental image display function. imtool starts the Image Tool which presents an integrated environment for displaying images and performing some common image processing tasks. The Image Tool provides all the image display capabilities of

imshow but also provides access to several other tools for navigating and exploring images, such as scroll bars, the Pixel Region tool, Image Information tool, and the Contrast Adjustment tool. For more information, see Chapter 3, "Displaying and Exploring Images.".

You can use either function to display an image. This example uses imshow. imshow(I)



Intensity Image pout.tif

2. Check How the Image Appears in the Workspace

To see how the imread function stores the image data in the workspace, check the Workspace browser in the MATLAB desktop. The Workspace browser displays information about all the variables you create during a MATLAB session. The imread function returned the image data in the variable I, which is a 291-by-240 element array of uint8 data. MATLAB can store images as uint8, uint16, or double arrays.

You can also get information about variables in the workspace by calling the whos command.

whos Name	Size	Bytes	Class
I	291x240	69840	uint8 array


Grand total is 69840 elements using 69840 bytes

For more information about image storage classes, see "Reading a Graphics Image" on page 2-15.

3. Improving Image Contrast

As you can see, pout.tif is a somewhat low contrast image. To see the distribution of intensities in pout.tif, you can create a histogram by calling the imhist function. (Precede the call to imhist with the figure command so that the histogram does not overwrite the display of the image I in the current figure window.)

figure, imhist(I)



Notice how the intensity range is rather narrow. It does not cover the potential range of [0, 255], and is missing the high and low values that would result in good contrast.

The toolbox provides several ways to improve the contrast in an image. One way is to call the histeq function to spread the intensity values over the full range of the image, a process called *histogram equalization*.

I2 = histeq(I);

Display the new equalized image, I2, in a new figure window.


figure, imshow(I2)



Equalized Version of pout.tif

Call imhist again to create a histogram of the equalized image I2. If you compare the two histograms, the histogram of I2 is more spread out than the histogram of I1.

figure, imhist(I2)



The toolbox includes several other functions that perform contrast adjustment, including the imadjust and adapthisteq functions. See "Intensity Adjustment" on page 10-36 for more information. In addition, the toolbox includes an interactive tool, called the Adjust Contrast tool, that you can use to adjust the contrast and brightness of an image interactively. To start this tool, call the imcontrast function. For more information, see "Adjusting the Contrast and Brightness of an Image" on page 3-31.

4. Write the Image to a Disk File

To write the newly adjusted image I2 to a disk file, use the imwrite function. If you include the filename extension '.png', the imwrite function writes the image to a file in Portable Network Graphics (PNG) format, but you can specify other formats.

```
imwrite (I2, 'pout2.png');
```

See the imwrite function reference page for a list of file formats it supports. See also "Writing a Graphics Image" on page 2-16 for a tutorial discussion on writing images using the Image Processing Toolbox.

5. Check the Contents of the Newly Written File

To see what imwrite wrote to the disk file, use the imfinfo function. This function returns information about the image in the file, such as its format, size, width, and height. See "Querying a Graphics File" on page 2-19 for more information about using imfinfo.

```
Colormap: []
             Histogram: []
         InterlaceType: 'none'
          Transparency: 'none'
SimpleTransparencyData: []
       BackgroundColor: []
       RenderingIntent: []
        Chromaticities: []
                 Gamma: []
           XResolution: []
           YResolution: []
        ResolutionUnit: []
               XOffset: []
               YOffset: []
            OffsetUnit: []
       SignificantBits: []
          ImageModTime: '29 Dec 2003 14:34:39 +0000'
                 Title: []
                Author: []
           Description: []
             Copyright: []
          CreationTime: []
              Software: []
            Disclaimer: []
               Warning: []
                Source: []
               Comment: []
             OtherText: []
```

Example 2 - Advanced Topics

This example introduces some advanced image processing concepts. The example calculates statistics about objects in the image but, before it performs these calculations, it preprocesses the image to achieve better results. The preprocessing involves creating a uniform background in the image and converting the image into a binary image. The example breaks this process into the following steps:

Step 1:	Read and display an image
Step 2:	Estimate the approximate value of background pixels
Step 3:	View the background approximation as a surface
Step 4:	Create an image with a uniform background
Step 5:	Adjust the contrast in the uniform image
Step 6:	Create a binary version of the image
Step 7:	Determine the number of objects in the image
Step 8:	Examine the label matrix
Step 9:	Display the label matrix as a pseudocolor indexed image
Step 10:	Measure properties of objects in the image
Step 11:	Compute statistics of objects in the image

1. Read and Display an Image

Clear the MATLAB workspace of any variables, close open figure windows, and close all open Image Tools.

```
clear, close all, imtool close all
Read and display the intensity image rice.png.
I = imread('rice.png');
```

imshow(I)



Intensity Image rice.png

2. Estimate the Value of Background Pixels

In the sample image, the background illumination is brighter in the center of the image than at the bottom. In this step, the example uses a morphological opening operation to estimate the background illumination. An opening is an erosion followed by a dilation, using the same structuring element for both operations. The morphological opening has the effect of removing objects that cannot completely contain the structuring element. For more information about morphological image processing, see Chapter 9, "Morphological Operations."

The example calls the imopen function to perform the morphological opening operation. Note the call to the strel function, which creates a disk-shaped structuring element with a radius of 15. To remove the rice grains from the image, the structuring element must be large enough so that it cannot fit entirely inside a single grain of rice.

```
background = imopen(I,strel('disk',15));
```

To see the estimated background image, type

figure, imshow(background)

3. View the Background Approximation as a **Surface**


Use the surf command to create a surface display of the background approximation background. The surf command creates colored parametric surfaces that enable you to view mathematical functions over a rectangular region. The surf function requires data of class double, however, so you first need to convert background using the double command.

```
figure, surf(double(background(1:8:end,1:8:end))),zlim([0 255]);
set(gca, 'ydir', 'reverse');
```

The example uses MATLAB indexing syntax to view only 1 out of 8 pixels in each direction; otherwise the surface plot would be too dense. The example also sets the scale of the plot to better match the range of the uint8 data and reverses the y-axis of the display to provide a better view of the data (the pixels at the bottom of the image appear at the front of the surface plot).

In the surface display, [0, 0] represents the origin, or upper left corner of the image. The highest part of the curve indicates that the highest pixel values of background (and consequently rice.png) occur near the middle rows of the image. The lowest pixel values occur at the bottom of the image and are represented in the surface plot by the lowest part of the curve.

The surface plot is a Handle Graphics[®] object. You can use object properties to fine-tune its appearance. For information on working with MATLAB graphics, see the MATLAB graphics documentation.



4. Create an Image with a Uniform Background

To create a more uniform background, subtract the background image, background, from the original image, ${\tt I}$.

I2 = imsubtract(I,background);

Because subtraction, like many MATLAB mathematical operations, is only supported for data of class double, you must use the Image Processing Toolbox image arithmetic imsubtract function.

Display the image with its more uniform background.

figure, imshow(I2)




Image with Uniform Background

5. Adjust the Contrast in the Processed Image

After subtraction, the image has a uniform background but is now a bit too dark. Use imadjust to adjust the contrast of the image.

```
I3 = imadjust(I2);
```

imadjust increases the contrast of the image by saturating 1% of the data at both low and high intensities of I2 and by stretching the intensity values to fill the uint8 dynamic range. See the reference page for imadjust for more information.

Display the adjusted image 13.

```
figure, imshow(I3);
```



Image After Intensity Adjustment

6. Create a Binary Version of the Image

Create a binary version of the image by using thresholding. The function graythresh automatically computes an appropriate threshold to use to convert the intensity image to binary. The im2bw function performs the conversion.

```
level = graythresh(I3);
bw = im2bw(I3,level);
figure, imshow(bw)
```



Binary Version of the Image

The binary image bw returned by im2bw is of class logical, as can be seen in this call to whos. The Image Processing Toolbox uses logical arrays to represent binary images. For more information, see "Binary Images" on page 2-4.

whos

MATLAB responds with

Name	Size	Bytes	Class
I	256x256	65536	uint8 array
12	256x256	65536	uint8 array
13	256x256	65536	uint8 array
background	256x256	65536	uint8 array
bw	256x256	65536	logical array
level	1x1	8	double array

Grand total is 327681 elements using 327688 bytes

7. Determine the Number of Objects in the Image

After converting the image to a binary image, you can use the bwlabel function to determine the number of grains of rice in the image. The bwlabel function labels all the components in the binary image bw and returns the number of components it finds in the image in the output value, numObjects.

```
[labeled,numObjects] = bwlabel(bw,4);
numObjects
ans =
```

The accuracy of the results depends on a number of factors, including

- The size of the objects
- Whether or not any objects are touching (in which case they might be labeled as one object)
- The accuracy of the approximated background
- The connectivity selected. The parameter 4, passed to the bwlabel function, means that pixels must touch along an edge to be considered connected. For more information about the connectivity of objects, see "Pixel Connectivity" on page 9-23.

8. Examine the Label Matrix


To better understand the label matrix returned by the bwlabel function, this step explores the pixel values in the image. There are several ways to get a closeup view of pixel values. For example, you can use imcrop to select a small portion of the image. Another way is to use toolbox Pixel Region tool to examine pixel values. Display the label matrix, using imshow,

```
figure, imshow(labeled);
Start the Pixel Region tool.
impixelregion
```

By default, it automatically associates itself with the image in the current figure. The Pixel Region tool draws a rectangle, called the *pixel region rectangle*, in the center of the visible part of the image. This rectangle defines

which pixels are displayed in the Pixel Region tool. As you move the rectangle, the Pixel Region tool updates the pixel values displayed in the window. For more information about using the toolbox modular interactive tools, see Chapter 4, "Building GUIs with Modular Tools.".

The following figure shows the Image Viewer with the Pixel Region rectangle positioned over the edges of two rice grains. Note how all the pixels in the rice grains have the values assigned by the bwlabel function and the background pixels have the value 0 (zero).



Examining the Label Matrix with the Pixel Region Tool

9. Display the Label Matrix as a Pseudocolor Indexed Image

A good way to view a label matrix is to display it as a pseudocolor indexed image. In the pseudocolor image, the number that identifies each object in the label matrix maps to a different color in the associated colormap matrix. The colors in the image make objects easier to distinguish.

To view a label matrix in this way, use the label2rgb function. Using this function, you can specify the colormap, the background color, and how objects in the label matrix map to colors in the colormap.

```
pseudo_color = label2rgb(labeled, @spring, 'c', 'shuffle');
imshow(pseudo color);
```



Label Matrix Displayed as Pseudocolor Image

10. Measure Object Properties in the Image

The regionprops command measures object or region properties in an image and returns them in a structure array. When applied to an image with labeled components, it creates one structure element for each component.

This example uses regionprops to create a structure array containing some basic properties for labeled. When you set the properties parameter to 'basic', the regionprops function returns three commonly used measurements: area, centroid (or center of mass), and bounding box. The bounding box represents the smallest rectangle that can contain a region, or in this case, a grain of rice.

BoundingBox

To find the area of the 51st labeled component, access the Area field in the 51st element in the graindata structure array. Note that structure field names are case sensitive.

```
graindata(51).Area
returns the following results
ans =
140
```

To find the smallest possible bounding box and the centroid (center of mass) for the same component, use this code:

```
graindata(51).BoundingBox, graindata(51).Centroid
ans =
   107.5000   4.5000   13.0000   20.0000
ans =
   114.5000   15.4500
```

11. Compute Statistical Properties of Objects in the Image

Now use MATLAB functions to calculate some statistical properties of the thresholded objects. First use max to find the size of the largest grain. (In this example, the largest grain is actually two grains of rice that are touching.)


```
max([graindata.Area])
returns
  ans =
404
```

Use the find command to return the component label of the grain of rice with this area.

```
biggrain = find([graindata.Area]==404)
returns
biggrain =
    59
Find the mean of all the rice grain sizes.
    mean([graindata.Area])
returns
ans =
    175.0396
```

Make a histogram containing 20 bins that show the distribution of rice grain sizes. The histogram shows that the most common sizes for rice grains in this image are in the range of 150 to 250 pixels.

hist([graindata.Area],20)



Getting Help

For more information about the topics covered in these exercises, read the tutorial chapters that make up the remainder of this documentation. For reference information about any of the Image Processing Toolbox functions, see the online "Function Reference", which complements the M-file help that is displayed in the MATLAB command window when you type

help functionname

For example,

help imtool

Online Help

The Image Processing Toolbox User's Guide documentation is available online in both HTML and PDF formats. To access the HTML help, select **Help** from the menu bar of the MATLAB desktop. In the Help Navigator pane, click the **Contents** tab and expand the **Image Processing Toolbox** topic in the list.

To access the PDF help, click **Image Processing Toolbox** in the **Contents** tab of the Help browser and go to the link under "Printable Documentation (PDF)." (Note that to view the PDF help, you must have Adobe's Acrobat Reader installed.)

Terminology

At the beginning of each chapter are glossaries of words you need to know to understand the information in the chapter. These tables clarify how we use terms that may be used in several different ways in image processing literature. For example:

- In the field of image processing, one word is sometimes used to describe more than one concept. For example the *resolution* of an image can describe the height and width of an image as a quantity of pixels in each direction, or it can describe the number of pixels per linear measure, such as 100 dots per inch.
- In the field of image processing, the same concepts are sometimes described by different terminology. For example, a *grayscale* image can also be called an *intensity* image.

Image Processing Demos

The Image Processing Toolbox is supported by a full complement of demo applications. These are very useful as templates for your own end-user applications, or for seeing how to use and combine your toolbox functions for powerful image analysis and enhancement.

To view all the Image Processing Toolbox demos, call the iptdemos function. This displays an HTML page in the MATLAB Help browser that lists all the Image Processing Toolbox demos.

You can also view this page by starting the MATLAB Help browser and clicking the **Demos** tab in the Help Navigator pane. From the list of products with demos, select the Image Processing Toolbox.

The toolbox demos are located under the subdirectory

matlabroot\toolbox\images\imdemos

where matlabroot represents your MATLAB installation directory.

MATLAB Newsgroup

If you read newsgroups on the Internet, you might be interested in the MATLAB newsgroup (comp.soft-sys.matlab). This newsgroup gives you access to an active MATLAB user community. It is an excellent way to seek advice and to share algorithms, sample code, and M-files with other MATLAB users.

Image Credits

This table lists the copyright owners of the images used in the Image Processing Toolbox documentation.

Image	Source
cameraman	Copyright Massachusetts Institute of Technology. Used with permission.
cell	Cancer cell from a rat's prostate, courtesy of Alan W. Partin, M.D., Ph.D., Johns Hopkins University School of Medicine.
circuit	Micrograph of 16-bit A/D converter circuit, courtesy of Steve Decker and Shujaat Nadeem, MIT, 1993.
concordaerial and westconcordaerial	Visible color aerial photographs courtesy of mPower3/Emerge.
concordorthophoto and westconcordorthophoto	Orthoregistered photographs courtesy of Massachusetts Executive Office of Environmental Affairs, MassGIS.
forest	Photograph of Carmanah Ancient Forest, British Columbia, Canada, courtesy of Susan Cohen.
LAN files	Permission to use Landsat [™] data sets provided by Space Imaging, LLC, Denver, Colorado.
liftingbody	Picture of M2-F1 lifting body in tow, courtesy of NASA (Image number E-10962).
m83	M83 spiral galaxy astronomical image courtesy of Anglo-Australian Observatory, photography by David Malin.

Image	Source
moon	Copyright Michael Myers. Used with permission.
saturn	Voyager 2 image, 1981-08-24, NASA catalog #PIA01364.
solarspectra	Courtesy of Ann Walker. Used with permission.
tissue	Courtesy of Alan W. Partin, M.D., PhD., Johns Hopkins University School of Medicine.
trees	Trees with a View, watercolor and ink on paper, copyright Susan Cohen. Used with permission.

Introduction

This chapter introduces you to the fundamentals of image processing using MATLAB and the Image Processing Toolbox.

Images in MATLAB and the Image Processing Toolbox (p. 2-2)	How images are represented in MATLAB and the Image Processing Toolbox
Image Types in the Toolbox (p. 2-3)	Fundamental image types supported by the Image Processing Toolbox
Converting Between Image Types (p. 2-11)	Converting between the image types
Converting Between Image Classes (p. 2-13)	Converting image data from one class to another
Multiframe Image Arrays (p. 2-14)	Working with multiframe data
Reading and Writing Image Data (p. 2-15)	Reading data into the MATLAB workspace, writing data to graphics files, and getting information about image files
Working with DICOM Files (p. 2-21)	Reading and writing DICOM files
Image Arithmetic (p. 2-28)	Adding, subtracting, multiplying, and dividing images
Coordinate Systems (p. 2-30)	Pixel versus spatial coordinates

Images in MATLAB and the Image Processing Toolbox

The basic data structure in MATLAB is the array, an ordered set of real or complex elements. This object is naturally suited to the representation of *images*, real-valued ordered sets of color or intensity data.

MATLAB stores most images as two-dimensional arrays (i.e., matrices), in which each element of the matrix corresponds to a single pixel in the displayed image. (Pixel is derived from picture element and usually denotes a single dot on a computer display.) For example, an image composed of 200 rows and 300 columns of different colored dots would be stored in MATLAB as a 200-by-300 matrix. Some images, such as truecolor images, require a three-dimensional array, where the first plane in the third dimension represents the red pixel intensities, the second plane represents the green pixel intensities, and the third plane represents the blue pixel intensities.

This convention makes working with images in MATLAB similar to working with any other type of matrix data, and makes the full power of MATLAB available for image processing applications. For example, you can select a single pixel from an image matrix using normal matrix subscripting.

I(2,15)

This command returns the value of the pixel at row 2, column 15 of the image I.

Note MATLAB expresses pixel coordinates by row and column (r,c). This is the reverse of spatial coordinates that are expressed as width and height (x,y). In the reference pages for toolbox functions, when the syntax for a function uses r and c, it refers to the pixel coordinate system. When the syntax uses x and y, it refers to the spatial coordinate system.

Image Types in the Toolbox


The Image Processing Toolbox defines four basic types of images, summarized in the following table. These image types determine the way MATLAB interprets data matrix elements as pixel colors. The sections that follow provide more information about each image type. See also "Converting Between Image Types" on page 2-11.

lmage Type	Interpretation	
Binary	Logical array containing only 0's and 1's, interpreted as black and white, respectively. Also known as a <i>bilevel</i> image.	
Indexed	Array of class logical, uint8, uint16, single, or double whose pixel values are direct indices into a colormap. The colormap is an <i>m</i> -by-3 array of class double. Also known as a <i>pseudocolor</i> image.	
	Note : For single or double arrays, integer values range from $[1, p]$. For logical, uint8, or uint16 arrays, values range from $[0, p-1]$	
Intensity	Array of class uint8, uint16, int16, single, or double whose pixel values specify intensity values. Also known as a <i>grayscale</i> image	
	Note : For single or double arrays, values range from [0, 1]. For uint8, values range from [0,255]. For uint16, values range from [0,65535]. For int16, values range from [-32768, 32767].	
Truecolor	<i>m</i> -by- <i>n</i> -by-3 array of class uint8, uint16, single, or double whose pixel values specify intensity values. Also known as an <i>RGB</i> image.	
	Note : For single or double arrays, values range from [0, 1]. For uint8, values range from [0, 255]. For uint16, values range from [0, 65535].	

Binary Images

In a binary image, also known as a bilevel image, each pixel assumes one of only two discrete values: 1 or 0. A binary image is stored as a logical array.

The following figure shows a binary image with a close-up view of some of the pixel values.



Pixel Values in a Binary Image

Indexed Images

An indexed image consists of an array, called X in this documentation, and a colormap matrix, called map. The pixel values in the array are direct indices into a colormap.

The colormap matrix is an m-by-3 array of class double containing floating-point values in the range [0,1]. Each row of map specifies the red, green, and blue components of a single color. An indexed image uses direct mapping of pixel values to colormap values. The color of each image pixel is determined by using the corresponding value of X as an index into map.

A colormap is often stored with an indexed image and is automatically loaded with the image when you use the imread function. After you read the image and the colormap into the MATLAB workspace as separate variables, you must keep track of the association between the image and colormap. However, you are not limited to using the default colormap—you can use any colormap that you choose.

The relationship between the values in the image matrix and the colormap depends on the class of the image matrix. If the image matrix is of class single or double, it normally contains integer values 1 through p, where p is the length of the colormap, the value 1 points to the first row in the colormap, the value 2 points to the second row, and so on. If the image matrix is of class logical, uint8 or uint16, the value 0 points to the first row in the colormap, the value 1 points to the second row, and so on.

The following figure illustrates the structure of an indexed image. In the figure, the image matrix is of class double, so the value 5 points to the fifth row of the colormap.




Image Courtesy of Susan Cohen

Pixel Values Index to Colormap Entries in Indexed Images


Intensity Images

An intensity image, also known as a grayscale image, is a data matrix, I, whose values represent intensities within some range. MATLAB stores an intensity image as a individual matrix, with each element of the matrix corresponding to one image pixel. The matrix can be of class uint8, uint16, int16, single, or

double. While intensity images are rarely saved with a colormap, MATLAB uses a colormap to display them.

For a matrix of class single or double, using the default grayscale colormap, the intensity 0 represents black and the intensity 1 represents white. For a matrix of type uint8, uint16, or int16, the intensity intmin(class(I)) represents black and the intensity intmax(class(I)) represents white.

The figure below depicts an intensity image of class double.



Pixel Values in an Intensity Image Define Gray Levels


Truecolor Images

A truecolor image, also known as an RGB image, is stored in MATLAB as an m-by-n-by-3 data array that defines red, green, and blue color components for each individual pixel. Truecolor images do not use a colormap. The color of each pixel is determined by the combination of the red, green, and blue intensities stored in each color plane at the pixel's location. Graphics file formats store truecolor images as 24-bit images, where the red, green, and blue components

are 8 bits each. This yields a potential of 16 million colors. The precision with which a real-life image can be replicated has led to the commonly used term truecolor image.

A truecolor array can be of class uint8, uint16, single, or double. In a truecolor array of class single or double, each color component is a value between 0 and 1. A pixel whose color components are (0,0,0) is displayed as black, and a pixel whose color components are (1,1,1) is displayed as white. The three color components for each pixel are stored along the third dimension of the data array. For example, the red, green, and blue color components of the pixel (10,5) are stored in RGB(10,5,1), RGB(10,5,2), and RGB(10,5,3), respectively.

The following figure depicts a truecolor image of class double.




The Color Planes of an RGB Image

To determine the color of the pixel at (2,3), you would look at the RGB triplet stored in (2,3,1:3). Suppose (2,3,1) contains the value 0.5176, (2,3,2) contains 0.1608, and (2,3,3) contains 0.0627. The color for the pixel at (2,3) is

0.5176 0.1608 0.0627

To further illustrate the concept of the three separate color planes used in an RGB image, the code sample below creates a simple RGB image containing uninterrupted areas of red, green, and blue, and then creates one image for each of its separate color planes (red, green, and blue). It displays each color plane image separately, and also displays the original image.

```
RGB=reshape(ones(64,1)*reshape(jet(64),1,192),[64,64,3]);
R=RGB(:,:,1);
G=RGB(:,:,2);
B=RGB(:,:,3);
imshow(R)
figure, imshow(G)
figure, imshow(B)
figure, imshow(RGB)
```



The Separated Color Planes of an RGB Image

Notice that each separated color plane in the figure contains an area of white. The white corresponds to the highest values (purest shades) of each separate color. For example, in the Red Plane image, the white represents the highest concentration of pure red values. As red becomes mixed with green or blue, gray pixels appear. The black region in the image shows pixel values that contain no red values, i.e., R == 0.

Converting Between Image Types

You might need to convert an image from one type to another. For example, if you want to filter a color image that is stored as an indexed image, you should first convert it to truecolor format. When you apply the filter to the truecolor image, MATLAB filters the intensity values in the image, as is appropriate. If you attempt to filter the indexed image, MATLAB simply applies the filter to the indices in the indexed image matrix, and the results might not be meaningful.

Note When you convert an image from one format to another, the resulting image might look different from the original. For example, if you convert a color indexed image to an intensity image, the resulting image is grayscale, not color.

The following table lists all the image type conversion functions in the Image Processing Toolbox.

Function	Description
dither	Create a binary image from a grayscale intensity image by dithering or create an indexed image from a truecolor image by dithering
gray2ind	Create an indexed image from a grayscale intensity image
grayslice	Create an indexed image from a grayscale intensity image by thresholding
im2bw	Create a binary image from a grayscale intensity image, indexed image, or truecolor image, based on a luminance threshold
ind2gray	Create a grayscale intensity image from an indexed image
ind2rgb	Create a truecolor image from an indexed image

Function	Description	
mat2gray	Create a grayscale intensity image from data in a matrix, by scaling the data	
rgb2gray	Create a grayscale intensity image from a truecolor image	
rgb2ind	Create an indexed image from a truecolor image	

You can also perform certain conversions just using MATLAB syntax. For example, you can convert an intensity image to truecolor format by concatenating three copies of the original matrix along the third dimension.

$$RGB = cat(3,I,I,I);$$

The resulting truecolor image has identical matrices for the red, green, and blue planes, so the image displays as shades of gray.

In addition to these standard conversion tools, there are some functions that return a different image type as part of the operation they perform. For example, the region-of-interest routines each return a binary image that you can use to mask an indexed or intensity image for filtering or for other operations.

Color Space Conversions

The Image Processing Toolbox represents colors as RGB values, either directly (in a truecolor image) or indirectly (in an indexed image). However, there are other methods for representing colors. For example, a color can be represented by its hue, saturation, and value components (HSV). Different methods for representing colors are called *color spaces*.

The toolbox provides a set of routines for converting between color spaces. The image processing functions themselves assume all color data is RGB, but you can process an image that uses a different color space by first converting it to RGB, and then converting the processed image back to the original color space. For more information about color space conversion routines, see Chapter 13, "Color."

Converting Between Image Classes

You can convert uint8 and uint16 image data to double using the MATLAB double function. However, converting between classes changes the way MATLAB and the toolbox interpret the image data. If you want the resulting array to be interpreted properly as image data, you need to rescale or offset the data when you convert it.

For easier conversion of classes, use one of these toolbox functions: im2uint8, im2uint16, im2single, or im2double. These functions automatically handle the rescaling and offsetting of the original data of any image class. For example, this command converts a double-precision RGB image with data in the range [0,1] to a uint8 RGB image with data in the range [0,255].

RGB2 = im2uint8(RGB1);

Losing Information in Conversions

When you convert to a class that uses fewer bits to represent numbers, you generally lose some of the information in your image. For example, a uint16 intensity image is capable of storing up to 65,536 distinct shades of gray, but a uint8 intensity image can store only 256 distinct shades of gray. When you convert a uint16 intensity image to a uint8 intensity image, im2uint8 quantizes the gray shades in the original image. In other words, all values from 0 to 127 in the original image become 0 in the uint8 image, values from 128 to 385 all become 1, and so on.

Converting Indexed Images

It is not always possible to convert an indexed image from one storage class to another. In an indexed image, the image matrix contains only indices into a colormap, rather than the color data itself, so no quantization of the color data is possible during the conversion.

For example, a uint16 or double indexed image with 300 colors cannot be converted to uint8, because uint8 arrays have only 256 distinct values. If you want to perform this conversion, you must first reduce the number of the colors in the image using the imapprox function. This function performs the quantization on the colors in the colormap, to reduce the number of distinct colors in the image. See "Reducing Colors in an Indexed Image" on page 13-12 for more information.

Multiframe Image Arrays

For some applications, you might need to work with collections of images related by time or view, such as magnetic resonance imaging (MRI) slices or movie frames.

The Image Processing Toolbox provides support for storing multiple images in the same array. Each separate image is called a *frame*. If an array holds multiple frames, they are concatenated along the fourth dimension. For example, an array with five 480-by-640 truecolor images would be 480-by-640-by-3-by-5. A similar multiframe intensity or indexed image would be 480-by-640-by-1-by-5.

Use the cat command to store separate images in one multiframe array. For example, if you have a group of images A1, A2, A3, A4, and A5, you can store them in a single array using

```
A = cat(4,A1,A2,A3,A4,A5)
```

You can also extract frames from a multiframe image. For example, if you have a multiframe image MULTI, this command extracts the third frame.

```
FRM3 = MULTI(:,:,:,3)
```

Note that, in a multiframe image array, each image must be the same size and have the same number of planes. In a multiframe indexed image, each image must also use the same colormap.

Multiframe Support Limitations

Many of the functions in the toolbox operate only on the first two or first three dimensions. You can still use four-dimensional arrays with these functions, but you must process each frame individually. For example, this call displays the seventh frame in the array MULTI.

```
imshow(MULTI(:,:,:,7))
```

If you pass an array to a function and the array has more dimensions than the function is designed to operate on, your results can be unpredictable. In some cases, the function simply processes the first frame of the array, but in other cases the operation does not produce meaningful results.

See the reference pages for information about how individual functions work with the dimensions of an image array.

Reading and Writing Image Data

This section describes how to read and write image data. Topics include

- Reading data stored in many standard graphics file formats
- Writing data to files in many standard graphics file formats
- Querying graphics image files for information stored in header fields
- Converting images between graphics file formats

For information about reading and writing data in Digital Imaging and Communications in Medicine (DICOM) file format, see "Working with DICOM Files" on page 2-21.

Reading a Graphics Image

The imread function reads an image from any supported graphics image file format, in any of the supported bit depths. Most image file formats use 8 bits to store pixel values. When these are read into memory, MATLAB stores them as class uint8. For file formats that support 16-bit data, PNG and TIFF, MATLAB stores the images as class uint16.

Note For indexed images, imread always reads the colormap into a matrix of class double, even though the image array itself may be of class uint8 or uint16.

For example, this code reads a truecolor image into the MATLAB workspace as the variable RGB.

```
RGB = imread('football.jpg');
```

This code reads an indexed image with its associated colormap into the MATLAB workspace in two separate variables.

```
[X,map] = imread('trees.tif');
```

In these examples, imread infers the file format to use from the contents of the file. You can also specify the file format as an argument to imread. MATLAB supports many common graphics file formats, such as Microsoft Windows Bitmap (BMP), Graphics Interchange Format (GIF), Joint Photographic

Experts Group (JPEG), Portable Network Graphics (PNG), and Tagged Image File Format (TIFF) formats. For the latest information concerning the bit depths and/or image formats supported, see the reference page for the imread and imformats functions.

Reading Multiple Images from a Graphics File

MATLAB supports several graphics file formats, such as HDF and TIFF, that can contain multiple images. By default, imread imports only the first image from a file. To import additional images from the file, use the syntax supported by the file format.

For example, when used with TIFF files, you can use an index value with imread that identifies the image in the file you want to import. This example reads a series of 27 images from a TIFF file and stores the images in a four-dimensional array. You can use imfinfo to determine how many images are stored in the file.

```
mri = uint8(zeros(128,128,1,27)); % preallocate 4-D array
for frame=1:27
   [mri(:,:,:,frame),map] = imread('mri.tif',frame);
end
```

When a file contains multiple images that are related in some way, such as a time sequence, you can store the images in MATLAB as a 4-D array. All the images must be the same size. For more information, see "Multiframe Image Arrays" on page 2-14.

Writing a Graphics Image

The function imwrite writes an image to a graphics file in one of the supported formats. The most basic syntax for imwrite takes the image variable name and a filename. If you include an extension in the filename, MATLAB infers the desired file format from it. (For more information, see the reference entry for the imwrite function.)

This example loads the indexed image X from a MAT-file, clown.mat, that contains the data matrix and the associated colormap and then writes the image to a BMP file.

```
load clown whos
```

Name	Size	Bytes	Class
X	200x320		double array
caption	2x1	4	char array
map	81x3	1944	double array

Grand total is 64245 elements using 513948 bytes

```
imwrite(X,map,'clown.bmp')
```

Specifying Additional Format-Specific Parameters

When using imwrite with some graphics formats, you can specify additional parameters. For example, with PNG files, you can specify the bit depth as an additional parameter. This example writes an intensity image I to a 4-bit PNG file.

```
imwrite(I, 'clown.png', 'BitDepth',4);
```

This example writes an image A to a JPEG file, using an additional parameter to specify the compression quality parameter.

```
imwrite(A, 'myfile.jpg', 'Quality', 100);
```

For more information about the additional parameters associated with certain graphics formats, see the reference pages for imwrite.

Reading and Writing Binary Images in 1-Bit Format

In certain file formats, a binary image can be stored in a 1-bit format. If the file format supports it, MATLAB writes binary images as 1-bit images by default. When you read in a binary image in 1-bit format, MATLAB represents it in the workspace as a logical array.

This example reads in a binary image and writes it as a TIFF file. Because the TIFF format supports 1-bit images, the file is written to disk in 1-bit format.

```
BW = imread('text.png');
imwrite(BW,'test.tif');
```

To verify the bit depth of test.tif, call imfinfo and check the BitDepth field.

```
info = imfinfo('test.tif');
```

```
info.BitDepth
ans =
```

1

Note When writing binary files, MATLAB sets the ColorType field to 'grayscale'.

Determining the Storage Class of the Output File

imwrite uses the following rules to determine the storage class used in the output image.

Storage Class of Image	Storage Class of Output Image File
logical	If the output image file format specified supports 1-bit images, imwrite creates a 1-bit image file.
	If the output image file format specified does not support 1-bit images, such as JPEG, imwrite converts the image to a class uint8 intensity image.
uint8	If the output image file format specified supports unsigned 8-bit images, imwrite creates an unsigned 8-bit image file.
uint16	If the output image file format specified support unsigned 16-bit images (PNG or TIFF), imwrite creates an unsigned 16-bit image file.
	If the output image file format specified does not support 16-bit images, imwrite scales the image data to class uint8 and creates an 8-bit image file.
int16	Partially supported; depends on file format.

Storage Class of Image	Storage Class of Output Image File	
single	Partially supported; depends on file format.	
double	MATLAB scales the image data to uint8 and creates an 8-bit image file, because most image file formats use 8 bits.	

Querying a Graphics File

Note You can also get information interactively about an image displayed in the Image Tool — see "Getting Information about an Image" on page 3-29.

The imfinfo function enables you to obtain information about graphics files that are in any of the formats supported by the toolbox. The information you obtain depends on the type of file, but it always includes at least the following:

- Name of the file
- File format
- Version number of the file format
- File modification date
- File size in bytes
- Image width in pixels
- Image height in pixels
- Number of bits per pixel
- Image type: truecolor (RGB), intensity (grayscale), or indexed

See the reference entry for imfinfo for more information.

Converting Graphics File Formats

To change the graphics format of an image, use imread to read in the image and then save the. image with imwrite, specifying the appropriate format.

To illustrate, this example uses the imread function to read an image in bitmap (BMP) format into the workspace. The example then writes the bitmap image to a file using Portable Network Graphics (PNG) format.

```
bitmap = imread('mybitmap.bmp','bmp');
imwrite(bitmap, 'mybitmap.png', 'png');
```

For the specifics of which bit depths are supported for the different graphics formats, and for how to specify the format type when writing an image to file, see the reference entries for imread and imwrite.

Working with DICOM Files

The Image Processing Toolbox includes support for working with image data in Digital Imaging and Communications in Medicine (DICOM) format. Topics covered include:

- "Reading Image Data from a DICOM File" on page 2-21
- "Reading Metadata from a DICOM File" on page 2-22
- "Writing Image Data or Metadata to a DICOM File" on page 2-23, including information about anonymizing a DICOM file

To see an example that reads both the image data and metadata from a DICOM file, modifies the image data, and writes the modified data to a new DICOM file, see "Example: Creating a New Series" on page 2-25. The example shows how to use the dicomuid function to generate a DICOM unique identifier, which you need to create a new series.

Reading Image Data from a DICOM File

To read image data from a DICOM file, use the dicomread function. The dicomread function reads files that comply with the DICOM specification but can also read certain common noncomplying files.

This example reads an image from a sample DICOM file included with the toolbox.

```
I = dicomread('CT-MONO2-16-ankle.dcm');
```

To view the image data, use one of the toolbox image display functions, imshow or imtool. (Because the image data is signed 16-bit data, you must use the autoscaling syntax with either display function.)

```
imshow(I, 'DisplayRange',[])
```



Reading Metadata from a DICOM File

To read metadata from a DICOM file, use the dicominfo function.

The metadata in a DICOM files provides information, such as the size, dimensions, and bit depth of the image. In addition, the DICOM specification defines numerous other metadata fields that describe many other characteristics of the data, such as the modality used to create the data, the equipment settings used to capture the image, and information about the study.

In this example, dicominfo reads the metadata from a file, returning the information in a structure where every field in the structure is a specific piece of DICOM metadata.

```
Height: 512
BitDepth: 16
ColorType: 'grayscale'
SelectedFrames: []
FileStruct: [1x1 struct]
StartOfPixelData: 1140
MetaElementGroupLength: 192
FileMetaInformationVersion: [2x1 double]
MediaStorageSOPClassUID: '1.2.840.10008.5.1.4.1.1.7'
MediaStorageSOPInstanceUID: [1x50 char]
TransferSyntaxUID: '1.2.840.10008.1.2'
ImplementationClassUID: '1.2.840.113619.6.5'
```

You can use the metadata structure returned by dicominfo to specify the DICOM file you want to read using dicomread. For example, you can use this code to read metadata from the sample DICOM file and then pass the metadata to dicomread to read the image from the file.

```
info = dicominfo('CT-MONO2-16-ankle.dcm');
I = dicomread(info);
```

Writing Image Data or Metadata to a DICOM File

To write image data or metadata to a file in DICOM format, use the dicomwrite function. This example writes the image I to the DICOM file ankle.dcm.

```
dicomwrite(I, 'h:\matlab\tmp\ankle.dcm')
```

When you write image data to a DICOM file, dicomwrite includes the minimum set of metadata fields required by the type of DICOM information object (IOD) you are creating. dicomwrite supports three types of DICOM IODs with full validation and supports many other types (e.g. X-ray, radiotherapy, nuclear medicine) without validation.

- Secondary capture (default)
- Magnetic resonance
- Computed tomography

You can also specify the metadata you want to write to the file by passing to dicomwrite an existing DICOM metadata structure that you retrieved using dicominfo.

```
info = dicominfo('CT-MONO2-16-ankle.dcm');
I = dicomread(info);
dicomwrite(I,'h:\matlab\tmp\ankle.dcm',info)
```

In this case, the dicomwrite function writes the relevant information in the metadata structure info to the new DICOM file.

Note that the metadata written to the file is not identical to the metadata in the info structure. When writing metadata to a file, there are certain fields that dicomwrite must update. For example, dicomwrite must update the file modification date in the new file. To illustrate, compare the instance ID in the original metadata with the ID in the new file.

```
info.SOPInstanceUID
ans =
1.2.840.113619.2.1.2411.1031152382.365.1.736169244
```

Using dicominfo, read the metadata from the newly written file and check the file modification date.

```
info2 = dicominfo('h:\matlab\tmp\ankle.dcm');
info2.SOPInstanceUID
ans =
1.2.841.113411.2.1.2411.10311244477.365.1.63874544
```

Anonymizing a DICOM File

When using a DICOM file as part of a training set, blinded study, or a presentation, you might want to remove confidential patient information. To do this, use the dicomanon function.

The dicomanon function creates a new series and study values, changes some of the metadata, and then writes the file. For example, you could replace steps 4, 5, and 6 in the example in "Example: Creating a New Series" on page 2-25 with a call to the dicomanon function.

Example: Creating a New Series

When writing a modified image to a DICOM file, you might want to make the modified image the start of a new series. In the DICOM standard, images can be organized into series. When you write an image with metadata to a DICOM file, dicomwrite puts the image in the same series by default. To create a new series, you must assign a new DICOM unique identifier to the SeriesInstanceUID metadata field. This example illustrates this process:

1 Read an image from a DICOM file into the MATLAB workspace.

```
I = dicomread('CT-MONO2-16-ankle.dcm');
```

To view the image, use either of the toolbox display functions, imshow or imtool. Because the DICOM image data is signed 16-bit data, you must use the autoscaling syntax.

```
imtool(I, 'DisplayRange',[])
```



2 Read the metadata from the same DICOM file.

```
info = dicominfo('CT-MONO2-16-ankle.dcm');
```

To identify which series an image belongs to, view the value of the SeriesInstanceUID field.

```
info.SeriesInstanceUID
ans =
1.2.840.113619.2.1.2411.1031152382.365.736169244
```


3 You typically only start a new DICOM series when you modify the image in some way. This example removes all the text from the image.

The example finds the maximum and minimum values of all pixels in the image. The pixels that form the white text characters are set to the maximum pixel value.

```
max(I(:))
ans =
    4080
min(I(:))
ans =
    32
```

To remove these text characters, the example sets all pixels with the maximum value to the minimum value.

```
Imodified = I;
Imodified(Imodified == 4080) = 32;
View the processed image.
imshow(Imodified)
```



4 Generate a new DICOM unique identifier (UID) using the dicomuid function. You need a new UID to write the modified image as a new series.

uid = dicomuid

uid =

1.3.6.1.4.1.9590.100.1.1.56461980611264497732341403390561061497

dicomuid is guaranteed to generate a unique UID.

5 Set the value of the SeriesInstanceUID field in the metadata associated with the original DICOM file to the generated value.

info.SeriesInstanceUID = uid;

6 Write the modified image to a new DICOM file, specifying the modified metadata structure, info, as an argument. Because you set the SeriesInstanceUID value, the image you write is part of a new series.

dicomwrite(Imodified, 'ankle_newseries.dcm',info);

To verify this operation, view the image and the SeriesInstanceUID metadata field in the new file.

Image Arithmetic

Image arithmetic is the implementation of standard arithmetic operations, such as addition, subtraction, multiplication, and division, on images. Image arithmetic has many uses in image processing both as a preliminary step in more complex operations and by itself. For example, image subtraction can be used to detect differences between two or more images of the same scene or object.

You can do image arithmetic using the MATLAB arithmetic operators. The Image Processing Toolbox also includes a set of functions that implement arithmetic operations for all numeric, nonsparse data types. The toolbox arithmetic functions accept any numeric data type, including uint8, uint16, and double, and return the result image in the same format. The functions perform the operations in double precision, on an element-by-element basis, but do not convert images to double-precision values in the MATLAB workspace. Overflow is handled automatically. The functions saturate return values to fit the data type. For details, see "Image Arithmetic Saturation Rules" on page 2-28.

Note On Intel architecture processors, the image arithmetic functions can take advantage of the Intel Performance Primitives Library (IPPL), thus accelerating their execution time. IPPL is only activated, however, when the data passed to these functions is of specific classes. See the reference pages for the individual arithmetic functions for more information.

Image Arithmetic Saturation Rules

The results of integer arithmetic can easily overflow the data type allotted for storage. For example, the maximum value you can store in uint8 data is 255. Arithmetic operations can also result in fractional values, which cannot be represented using integer arrays.

MATLAB arithmetic operators and the Image Processing Toolbox arithmetic functions use these rules for integer arithmetic:

- Values that exceed the range of the integer type are saturated to that range.
- Fractional values are rounded.

For example, if the data type is uint8, results greater than 255 (including Inf)
are set to 255. The following table lists some additional examples.

Result	Class	Truncated Value
300	uint8	255
-45	uint8	0
10.5	uint8	11

Nesting Calls to Image Arithmetic Functions

You can use the image arithmetic functions in combination to perform a series of operations. For example, to calculate the average of two images,

$$C = \frac{A+B}{2}$$

You could enter

```
I = imread('rice.png');
I2 = imread('cameraman.tif');
K = imdivide(imadd(I,I2), 2); % not recommended
```

When used with uint8 or uint16 data, each arithmetic function rounds and saturates its result before passing it on to the next operation. This can significantly reduce the precision of the calculation. A better way to perform this calculation is to use the imlincomb function. imlincomb performs all the arithmetic operations in the linear combination in double precision and only rounds and saturates the final result.

```
K = imlincomb(.5,I,.5,I2); % recommended
```


Coordinate Systems

Locations in an image can be expressed in various coordinate systems, depending on context. This section discusses the two main coordinate systems used in the Image Processing Toolbox and the relationship between them. These two coordinate systems are described in

- "Pixel Coordinates"
- "Spatial Coordinates" on page 2-31

Pixel Coordinates

Generally, the most convenient method for expressing locations in an image is to use pixel coordinates. In this coordinate system, the image is treated as a grid of discrete elements, ordered from top to bottom and left to right, as illustrated by the following figure.



The Pixel Coordinate System

For pixel coordinates, the first component r (the row) increases downward, while the second component c (the column) increases to the right. Pixel coordinates are integer values and range between 1 and the length of the row or column.


There is a one-to-one correspondence between pixel coordinates and the coordinates MATLAB uses for matrix subscripting. This correspondence makes the relationship between an image's data matrix and the way the image is displayed easy to understand. For example, the data for the pixel in the fifth row, second column is stored in the matrix element (5,2).

Spatial Coordinates

In the pixel coordinate system, a pixel is treated as a discrete unit, uniquely identified by a single coordinate pair, such as (5,2). From this perspective, a location such as (5,3,2,2) is not meaningful.

At times, however, it is useful to think of a pixel as a square patch. From this perspective, a location such as (5.3,2.2) *is* meaningful, and is distinct from (5,2). In this spatial coordinate system, locations in an image are positions on a plane, and they are described in terms of x and y (not r and c as in the pixel coordinate system).

The following figure illustrates the spatial coordinate system used for images. Notice that y increases downward.



The Spatial Coordinate System

This spatial coordinate system corresponds closely to the pixel coordinate system in many ways. For example, the spatial coordinates of the center point of any pixel are identical to the pixel coordinates for that pixel.

There are some important differences, however. In pixel coordinates, the upper left corner of an image is (1,1), while in spatial coordinates, this location by default is (0.5,0.5). This difference is due to the pixel coordinate system's being discrete, while the spatial coordinate system is continuous. Also, the upper left corner is always (1,1) in pixel coordinates, but you can specify a nondefault

origin for the spatial coordinate system. See "Using a Nondefault Spatial Coordinate System" on page 2-32 for more information.

Another potentially confusing difference is largely a matter of convention: the order of the horizontal and vertical components is reversed in the notation for these two systems. As mentioned earlier, pixel coordinates are expressed as (r,c), while spatial coordinates are expressed as (x,y). In the reference pages, when the syntax for a function uses r and c, it refers to the pixel coordinate system. When the syntax uses x and y, it refers to the spatial coordinate system.

Using a Nondefault Spatial Coordinate System

By default, the spatial coordinates of an image correspond with the pixel coordinates. For example, the center point of the pixel in row 5, column 3 has spatial coordinates x=3, y=5. (Remember, the order of the coordinates is reversed.) This correspondence simplifies many of the toolbox functions considerably. Several functions primarily work with spatial coordinates rather than pixel coordinates, but as long as you are using the default spatial coordinate system, you can specify locations in pixel coordinates.


In some situations, however, you might want to use a nondefault spatial coordinate system. For example, you could specify that the upper left corner of an image is the point (19.0,7.5), rather than (0.5,0.5). If you call a function that returns coordinates for this image, the coordinates returned will be values in this nondefault spatial coordinate system.

To establish a nondefault spatial coordinate system, you can specify the XData and YData image properties when you display the image. These properties are two-element vectors that control the range of coordinates spanned by the image. By default, for an image A, XData is [1 size(A,2)], and YData is [1 size(A,1)].

For example, if A is a 100 row by 200 column image, the default XData is [1 200], and the default YData is [1 100]. The values in these vectors are actually the coordinates for the center points of the first and last pixels (not the pixel edges), so the actual coordinate range spanned is slightly larger; for instance, if XData is [1 200], the x-axis range spanned by the image is [0.5 200.5].

These commands display an image using nondefault XData and YData.

```
A = magic(5);
x = [19.5 23.5];
y = [8.0 12.0];
image(A,'XData',x,'YData',y), axis image, colormap(jet(25))
```



For information about the syntax variations that specify nondefault spatial coordinates, see the reference page for imshow.

Displaying and Exploring Images

This chapter describes the image display and exploration tools provided by the Image Processing Toolbox.

Overview (p. 3-2)	Comparison of toolbox display functions	
Using imshow to Display Images (p. 3-4)	How to use the imshow display function	
Using the Image Tool to Explore Images (p. 3-8)	How to use the Image Tool integrated display and exploration environment	
Using Image Tool Navigation Aids (p. 3-16)	Image Tool navigation aids including the Overview tool, panning, and zooming	
Getting Information about the Pixels in an Image $(p. 3-22)$	Image Tool pixel information tools, including the Pixel Region tool and the Pixel Information tool	
Getting Information about an Image (p. 3-29)	Image Tool's Image Information tool	
Adjusting the Contrast and Brightness of an Image (p. 3-31)	Image Tool's Adjust Contrast tool	
Viewing Multiple Images (p. 3-41)	Using imshow and imtool to view multiple images	
Displaying Different Image Types (p. 3-45)	Using imshow and imtool with each image type	
Special Display Techniques (p. 3-51)	Using the colorbar, montage, and warp functions	
Printing Images (p. 3-56)	Print images from imshow and the Image Tool	
Setting Toolbox Display Preferences (p. 3-58)	Setting toolbox preferences	

Overview

The Image Processing Toolbox includes two display functions, imshow and imtool. Both functions work within the Handle Graphics architecture: they create an image object and display it in an axes object contained in a figure object. The toolbox functions automatically set the values of certain figure, axes, and image object properties to control how the image data is displayed — see "Understanding Handle Graphics Object Property Settings" on page 3-2.

imshow is the toolbox's fundamental image display function. Use imshow when you want to display any of the different image types supported by the toolbox, such as intensity (grayscale), truecolor (RGB), binary, and indexed. For more information, see "Using imshow to Display Images" on page 3-4. The imshow function is also a key building block for image applications you might want to create using the toolbox modular tools. For more information, see Chapter 4, "Building GUIs with Modular Tools."

The other toolbox display function, imtool, launches the Image Tool which presents an integrated environment for displaying images and performing some common image processing tasks. The Image Tool provides all the image display capabilities of imshow but also provides access to several other tools for navigating and exploring images, such as scroll bars, the Pixel Region tool, Image Information tool, and the Adjust Contrast tool. For more information, see "Using the Image Tool to Explore Images" on page 3-8.

In general, using the toolbox functions to display images is preferable to using the MATLAB image display functions: image and imagesc. The toolbox functions are easier to use and are optimized for displaying images.

Understanding Handle Graphics Object Property Settings

When you display an image, imshow and imtool set the Handle Graphics properties that control how the image is displayed. The following table lists the relevant properties and their settings for each image type. The table uses standard toolbox terminology to refer to the various image types: X represents an indexed image, I represents an intensity image, BW represents a binary image, and RGB represents an RGB (or truecolor) image.

Note Both imshow and imtool can perform automatic scaling of image data. When called with the syntax imshow(I, 'DisplayRange',[]), and similarly for imtool, the functions set the axes CLim property to $[\min(I(:))$ max(I(:))]. CDataMapping is always scaled for intensity images, so that the value $\min(I(:))$ is displayed using the first colormap color, and the value $\max(I(:))$ is displayed using the last colormap color.

Handle Graphics Property	Indexed Images	Intensity (Grayscale) Images	Binary Images	Truecolor (RGB) Images
CData (Image)	Set to the data in X	Set to the data in I	Set to data in BW	Set to data in RGB
CDataMapping (Image)	Set to 'direct'	Set to 'scaled'	Set to 'direct'	Ignored when CData is 3-D
CLim (Axes)	Does not apply	double: [0 1] uint8: [0 255] uint16: [0 65535]	Set to [0 1]	Ignored when CData is 3-D
Colormap (Figure)	Set to data in map	Set to grayscale colormap	Set to a grayscale colormap whose values range from black to white	Ignored when CData is 3-D

Using imshow to Display Images

You can use the imshow function to display an image that has already been imported into the MATLAB workspace or to display an image stored in a graphics file. For example, this code reads an image into the MATLAB workspace and then displays it in a MATLAB figure window.

```
moon = imread('moon.tif');
imshow(moon);
```

The imshow function displays the image in a MATLAB figure window, as shown in the following figure.




Image Displayed in a Figure Window by imshow

```
The imshow filename syntax imshow('moon.tif');
```

can be useful for scanning through images. Note, however, that when you use this syntax, the image data is not stored in the MATLAB workspace. If you want to bring the image into the workspace, you must use the getimage function, which retrieves the image data from the current Handle Graphics image object. For example,

```
moon = getimage;
```

assigns the image data from moon.tif to the variable moon if the figure window in which it is displayed is currently active.

For more information about using imshow, see these additional topics.

- "Specifying the Initial Image Magnification" on page 3-5
- "Controlling the Appearance of the Figure" on page 3-6

For more information about using imshow to display the various image types supported by the toolbox, see "Displaying Different Image Types" on page 3-45.

Specifying the Initial Image Magnification

By default, imshow attempts to display an image in its entirety at 100% magnification (one screen pixel for each image pixel). However, if an image is too large to fit in a figure window on the screen at 100% magnification, imshow scales the image to fit onto the screen and issues a warning message.

To override the default initial magnification behavior for a particular call to imshow, specify the InitialMagnification parameter. For example, to view an image at 150% magnification, use this code.

```
pout = imread('pout.tif');
imshow(pout, 'InitialMagnification', 150)
```

imshow attempts to honor the magnification you specify. However, if the image does not fit on the screen at the specified magnification, imshow scales the image to fit and issues a warning message. You can also specify the text string 'fit' as the initial magnification value. In this case, imshow scales the image to fit the current size of the figure window.

You can also change the default initial magnification behavior of imshow by setting the ImshowInitialMagnification toolbox preference. To make this preference persist between sessions, include the command to set the preference

in your startup.m file. To learn more about toolbox preferences, see "Setting the Value of Toolbox Preferences" on page 3-59.

When imshow scales an image, it uses interpolation to determine the values for screen pixels that do not directly correspond to elements in the image matrix. For more information, see "Interpolation" on page 5-3.

Controlling the Appearance of the Figure

By default, when imshow displays an image in a figure, it surrounds the image with a gray border and does not include a visible axes box. If you want to display an image without the gray border or include a visible axes box with tick labels, you must set toolbox preferences. (For more information about setting toolbox preferences, see "Setting Toolbox Display Preferences" on page 3-58.)

For example, to display an image without a border, set the ImshowBorder preference to 'tight'. By default, this preference is set to 'loose', which causes the border to be included. This code sets the preference to suppress the border and then displays an image.

```
iptsetpref('ImshowBorder','tight')
imshow('moon.tif')
```

The following figure shows the same image displayed with and without the border. Note that the image is the same size but the figure window takes up less space on your screen.




Image Displayed With and Without a Border

Using the Image Tool to Explore Images

The Image Tool is an image display tool that also provides access to several other related tools, such as, the Pixel Region tool, Image Information tool, and the Adjust Contrast tool. The Image Tool also provides navigation aids that can help explore large images, such as, scroll bars, the Overview tool, pan tool, and zoom buttons. The Image Tool presents an integrated environment for displaying images and performing common image processing tasks.

For example, this code reads an image into the MATLAB workspace and then displays it in the Image Tool.

```
moon = imread('moon.tif');
imtool(moon);
```

The following figure shows the image displayed in the Image Tool, with all of the related tools active. For more information about using the Image Tool and related tools, see the topics in the following list.

- "Opening the Image Tool" on page 3-10
- "Specifying the Initial Image Magnification" on page 3-11
- "Closing the Image Tool" on page 3-14
- "Specifying the Colormap" on page 3-11
- \bullet "Importing Image Data from the Workspace" on page 3-13
- "Exporting the Image to the Workspace" on page 3-14
- "Closing the Image Tool" on page 3-14
- "Printing the Image in the Image Tool" on page 3-15
- "Using Image Tool Navigation Aids" on page 3-16
- "Getting Information about the Pixels in an Image" on page 3-22.
- "Getting Information about an Image" on page 3-29
- "Adjusting the Contrast and Brightness of an Image" on page 3-31
- \bullet "Displaying Different Image Types" on page 3-45




Image Tool and Related Tools

Opening the Image Tool

To start the Image Tool, use the imtool function. Once started, you can launch another Image Tool from within an Image Tool by using the **New** option from the **File** menu. The following shows some common imtool syntaxes. For complete information, see the imtool function reference page.

When called with no arguments,

```
imtool
```

imtool opens an empty Image Tool window. You can bring an image into the Image Tool by using the **Import from Workspace** option from the **File** menu—see "Importing Image Data from the Workspace" on page 3-13.

You can also call imtool specifying the name of the MATLAB workspace variable that contains image data.

```
moon = imread('moon.tif');
imtool(moon)
```

Alternatively, you can specify the name of the graphics file containing the image.

```
imtool('moon.tif');
```

This syntax can be useful for scanning through graphics files. Note, however, that when you use this syntax, the image data is not stored in a MATLAB workspace variable. To bring the image displayed in the Image Tool into the workspace, you must use the <code>getimage</code> function or the <code>Export</code> from <code>Workspace</code> option from the Image Tool <code>File</code> menu — see "Exporting the Image to the Workspace" on page 3-14.

Specifying the Initial Image Magnification

Like imshow, the imtool function attempts to display an image in its entirety at 100% magnification (one screen pixel for each image pixel). Unlike imshow, imtool always honors the specified numeric magnification, showing only a portion of the image if it is too big to fit in a figure on the screen and adding scroll bars to allow navigation to parts of the image that are not currently visible. If the specified magnification would make the image too large to fit on the screen, imtool scales the image to fit, without issuing a warning. This is the default behavior, specified by the imtool 'InitialMagnification' parameter value 'adaptive'.

To override this default initial magnification behavior for a particular call to imtool, specify the InitialMagnification parameter. For example, to view an image at 150% magnification, use this code.

```
pout = imread('pout.tif');
imtool(pout, 'InitialMagnification', 150)
```

You can also specify the text string 'fit' as the initial magnification value. In this case, imtool scales the image to fit the default size of a figure window.

You can also change the default initial magnification behavior of imtool by setting the ImtoolInitialMagnification toolbox preference. The magnification value you specify affects every call to imtool for the current MATLAB session. To make this preference persist between sessions, include the command to set the preference in your startup.m file. To learn more about toolbox preferences, see "Setting the Value of Toolbox Preferences" on page 3-59.

When imtool scales an image, it uses interpolation to determine the values for screen pixels that do not directly correspond to elements in the image matrix. For more information, see "Interpolation" on page 5-3.

Specifying the Colormap


A colormap is a matrix that can have any number of rows, but must have three columns. Each row in the colormap is interpreted as a color, with the first element specifying the intensity of red, the second green, and the third blue.

To specify the color map used to display an indexed image or an intensity image in the Image Tool, select the **Choose Colormap** option on the **Tools** menu. This activates the Choose Colormap tool, shown below. Using this tool you can select

one of the MATLAB colormaps or select a colormap variable from the MATLAB workspace.

When you select a colormap, the Image Tool executes the colormap function you specified and updates the image displayed. You can edit the colormap command in the **Evaluate Colormap** text box; for example, you can change the number of entries in the colormap (default is 256). You can enter your own colormap function in this field. Press **Enter** to execute the command.

When you choose a colormap, the image updates to use the new map. If you click **OK**, the Image Tool applies the colormap and closes the Choose Colormap tool. If you click **Cancel**, the image reverts to the prevous colormap.




Choose Colormap Tool

Importing Image Data from the Workspace

To import image data from the MATLAB workspace into the Image Tool, use the **Import from Workspace** option on the Image Tool **File** menu. In the dialog box, shown below, you select the workspace variable that you want to import into the workspace.

The following figure shows the **Import from Workspace** dialog box. You can use the Filter menu to limit the images included in the list to certain image types, i.e., binary, intensity, RGB, or indexed.



Import from Workspace Dialog Box

Exporting the Image to the Workspace

To export the image displayed in the Image Tool to the MATLAB workspace, you can use the **Export to Workspace** option on the Image Tool **File** menu. In the dialog box, shown below, you specify the name you want to assign to the variable in the workspace.



Export Image to Workspace Dialog Box

You can also use the getimage function to bring image data from the Image Tool into the MATLAB workspace.

The getimage function retrieves the image data (CData) from the current Handle Graphics image object. Because, by default, the Image Tool does not make handles to objects visible, you must use the toolbox function image to get a handle to the image axes displayed in the Image Tool. For example,

```
moon = getimage(imgca);
```

assigns the image data from moon.tif to the variable moon if the figure window in which it is displayed is currently active.

Closing the Image Tool

To close the Image Tool window, use the **Close** button in the window title bar or select the **Close** option from the Image Tool **File** menu. You can also use the imtool function to return a handle to the Image Tool and use the handle to close the Image Tool. When you close the Image Tool, any related tools that are currently open also close.

Because the Image Tool does not make the handles to its figure objects visible, the Image Tool does not close when you call the close all command. If you want to close multiple Image Tools, use the imtool close all syntax or select **Close all** from the Image Tool **File** menu.

Printing the Image in the Image Tool

To print the image displayed in the Image Tool, select the **Print to Figure** option from the **File** menu. The Image Tool opens another figure window and displays the image. Use the **Print** option on the **File** menu of this figure window to print the image. See "Printing Images" on page 3-56 for more information.

Using Image Tool Navigation Aids

If an image is large or viewed at a large magnification, the Image Tool displays only a portion of the entire image. When this occurs, the Image Tool includes scroll bars to allow navigation around the image. In some cases, scroll bars might not be sufficient. To help navigate large images, the Image Tool includes the following navigation aids:

- Overview tool Provides a view of the entire image to help you understand which portion of the image is currently displayed in the Image Tool. See "Overview Navigation" on page 3-16 for more information.
- Pan tool Lets you click and grab the image displayed and move it in the Image Tool. See "Panning the Image Displayed in the Image Tool" on page 3-19 for more information.
- Zoom tools Lets you zoom in or out on the image. See "Zooming In and Out on an Image" on page 3-19 for more information.
- Magnification Box Lets you specify the exact magnification of the image.
 See "Specifying the Magnification of the Image" on page 3-20 for more information.

Overview Navigation

To get an overview of the image displayed in the Image Tool, use the Overview tool. The Overview tool displays a view of the entire image, scaled to fit, in a separate window. Superimposed over this view of the image is a rectangle, called the *detail rectangle*. The detail rectangle shows which part of the image is currently visible in the Image Tool window. You can change the portion of the image visible in the Image Tool by moving the detail rectangle over the image in the Overview tool.

For example, view an image in the Image Tool.

```
imtool('moon.tif')
```

When the Image Tool starts, the Overview tool also starts, by default. You can also start the Overview tool by clicking the Overview button in the Image Tool toolbar or by selecting the **Overview** option from the **Tools** menu in the Image Tool. The following figure shows the Image Tool with the Overview tool. For more information about using the Overview tool, see these topics:

• "Using the Overview Tool" on page 3-17

- "Specifying the Color of the Detail Rectangle" on page 3-18
- "Getting the Position and Size of the Detail Rectangle" on page 3-18
- "Printing the View of the Image in the Overview Tool" on page 3-18




Image Tool with Overview Tool

Using the Overview Tool

To use the Overview tool to explore an image displayed in the Image Tool, follow this procedure:

1 Start the Overview tool by clicking the Overview button ☐ in the Image Tool toolbar or by selecting Overview from the **Tools** menu. The Overview

tool opens in a separate window containing a view the entire image, scaled to fit.

The Image Tool opens the Overview tool, by default. If the Overview tool is already active, clicking the Overview button brings the tool to the front of the windows open on your screen.

- 2 Using the mouse, move the cursor into the detail rectangle. The cursor changes to the fleur shape, .
- **3** Press and hold the mouse button to drag the detail rectangle anywhere on the image. The Image Tool updates the view of the image to make the specified region visible.

Specifying the Color of the Detail Rectangle

By default, the color of the detail rectangle in the Overview tool is blue. You might want to change the color of the rectangle to achieve better contrast with the predominant color of the underlying image. To do this, right-click anywhere inside the boundary of the detail rectangle and select a color from the **Set Rectangle Color** option on the context menu.

Getting the Position and Size of the Detail Rectangle

To get the current position and size of the detail rectangle, right-click anywhere inside it and select **Copy Position** from the context menu. You can also access this option from the **Edit** menu of the Overview tool.

This option copies the position information to the clipboard. The position information is a vector of the form [xmin ymin width height]. To paste this position vector into the MATLAB workspace or another application, right-click and select **Paste** from the context menu.

Printing the View of the Image in the Overview Tool

You can print the view of the image displayed in the Overview tool. Select the **Print to Figure** option from the Overview Tool **File** menu. See "Printing Images" on page 3-56 for more information.

Panning the Image Displayed in the Image Tool

To change the portion of the image displayed in the Image Tool, you can use the Drag Image to Pan button to move the image displayed in the window. This is called *panning* the image.

To pan an image displayed in the Image Tool,

- 1 Click the Drag image to pan button in the toolbar or select **Pan** from the **Tools** menu.
- **2** Move the cursor over the image in the Image Tool, using the mouse. The cursor changes to an open-hand shape, $\langle \uparrow \rangle$.
- **3** Press and hold the mouse button and drag the image in the Image Tool. When you drag the image, the cursor changes to the closed-hand shape $\{\gamma\}$.
- **4** To leave Pan mode, click the Drag image to pan button again to deselect it.

Note As you pan the image in the Image Tool, the Overview tool updates the position of the detail rectangle — see "Overview Navigation" on page 3-16.

Zooming In and Out on an Image

To enlarge an image to get a closer look or shrink an image to see the whole image in context, use the Zoom buttons on the toolbar. (You can also zoom in or out on an image by changing the magnification — see "Specifying the Magnification of the Image" on page 3-20.)

To zoom in or zoom out on an image,

1 Click the appropriate magnifying glass button in the Image Tool toolbar or select the **Zoom In** or **Zoom Out** option in the **Tools** menu.



2 Move the cursor over the image you want to zoom in or out on, using the mouse. The cursor changes to the appropriate magnifying glass icon. With each click, the Image Tool changes the magnification of the image, centering the new view of the image on the spot where you clicked.

When you zoom in or out on an image, the magnification value displayed in the magnification edit box changes and the **Overview** window updates the position of the detail rectangle.

3 To leave zoom mode, click the active zoom button again to deselect it.

Specifying the Magnification of the Image

To enlarge an image to get a closer look or to shrink an image to see the whole image in context, you can use the magnification edit box, shown in the following figure. (You can also use the Zoom buttons to enlarge or shrink an image. See "Zooming In and Out on an Image" on page 3-19 for more information.)




Image Tool Magnification Edit Box and Menu

To change the magnification of an image,

- **1** Move the cursor into the magnification edit box. The cursor changes to the text entry cursor.
- **2** Type a new value in the magnification edit box and press **Enter.** The Image Tool changes the magnification of the image and displays the new view in the window.

You can also specify a magnification by clicking the menu associated with the magnification edit box and selecting from a list of preset magnifications. If you choose the **Fit to Window** option, the Image Tool scales the image so that the entire image is visible.

Getting Information about the Pixels in an Image

Often, you need to get information about the pixels in an image such as their location and value. The Image Tool provides several ways to get this information, including:

- Pixel Information tool Displays the location and value of the pixel under the cursor in the lower left corner of the Image Tool window. See "Determining the Value of Individual Pixels" on page 3-22 for more information.
- Display Range tool Displays the display range of the image in the lower right corner of the Image Tool window. See "Getting the Display Range of an Image" on page 3-24 for more information.
- Pixel Region tool Displays an extreme close-up view of the pixels in a specific region of an image. See "Viewing Pixel Values with the Pixel Region Tool" on page 3-25 for more information.


Determining the Value of Individual Pixels

The Image Tool provides information about the location and value of individual pixels in an image. This information is displayed in the Pixel Information tool at the bottom left corner of the Image Tool window. The pixel value and location information represent the pixel under the current location of the cursor. The Image Tool updates this information as you move the cursor over the image.

For example, view an image in the Image Tool.

```
imtool('moon.tif')
```

The following figure shows the Image Tool with pixel location and value displayed in the Pixel Information tool. For more information, see "Saving the Pixel Value and Location Information" on page 3-23.



Pixel Information in Image Tool

Saving the Pixel Value and Location Information

To save the pixel location and value information displayed, right-click a pixel in the image and choose the **Copy pixel info** option. The Image Tool copies the *x*- and *y*-coordinates and the pixel value to the clipboard.

To paste this position vector into the MATLAB workspace or another application, right-click and select **Paste** from the context menu.

Getting the Display Range of an Image


The Image Tool provides information about the display range of pixels in an intensity image. The display range is the value of the axes CLim property, which controls the mapping of image CData to the figure colormap. CLim is a two-element vector [cmin cmax] specifying the CData value to map to the first color in the colormap (cmin) and the CData value to map to the last color in the colormap (cmax). Data values in between are linearly scaled.

The Image Tool displays this information in the Display Range tool at the bottom right corner of the window. The Image Tool does not show the display range for indexed, RGB, or binary images.

For example, view an image in the Image Tool.

```
imtool('moon.tif')
```

The following figure shows the Image Tool displaying the image with display range information.



Display Range Information in Image Tool

Viewing Pixel Values with the Pixel Region Tool

To view the values of pixels in a specific region of an image displayed in the Image Tool, use the Pixel Region tool. The Pixel Region tool superimposes a rectangle, called the *pixel region rectangle*, over the image displayed in the Image Tool. This rectangle defines the group of pixels that are displayed, in extreme close-up view, in the Pixel Region tool window.

For example, view an image in the Image Tool

```
imtool('moon.tif')
```

Start the Pixel Region tool by clicking the Pixel Region button in the Image Tool toolbar or by selecting the **Pixel Region** option from the **Tools** menu in the Image Tool. The following figure shows the Image Tool with the Pixel Region tool. For more information about using the Pixel Region tool, see these additional topics:

- "Selecting a Region" on page 3-26
- "Customizing the View" on page 3-27
- "Determining the Location of the Pixel Region Rectangle" on page 3-28
- "Printing the View of the Image in the Pixel Region Tool" on page 3-28




Image Tool with Pixel Region Tool and Pixel Region Rectangle

Selecting a Region

To examine pixels in specific regions of an image, perform this procedure:

1 Start the Pixel Region tool by clicking the Pixel Region button in the Image Tool toolbar or by selecting the **Pixel Region** option from the **Tools** menu. The Image Tool displays the pixel region rectangle in the center of the target image and opens the Pixel Region tool.


Note Scrolling the image can move the pixel region rectangle off the part of the image that is currently displayed. To bring the pixel region rectangle back to the center of the part of the image that is currently visible, click the Pixel Region button again. For help finding the Pixel Region tool in large images, see "Determining the Location of the Pixel Region Rectangle" on page 3-28.

- **2** Using the mouse, position the pointer over the pixel region rectangle. The pointer changes to the fleur shape, ♠ .
- **3** Click the left mouse button and drag the pixel region rectangle to any part of the image. As you move the pixel region rectangle over the image, the Pixel Region tool updates the pixel values displayed. You can also move the pixel region rectangle by moving the scroll bars in the Pixel Region tool window.

Customizing the View

The pixel region rectangle defines the group of pixels that are displayed in the Pixel Region tool. To view a larger region, grab any side of the Pixel Region tool figure window and resize it, or use the zoom tools in the Pixel Region toolbar to zoom in or out on the image.

The Pixel Region tool displays the pixels at high magnification, overlaying each pixel with its numeric value. For RGB images, this information includes three numeric values, one for each band of the image. For indexed images, this information includes the index value and the associated RGB value. If you would rather not see the numeric values in the display, go to the Pixel Region tool **Edit** menu and deselect the **Superimpose Pixel Values** option.



Pixel Region Tool Edit Menu


Determining the Location of the Pixel Region Rectangle

To determine the current location of the pixel region in the target image, you can use the pixel information given at the bottom of the tool. This information includes the x- and y-coordinates of pixels in the target image coordinate system.

You can also retrieve the current position of the pixel region rectangle by selecting the **Copy Position** option from the Pixel Region tool **Edit** menu. This option copies the position information to the clipboard. The position information is a vector of the form [xmin ymin width height].

To paste this position vector into the MATLAB workspace or another application, right-click and select **Paste** from the context menu.

The following figure shows these components of the Pixel Region tool.



Pixel Region Rectangle Location Information

Printing the View of the Image in the Pixel Region Tool

You can print the view of the image displayed in the Pixel Region tool. Select the **Print to Figure** option from the Pixel Region Tool **File** menu. See "Printing Images" on page 3-56 for more information.

Getting Information about an Image

To get information about the image displayed in the Image Tool, use the Image Information tool. The Image Information tool can provide two types of information about an image:

- Basic information Includes width, height, class, and image type. For intensity (grayscale) and indexed images, this information also includes the minimum and maximum intensity values.
- Image metadata Displays all the metadata from the graphics file that contains the image. This is the same information returned by the imfinfo function or the dicominfo function.

Note The Image Information tool can display image metadata only when you specify the filename containing the image to Image Tool, e.g. imtool('moon.tif').

For example, view an image in the Image Tool

```
imtool('moon.tif')
```

Start the Image Information tool by clicking the Image information button in the Image Tool toolbar or by selecting the **Image Information** option from the **Tools** menu in the Image Tool.

The following figure shows the Image Tool with the Image Information tool. In the figure, the Image Information tool displays both basic image information and image metadata.




Image Tool with Image Information Tool

Adjusting the Contrast and Brightness of an Image

To adjust the contrast or brightness of an image displayed in the Image Tool, use the Adjust Contrast tool. The Adjust Contrast tool provides an interactive way to adjust the contrast and brightness of an image by manipulating the display range of the image.

The Adjust Contrast tool displays a histogram of the image that is overlaid with a red rectangular box, called a *window*. The histogram represents the *dynamic range* of the image, i.e., the full grayscale resolution possible given the image storage class. The window represents the *display range* of the image, i.e., the actual range of pixel values in the image. An image where grayscale values in the display range do not take full advantage of the dynamic range have a dull, washed out, low-contrast look. By changing the size of the window, you can make the display range take better advantage of the full dynamic range of the image. The Adjust Contrast tool also provides a way to adjust contrast and brightness using the mouse — see "Using the Window/Level Tool" on page 3-37.

For example, view an image in the Image Tool

```
imtool('moon.tif')
```

Start the Adjust Contrast tool by clicking the Adjust Contrast button on in the Image Tool toolbar, or by selecting the **Adjust Contrast** option from the **Tools** menu in the Image Tool.

The following figure shows the Image Tool with the Adjust Contrast tool. For more information, see these additional topics:

- "Understanding Contrast Adjustment" on page 3-32
- "Adjusting Contrast and Brightness" on page 3-34
- "Autoscaling" on page 3-39




Image Tool with Adjust Contrast Tool


Understanding Contrast Adjustment

An image lacks contrast when there are no sharp differences between black and white. Brightness refers to the overall lightness or darkness of an image.

To change the contrast or brightness of an image, the Adjust Contrast tool performs *contrast stretching*. In this process, pixel values below a specified value are mapped to black and pixel values above a specified value are mapped to white. The result is a linear mapping of a subset of pixel values to the entire range of display intensities (dynamic range). This produces an image of higher

contrast by darkening pixels whose value is below a specified value and lightening pixels whose value is above a specified value. The Adjust Contrast tools adjust brightness by moving this window over the display range, without changing its size. In this way, the pixel values map to lighter or darker intensities.

The following figure shows this mapping. Note that the lower limit and upper limit mark the boundaries of the window, displayed graphically as the red box in the Adjust Contrast tool.



Display Range to Dynamic Range Mapping

The Adjust Contrast tool accomplishes this contrast stretching by modifying the CLim property of the axes object that contains the image. The CLim property controls the mapping of image pixel values to display intensities.

By default, the Image Tool sets the CLim property to the entire dynamic range available to the data type. For example, the dynamic range of an image of class uint8 is from 0 to 255. When you use the Adjust Contrast tool, you change the contrast in the image by changing this mapping between image pixel values (display range) and the dynamic range. You create a window over the range that defines which pixels in the image map to the black in the dynamic range by shrinking the range from the bottom up.

Adjusting Contrast and Brightness

The Adjust Contrast tool provides several ways you can change the size of the window to change the mapping between pixel values and display intensities. This example illustrates these capabilities.

1 View an image in the Image Tool. This example opens the image pout.tif, which is a low-contrast image.

```
imtool('pout.tif')
```

2 Start the Adjust Contrast tool by clicking the Adjust Contrast button in the Image Tool toolbar, or by selecting Adjust Contrast from the **Tools** menu in the Image Tool.

The following figure shows the image displayed in the Image Tool with the Adjust Contrast tool open in a separate window. In the figure, note how pixel values in the image histogram are clustered in the middle of the dynamic range. Note that the display range, shown in the lower right corner of the Image Tool, is the full dynamic range of the image.





Image with Default Pixel Value to Display Intensity Mapping

3 Adjust the contrast by changing the size of the window overlaid on the image histogram. The Adjust Contrast tool provides several ways to change this window:

- By grabbing one of the red handles on the right and left edges of the window and dragging it. If you shrink the window from the left, the image becomes darker. If you shrink the window from the right, the image becomes lighter.
- By specifying values in the Minimum value and Maximum value fields and pressing Enter.
- By clicking the dropper button associated with the minimum or maximum value fields. When you do this, the cursor becomes an eye dropper shape.
 Position this cursor over the pixel in the image you want to be the minimum (or maximum) value and click the mouse button.
- By specifying values in the Window Width and Window Center fields and pressing Enter. These values provide another way to specify the size of the window.

If, while making interactive adjustments to contrast and brightness, you want to return the image to its original state, click the **Reset Image** button. The following figure shows the Adjust Contrast tool with the window resized. For information about adjusting the contrast using the **Auto Scale** button, see "Autoscaling" on page 3-39.



Adjust Contrast tool with Window Resized

4 Adjust the brightness by moving the window to the left or right, without changing its size. Move the cursor anywhere in the window, click and drag the window.

The following figure shows the pout.tif image after contrast adjustment. Note that the Image Tool updates the display range values displayed in the lower right corner of the Image Tool window.



Contrast Adjusted Image

Using the Window/Level Tool

The Adjust Contrast tool also enables contrast and brightness adjustment by clicking and dragging the mouse. In medical applications, this type of interactivity is often called adjusting the window/level.

When you start the Adjust Contrast tool and move the cursor over the image displayed in the Image Tool, the cursor changes shape to the Window/Level cursor . The following table summarizes the mouse motion.

Mouse Motion		Description	
Horizontally to the left	•	Shrinks the window from both sides	
Horizontally to the right		Expands the window from both sides	
Vertically up	†	Moves the window to the right over the histogram, increasing brightness.	
Vertically down	↓	Moves the window to the left over the image histogram, decreasing brightness.	

The following example shows how to use the window/level capability to improve the contrast of an image.

1 Reads an image from a sample DICOM file included with the toolbox.

```
I = dicomread('CT-MONO2-16-ankle.dcm');
```

2 View the image data using the Image Tool. Because the image data is signed 16-bit data, this example uses the autoscaling syntax.

```
imshow(I, 'DisplayRange',[])
```




- **3** Start the Adjust Contrast tool by clicking the Adjust Contrast button the Image Tool toolbar, or by selecting Adjust Contrast from the **Tools** menu in the Image Tool.
- **4** Move the cursor over the image. The cursor changes to the window/level shape •/...
- **5** Press and hold the left mouse button. As you move the window/level cursor horizontally to the left or right to adjust the contrast or move the cursor vertically up or down to change the brightness.

Autoscaling

You can perform automatic contrast adjustment by setting the axes CLim values to the minimum and maximum pixel values in the image. By default, the CLim minimum and maximum values are set to the full dynamic range of the image. To do this, click the **Autoscaling** button in the Adjust Contrast tool.

You can also trim outliers at the top and bottom of the image histogram. By default, the Adjust Contrast tool removes the top 1% and the bottom 1%, but you can specify other percentages. (You can perform this same operation from the command line using the stretchlim function.)



Viewing Multiple Images

If you specify a file that contains multiple images, imshow and imtool only display the first image in the file. To view all the images in the file, import the images into the MATLAB workspace by calling imread. See "Reading Multiple Images from a Graphics File" on page 2-16 for more information.

Some applications create collections of images related by time or view, such as magnetic resonance imaging (MRI) slices or frames of data acquired from a video stream. The Image Processing Toolbox supports these collections of images as four-dimensional arrays, where each separate image is called a frame and the frames are concatenated along the fourth dimension. All the frames in a multiframe image must be the same size.

Once the images are in the MATLAB workspace, there are two ways to display them using imshow:

- Displaying each image in a separate figure window
- Displaying multiple frames in a single figure window

To view all the frames in a multiframe image at once, you can also use the montage function. See "Displaying All Frames of a Multiframe Image at Once" on page 3-52 for more information.

Displaying Each Image in a Separate Figure

The simplest way to display multiple images is to display them in separate figure windows. MATLAB does not place any restrictions on the number of images you can display simultaneously.

The Image Tool can only display one image frame at a time. Each time you call imtool, it opens a new figure window. Use standard MATLAB indexing syntax to specify the frame to display.

```
imtool(multiframe array(:,:,:,1));
```

In contrast, imshow always displays an image in the current figure. If you display two images in succession, the second image replaces the first image. To view multiple figures with imshow, use the figure command to explicitly create a new empty figure before calling imshow for the next image. For example, to view the first three frames in an array of intensity images I,

```
imshow(I(:,:,:,1))
```

```
figure, imshow(I(:,:,:,2))
figure, imshow(I(:,:,:,3))
```

The Image Tool can only display one image frame at a time. Use standard MATLAB indexing syntax to specify the frame to display.

```
imtool(multiframe array(:,:,:,1));
```

Displaying Multiple Images in the Same Figure

You can use the imshow function with the MATLAB subplot function or the MATLAB subimage function to display multiple images in a single figure window.

Note imtool does not support this capability.

Dividing a Figure Window into Multiple Display Regions. subplot divides a figure into multiple display regions. The syntax of subplot is


```
subplot(m,n,p)
```


This syntax divides the figure into an m-by-n matrix of display regions and makes the pth display region active.

Note When you use subplot to display multiple color images in one figure window, the images must share the colormap of the last image displayed. In some cases, as illustrated by the following example, the display results can be unacceptable. As an alternative, you can use the subimage function, described in "Using the subimage Function to Display Multiple Images" on page 3-43, or you can map all images to the same colormap as you load them.

For example, you can use this syntax to display two images side by side.

```
[X1,map1]=imread('forest.tif');
[X2,map2]=imread('trees.tif');
subplot(1,2,1), imshow(X1,map1)
subplot(1,2,2), imshow(X2,map2)
```






Two Images in Same Figure Using the Same Colormap

Using the subimage Function to Display Multiple Images. subimage converts images to RGB before displaying them and therefore circumvents the colormap sharing problem. This example uses subimage to display the forest and the trees images with better results.

```
[X1,map1]=imread('forest.tif');
[X2,map2]=imread('trees.tif');
subplot(1,2,1), subimage(X1,map1)
subplot(1,2,2), subimage(X2,map2)
```



Two Images in Same Figure Using Separate Colormaps

Displaying Different Image Types

This section describes how to use imshow and imtool with the different types of images supported by the Image Processing Toolbox.

- Indexed images
- Intensity (grayscale) images
- Binary images
- RGB (truecolor) images

If you need help determining what type of image you are working with, see "Image Types in the Toolbox" on page 2-3.

Displaying Indexed Images

To display an indexed image, using either imshow or imtool, specify both the image matrix and the colormap. This documentation uses the variable name X to represent an indexed image in the workspace, and map to represent the colormap.

```
imshow(X,map)
or
imtool(X,map)
```

For each pixel in X, these functions display the color stored in the corresponding row of map. If the image matrix data is of class double, the value 1 points to the first row in the colormap, the value 2 points to the second row, and so on. However, if the image matrix data is of class uint8 or uint16, the value 0 (zero) points to the first row in the colormap, the value 1 points to the second row, and so on. This offset is handled automatically by the imtool and imshow functions.

If the colormap contains a greater number of colors than the image, the functions ignore the extra colors in the colormap. If the colormap contains fewer colors than the image requires, the functions set all image pixels over the limits of the colormap's capacity to the last color in the colormap. For example, if an image of class uint8 contains 256 colors, and you display it with a colormap that contains only 16 colors, all pixels with a value of 15 or higher are displayed with the last color in the colormap.

Displaying Intensity Images

To display an intensity (grayscale) image, using either imshow or imtool, specify the image matrix as an argument. This documentation uses the variable name I to represent an intensity image in the workspace.

```
imshow(I)
or
imtool(I)
```

Both functions display the image by *scaling* the intensity values to serve as indices into a grayscale colormap.

If I is double, a pixel value of 0.0 is displayed as black, a pixel value of 1.0 is displayed as white, and pixel values in between are displayed as shades of gray. If I is uint8, then a pixel value of 255 is displayed as white. If I is uint16, then a pixel value of 65535 is displayed as white.

Intensity images are similar to indexed images in that each uses an m-by-3 RGB colormap, but you normally do not specify a colormap for an intensity image. MATLAB displays intensity images by using a grayscale system colormap (where R=G=B). By default, the number of levels of gray in the colormap is 256 on systems with 24-bit color, and 64 or 32 on other systems. (See "Working with Different Screen Bit Depths" on page 13-3 for a detailed explanation.)

Displaying Intensity Images That Have Unconventional Ranges

In some cases, the image data you want to display as an intensity image might have a display range that is outside the conventional toolbox range (i.e., [0,1] for single or double arrays, [0,255] for uint8 arrays, [0,65535] for uint16 arrays, or [-32767,32768] for int16 arrays). For example, if you filter an intensity image, some of the output data might fall outside the range of the original data.


To display unconventional range data as an image, you can specify the display range directly, using this syntax for both the imshow and imtool functions.

```
imshow(I, 'DisplayRange',[low high])
or
imtool(I, 'DisplayRange',[low high])
```

If you use an empty matrix ([]) for the display range, these functions scale the data automatically, setting low and high to the minimum and maximum values in the array.

The next example filters an intensity image, creating unconventional range data. The example calls imtool to display the image, using the automatic scaling option. If you execute this example, note the display range specified in the lower right corner of the Image Tool window.

```
I = imread('testpat1.png');
J = filter2([1 2;-1 -2],I);
imtool(J,'DisplayRange',[]);
```




Displaying Binary Images

In MATLAB, a binary image is of class logical. Binary images contain only 0's and 1's. Pixels with the value 0 are displayed as black; pixels with the value 1 are displayed as white.

Note For the toolbox to interpret the image as binary, it must be of class logical. Intensity images that happen to contain only 0's and 1's are not binary images.

To display a binary image, using either imshow or imtool, specify the image matrix as an argument. For example, this code reads a binary image into the MATLAB workspace and then displays the image. This documentation uses the variable name BW to represent a binary image in the workspace


```
BW = imread('circles.png');
imshow(BW)
or
imtool(BW)
```



Changing the Display Colors of a Binary Image

You might prefer to invert binary images when you display them, so that 0 values are displayed as white and 1 values are displayed as black. To do this, use the NOT (\sim) operator in MATLAB. (In this figure, a box is drawn around the image to show the image boundary.) For example:

```
imshow(~BW)
or
imtool(~BW)
```




You can also display a binary image using the indexed image colormap syntax. For example, the following command specifies a two-row colormap that displays 0's as red and 1's as blue.

```
imshow(BW,[1 0 0; 0 0 1])
```

or

imtool(BW,[1 0 0; 0 0 1])



Displaying Truecolor Images

Truecolor images, also called RGB images, represent color values directly, rather than through a colormap. A truecolor image is an m-by-n-by-3 array. For each pixel (r,c) in the image, the color is represented by the triplet (r,c,1:3).

To display a truecolor image, using either imshow or imtool, specify the image matrix as an argument. For example, this code reads a truecolor image into the

MATLAB workspace and then displays the image. This documentation uses the variable name RGB to represent a truecolor image in the workspace

```
RGB = imread('peppers.png');
imshow(RGB)
or
imtool(RGB)
```



Systems that use 24 bits per screen pixel can display truecolor images directly, because they allocate 8 bits (256 levels) each to the red, green, and blue color planes. On systems with fewer colors, imshow displays the image using a combination of color approximation and dithering. See "Working with Different Screen Bit Depths" on page 13-3 for more information.

Note If you display a color image and it appears in black and white, check if the image is an indexed image. With indexed images, you must specify the colormap associated with the image. For more information, see "Displaying Indexed Images" on page 3-45.

Special Display Techniques

In addition to imshow and imtool, the toolbox includes functions that perform specialized display operations, or exercise more direct control over the display format. These functions, together with the MATLAB graphics functions, provide a range of image display options.

This section includes the following topics:

- "Adding a Colorbar" on page 3-51
- "Displaying All Frames of a Multiframe Image at Once" on page 3-52
- "Converting a Multiframe Image to a Movie" on page 3-54
- "Texture Mapping" on page 3-55

Adding a Colorbar

To display an image with a colorbar that indicates the range of intensity values, first use the imshow function to display the image in a MATLAB figure window and then call the colorbar function to add the colorbar to the image.


When you add a colorbar to an axes object that contains an image object, the colorbar indicates the data values that the different colors in the image correspond to.

If you want to add a colorbar to an image displayed in the Image Tool, select the **Print to Figure** option from the Image Tool **File** menu. The Image Tool displays the image in a separate figure window to which you can add a colorbar.

Seeing the correspondence between data values and the colors displayed by using a colorbar is especially useful if you are displaying unconventional range data as an image, as described under "Displaying Intensity Images That Have Unconventional Ranges" on page 3-46.

In the example below, a grayscale image of class uint8 is filtered, resulting in data that is no longer in the range [0,255].

```
RGB = imread('saturn.png');
I = rgb2gray(RGB);
h = [1 2 1; 0 0 0; -1 -2 -1];
I2 = filter2(h,I);
imshow(I2,'DisplayRange',[]), colorbar
```



Displaying All Frames of a Multiframe Image at Once

To view all the frames in a multiframe array at one time, use the montage function. montage divides a figure window into multiple display regions and displays each image in a separate region.

The syntax for montage is similar to the imshow syntax. To display a multiframe intensity image, the syntax is


montage(I)

To display a multiframe indexed image, the syntax is montage(X,map)

Note All the frames in a multiframe indexed array must use the same colormap.

This example loads and displays all frames of a multiframe indexed image. The example initializes an array to hold the 27 frames in the multiframe image file and then loops, using imread to read a single frame from the image file at each iteration.

```
mri = uint8(zeros(128,128,1,27));
for frame=1:27
    [mri(:,:,:,frame),map] = imread('mri.tif',frame);
end
montage(mri,map);
```



All Frames of Multiframe Image Displayed in One Figure

montage displays the first frame in the first position of the first row, the next frame in the second position of the first row, and so on. montage arranges the frames so that they roughly form a square.

Converting a Multiframe Image to a Movie

To create a MATLAB movie from a multiframe image array, use the immovie function. This example creates a movie from a multiframe indexed image.

```
mov = immovie(X,map);
```

In the example, X is a four-dimensional array of images that you want to use for the movie.

You can play the movie in MATLAB using the movie function.

```
movie(mov);
```

This example loads the multiframe image mri.tif and makes a movie out of it. It won't do any good to show the results here, so try it out; it's fun to watch.

```
mri = uint8(zeros(128,128,1,27));
for frame=1:27
    [mri(:,:,:,frame),map] = imread('mri.tif',frame);
end

mov = immovie(mri,map);
movie(mov);
```

Note that immovie displays the movie as it is being created, so you actually see the movie twice. The movie runs much faster the second time (using movie).


Note To view a MATLAB movie, you must have MATLAB installed. To make a movie that can be run outside MATLAB, use the MATLAB avifile and addframe functions to create an AVI file. AVI files can be created using indexed and RGB images of classes uint8 and double, and don't require a multiframe image.

Texture Mapping

When you use imshow or imtool to view an image, MATLAB displays the image in two dimensions. However, it is also possible to map an image onto a parametric surface, such as a sphere, or below a surface plot. The warp function creates these displays by *texture mapping* the image. Texture mapping is a process that maps an image onto a surface grid using interpolation.

This example texture-maps an image of a test pattern onto a cylinder.

```
[x,y,z] = cylinder;
I = imread('testpat1.png');
warp(x,y,z,I);
```



An Image Texture Mapped onto a Cylinder

The image might not map onto the surface in the way that you expect. One way to modify the way the texture map appears is to change the settings of the Xdir, Ydir, and Zdir properties. For more information, see "Changing Axis Direction" in the MATLAB Graphics documentation.

For more information about texture mapping, see the reference entry for the warp function.

Printing Images

If you want to output a MATLAB image to use in another application (such as a word-processing program or graphics editor), use imwrite to create a file in the appropriate format. See "Writing a Graphics Image" on page 2-16 for details.

If you want to print an image, use imshow to display the image in a MATLAB figure window. If you are using the Image Tool, you must use the **Print to Figure** option on the Image Tool **File** menu. When you choose this option, the Image Tool opens a separate figure window and displays the image in it. You can access the standard MATLAB printing capabilities in this figure window. You can also use the **Print to Figure** option to print the image displayed in the Overview tool and the Pixel Region tool.

Once the image is displayed in a figure window, you can use either the MATLAB print command or the **Print** option from the **File** menu of the figure window to print the image. When you print from the figure window, the output includes nonimage elements such as labels, titles, and other annotations.

Printing and Handle Graphics Object Properties

The output reflects the settings of various properties of Handle Graphic objects. In some cases, you might need to change the settings of certain properties to get the results you want. Here are some tips that might be helpful when you print images:

- Image colors print as shown on the screen. This means that images are not affected by the figure object's InvertHardcopy property.
- To ensure that printed images have the proper size and aspect ratio, set the figure object's PaperPositionMode property to auto. When PaperPositionMode is set to auto, the width and height of the printed figure are determined by the figure's dimensions on the screen. By default, the value of PaperPositionMode is manual. If you want the default value of PaperPositionMode to be auto, you can add this line to your startup.m file.

```
set(0, 'DefaultFigurePaperPositionMode', 'auto')
```

For detailed information about printing with **File/Print** or the print command (and for information about Handle Graphics), see "Printing and Exporting Figures with MATLAB" in the MATLAB Graphics documentation. For a

complete list of options for the print command, enter help print at the MATLAB command-line prompt or see the print command reference page in the MATLAB documentation.

Setting Toolbox Display Preferences

You can use Image Processing Toolbox preferences to control certain characteristics of how imshow and imtool display images on your screen. For example, using toolbox preferences, you can specify the initial magnification used by imtool and imshow.

This section

- Lists the preferences supported by the toolbox
- Describes how to get the current value of a preference using the iptgetpref function
- Describes how to set the value of a preference using the iptsetpref function

Toolbox Preferences

The Image Processing Toolbox supports several preferences that affect how imshow and imtool display images. The following table lists these preferences with brief descriptions. For detailed information about toolbox preferences and their values, see the iptsetpref reference page.

Toolbox Preference	Description
ImshowBorder	Controls whether imshow displays the figure window as larger than the image (leaving a border between the image axes and the edges of the figure), or the same size as the image (leaving no border).
ImshowAxesVisible	Controls whether imshow displays images with the axes box and tick labels.
ImshowInitialMagnification	Controls the magnification imshow uses when it initially displays an image. This preference can be overridden for a single call to imshow; see "Specifying the Initial Image Magnification" on page 3-5 for more details.
ImtoolInitialMagnification	Controls the magnification the Image Tool uses when it initially displays an image. This preference can be overridden for a single call to imtool; see "Specifying the Initial Image Magnification" on page 3-11 for more details.

Retrieving the Values of Toolbox Preferences

To determine the current value of a preference, use the iptgetpref function. This example uses iptgetpref to determine the value of the imtoolInitialMagnification preference.

```
iptgetpref('ImtoolInitialMagnification')
ans =
   100
```

Preference names are case insensitive and can be abbreviated. For more information, see the iptgetpref reference page.

Setting the Value of Toolbox Preferences

To specify the value of a toolbox preference, use the iptsetpref function. This example calls iptsetpref to specify that imshow resize the figure window so that it fits tightly around displayed images.

```
iptsetpref('ImshowBorder', 'tight');
```

For detailed information about toolbox preferences and their values, see the iptsetpref reference page.

The value you specify lasts for the duration of the current MATLAB session. To preserve your preference settings from one session to the next, include the iptsetpref commands in your startup.m file.

Building GUIs with Modular Tools

This chapter describes how to use the toolbox modular tools to create custom image processing applications.

"Overview" on page 4-2

Lists the modular interactive tools

"Using Modular Tools" on page 4-6

Describes how to use the modular tools to create GUIs

"Creating Your Own Modular Tools" on

Describes the utility function the toolbox provides to help

page 4-28

you create your own modular tools

Overview

The toolbox includes several new modular interactive tools that you can activate from the command line and use with images displayed in a MATLAB figure window, called the target image in this documentation. The tools are modular because they can be used independently or in combination to create custom graphical user interfaces (GUIs) for image processing applications. The Image Tool uses these modular tools.

The following table lists the modular tools in alphabetical order. The table includes an illustration of the tool and the function you use to create them. For more information about how the tools operate, see "Using the Image Tool to Explore Images" on page 3-8. For more information about using tools to create GUIs, see "Using Modular Tools" on page 4-6.

Modular Tool	Example	Description
Adjust Contrast tool	Adjust Contrast (Image Tool 1) File Window Help Auto Scale Reset Image Minimum Value 0 Window Wicth 255 Maximum Value 255 Window Center 128 Adjust the histogram above, or click and drag the mouse	Displays a histogram of the target image and enables interactive adjustment of contrast and brightness by manipulating the display range. Use the imcontrast function to create the tool in a separate figure window and associate it with an image.
Display Range tool	Display range: [0 255]	Displays a text string identifying the display range values of the associated image.
		Use the imdisplayrange function to create the tool, associate it with an image, and embed it in a figure or uipanel.

Modular Tool	Example	Description
Image Information tool	Trace of State Trace	Displays basic attributes about the target image. If the name of the graphics file containing the image was specified, the tool includes any metadata the image file might contain. Use the imageinfo function to create the tool in a separate figure window and associate it with an image.
Magnification box	100%	Creates a text edit box containing the current magnification of the target image. Users can change the magnification of the image by entering a new magnification value. Use immagbox to create the tool, associate it with an image, and embed it in a figure or uipanel.
		Note: The target image must be contained in a scroll panel.

Modular Tool	Example	Description
Overview tool	Dverview (Image Tool 1) File Edit Window Help	Displays the target image in its entirety with the portion currently visible in the scroll panel outlined by a rectangle superimposed on the image. Moving the rectangle changes the portion of the target image that is currently visible in the scroll panel. Use imoverview to create the tool in a separate figure window and associate it with an image. Use imoverviewpanel to create the tool in a uipanel that can be embedded within another figure or uipanel.
		Note: The target image must be contained in a scroll panel.
Pixel Information tool	Pixel info: (X, Y) Intensity	Displays information about the pixel the mouse is over in the target image.
		Use impixelinfo to create the tool, associate it with an image, and display it in a figure or uipanel.
		If you want to display only the pixel values, without the Pixel info label, use impixelinfoval.

Modular Tool	Example	Description
Pixel Region tool	File Edit Window Help 215 211 219 217 218 221 218 220 218 209 2 2 211 208 213 213 216 219 219 219 211 208 2 211 203 208 213 220 219 216 216 206 207 2 203 198 205 215 226 222 217 216 203 199 1 195 195 204 217 228 223 217 217 202 186 1 194 196 200 212 225 223 209 202 200 184 1 191 188 188 199 211 213 199 189 195 184 1 191 Pixel info: (134, 230) 183	Display pixel values for a specified region in the target image. Use impixelregion to create the tool in a separate figure window and associate it with an image. Use impixelregionpanel to create the tool as a uipanel that can be embedded within another figure or uipanel.
Scroll Panel tool	File Tools Help Tools Help	Display target image in a scrollable panel. Use imscrollpanel to add a scroll panel to an image displayed in a figure window.

Using Modular Tools

To use the modular tools to create custom graphical user interfaces (GUIs) for image processing applications, follow this general procedure:

1 Display the target image in a figure window.

Image processing applications typically include the display of the target image, i.e., the image being processed. You can use the imshow function as the foundation for your GUI application. (You can also use the MATLAB image and imagesc functions.) See "Displaying the Target Image" on page 4-7 for more information.

2 Create the modular tool, specifying the target image.

The modular tools operate on an image. When you create a tool, you must associate it with a target image. Most of the tools associate themselves with the image in the current axes, by default. But you can specify the handle to a specific image object, or a handle to a figure, axes, uipanel object that contains an image. See "Specifying the Target Image" on page 4-7 for more information.

Depending on how you designed your GUI, you might also want to specify the parent object of the modular tool. This is optional; by default, the tools either use the same parent as the target image or open in a separate figure window. If you want to change this default, you must specify the parent. See "Specifying the Parent of a Modular Tool" on page 4-11 for more information.

In addition, when you create custom GUIs, you might need to specify the position of the graphics objects in the GUI, including the modular tools. See "Positioning the Modular Tools in a GUI" on page 4-13 for more information.

3 Set up interactivity between the tool and the target image.

This is an optional step. The modular tools all setup their interactive connection to the target image automatically. However, your GUI might require some additional connectivity. See "Making Connections for Interactivity" on page 4-22.

The following sections provide more detail on these steps. For a complete illustration, see "Example: Building a Pixel Information GUI" on page 4-15.

Displaying the Target Image

As the foundation for any image processing GUI you create, use imshow to display the target image (or images) in a MATLAB figure window. (You can also use the MATLAB image or imagesc functions.) Once the image is displayed in the figure, you can associate any of the modular tools with the image displayed in the figure.

This example uses imshow to display an image in a figure window.

```
himage = imshow('pout.tif');
```

Because some of the modular tools add themselves to the figure window containing the image, make sure that the Image Processing Toolbox ImshowBorder preference is set to 'loose', if you are using the imshow function. By including a border, you ensure that the modular tools do not display over the image in the figure. This is the default setting.

Specifying the Target Image

To associate a modular tool with a target image displayed in a MATLAB figure window, create the tool using the appropriate tool creation function, specifying a handle to the target image as an argument. The function creates the tool and automatically sets up the interactivity connection between the tool and the target image that the tool requires.

This section covers the following topics:

- "Associating Modular Tools with the Default Target Image" on page 4-7
- "Associating Modular Tools with a Particular Image" on page 4-8
- "Getting the Handle of the Target Image" on page 4-10

Associating Modular Tools with the Default Target Image

By default, most of the modular tool creation functions support a no-argument syntax that uses the image in the current figure as the target image. If the current figure contains multiple images, the tools associate themselves with the first image in the figure object's children (the last image created).

impixelinfo, impixelinfoval and imdisplayrange canwork with multiple images in a figure.

For example, to use the Pixel Information tool with a target image, display the image in a figure window, using imshow, and then call the impixelinfo function to create the tool. In this example, the image in the current figure is the target image.

```
imshow('pout.tif');
impixelinfo
```

The following figure shows the target image in a figure with the Pixel Information tool in the lower-left corner of the window. The Pixel Information tool automatically sets up a connection to the target image: when you move the cursor over the image, the tool displays the x- and y-coordinates and value of the pixel under the cursor.




Figure Window with Pixel Information Tool

Associating Modular Tools with a Particular Image

You can specify the target image of the modular tool when you create it. Pass a handle to the target image as an argument to the modular tool creation

function. You can also specify a handle to a figure, axes, or uipanel object that contains the target image.

Continuing the example in the previous section, you might want to add the Display Range tool to the figure window that already contains the Pixel Information tool. To do this, call the imdisplayrange function, specifying the handle to the target image. You could also have specified the handle of the figure, axes, or uipanel object containing the target image.

```
himage = imshow('pout.tif');
hpixelinfopanel = impixelinfo(himage)
hdrangepanel = imdisplayrange(himage)
```

Note that the example retrieves handles to the uipanel objects created by the impixelinfo and imdisplayrange functions; both tools are uipanel objects. It can be helpful to get handles to the tools if you want to change their positioning. See "Positioning the Modular Tools in a GUI" on page 4-13 for more information.

The following figure shows the target image in a figure with the Pixel Information tool in the lower-left corner and the Display Range tool in the lower-right corner of the window. The Display Range tool automatically sets up a connection to the target image: when you move the cursor over the image (or images) in the figure, the Display Range tool shows the display range of the image.




Figure Window with Pixel Information and Display Range Tools

Getting the Handle of the Target Image

The examples in the previous section use the optional imshow syntax in which it returns a handle to the image displayed, himage. When creating GUIs with the modular tools, having a handle to the target image can be useful. You can get the handle when you first display the image, using this optional imshow syntax.

You can also get a handle to the target image using the imhandles function. The imhandles function returns all the image objects that are children of a specified figure, axes, uipanel, or image object.

For example, imshow returns a handle to the image in this syntax.

```
hfig = figure;
himage = imshow('moon.tif')
himage =
  152.0055
```

When you call the imhandles function, specifying a handle to the figure (or axes) containing the image, it returns a handle to the same image.

```
himage2 = imhandles(hfig)
himage2 =

152.0055
```

Specifying the Parent of a Modular Tool

When you create a modular tool, in addition to specifying the target image, you can optionally specify the object that will be the parent of the tool. By specifying the parent, you determine where the tool appears on your screen. Using this syntax of the modular tool creation functions, you can add the tool to the figure window containing the target image, open the tool in a separate figure window, or create some other combination.

Specifying the parent is optional; the modular tools all have a default behavior. Some of the smaller tools, such as the Pixel Information tool, use the parent of the target image as their parent, inserting themselves in the same figure window as the target image. Other modular tools, such as the Pixel Region tool or the Overview tool, open in a separate figure of their own.


Two of the tools, the Pixel Region tool and the Overview tool, provide a separate creation function to provide this capability. Their primary creation functions, imoverview and impixelregion, open the tools in a separate figure window. To specify a different parent, you must use the imoverviewpanel and impixelregionpanel functions.

Note The Overview tool and the Pixel Region tool provide additional capabilities when created in their own figure window. For example, both tools include zoom buttons which are not part of their uipanel versions.

This example shows the default behavior when you create the Pixel Region tool using the impixelregion function. The tool opens in a separate figure window, as shown in the following figure.

```
himage = imshow('pout.tif')
hpixelinfopanel = impixelinfo(himage)
hdrangepanel = imdisplayrange(himage)
```






Target Image with Pixel Region Tool in Separate Window (Default)

To embed the Pixel Region tool in the same window as the target image, you must specify the handle of the target image's parent figure as the parent of the Pixel Region tool when you create it.

The following example creates a figure and an axes, getting handles to both objects. The example needs these handles to perform some repositioning of the objects in the figure to ensure their visibility. See "Positioning the Modular Tools in a GUI" on page 4-13 for more information. The example then creates the modular tools, specifying the figure containing the target image as the parent of the Pixel Region tool. Note the example uses the impixelregionpanel function to create the tool.

```
hfig = figure;
hax = axes('units','normalized','position',[0 .5 1 .5]);
himage = imshow('pout.tif')
hpixelinfopanel = impixelinfo(himage)
hdrangepanel = imdisplayrange(himage)
hpixreg = impixelregionpanel(hfig,himage)
set(hpixreg, 'Units','normalized','Position',[0 .08 1 .4])
```

The following figure shows the Pixel Region embedded in the same figure as the target image.



Target Image with Embedded Pixel Region Tool

Positioning the Modular Tools in a GUI

When you create the modular tools, they have default positioning behavior. For example, the impixelinfo function creates the tool as a uipanel object that is

the full width of the figure window, positioned in the lower-left corner of the target image figure window.

Because the modular tools are constructed from standard Handle Graphics objects, such as uipanel objects, you can use properties of the objects to change their default positioning or other characteristics.

For example, in "Specifying the Parent of a Modular Tool" on page 4-11, when the Pixel Region tool was embedded in the same figure window as the target image, the example had to reposition both the image object and the Pixel Region tool uipanel object to make them both visible in the figure window.

To reposition a modular tool or other graphics object, set the value of the Position property of the object. As the value of this property, you specify a four-element position vector [left bottom width height], where left and bottom specify the distance from the lower-left corner of the parent container object, such as a figure. The width and height specify the dimensions of the object. You must specify the units of these values. Many graphics object use normalized units which specify the relative position, not the exact location in pixels, to allow better resizing behavior. Get the value of the Units property of the object to determine how the object interprets the position vector.

For example, when you first create an embedded Pixel Region tool in a figure, it appears to take over the entire figure because, by default, the position vector is set to [0 0 1 1], in normalized units. This position vector tells the tool to align itself with the bottom-left corner of its parent and fill the entire object. To accommodate the image and the Pixel Information tool and Display Range tools, change the position of the Pixel Region so that it fills the lower half of the figure, leaving room at the bottom for the Pixel Information and Display Range tools. Here is the position vector for the Pixel Region tool.

```
set(hpixreg, 'Units', 'normalized', 'Position', [0.081.4])
```

To accommodate the Pixel Region tool, you must reposition the target image so that it takes the upper half of the window, using the following position vector. To reposition the image, you must specify the Position property of the axes object that contains it; image objects do not have a Position property.

```
set(hax, 'Units', 'normalized', 'Position', [0 0.5 1 0.5])
```

Example: Building a Pixel Information GUI

This example shows how to use the tools to create a simple GUI. If your work typically requires information about the pixels in an image, you might want to create a custom image display function that provides this information. You can do this by using the three modular tools that provide pixel information:

- Pixel Information tool
- Display Range tool
- Pixel Region tool

This example creates a simple image display function that includes these tools. In this GUI, the Pixel Region tool is embedded in the same figure window as the target image. The example suppresses the figure window toolbar and menu bar because the standard figure zoom tools are not compatible with the toolbox modular navigation tools — see "Adding Navigation Aids to a GUI" on page 4-17.

```
function my pixinfotool(im)
% Create figure, setting up properties
hfig = figure('Toolbar', 'none',...
              'Menubar', 'none',...
              'Name', 'My Pixel Info Tool',...
              'NumberTitle','off',...
              'IntegerHandle', 'off');
% Create axes
% Reposition the image to accommodate the Pixel Region tool
hax = axes('Units','normalized',...
           'Position',[0 .5 1 .5]);
% Display image, getting handle to image
himage = imshow(im)
% Add Pixel Information tool to image figure window
hpixinfo = impixelinfo(himage)
% Add Display Range tool to image figure window
hdrange = imdisplayrange(himage)
% Add Pixel Region tool as panel in same figure
```

```
hpixreg = impixelregionpanel(hfig,himage)
% Reposition the Pixel Region tool to fit in the figure
% window, leaving room for the Pixel Information and
% Display Range tools.
set(hpixreg, 'units', 'normalized', 'position', [0 .08 1 .4])
```

To use the tool, pass it an image that is already in the MATLAB workspace.

```
pout = imread('pout.tif');
my pixinfotool(pout)
```

The tool opens a figure window, displaying the image in the upper half and the three pixel information modular tools, the Pixel Information tool, Display Range tool, and the Pixel Region tool, in the lower half.



Custom Image Display Tool with Pixel Information

Adding Navigation Aids to a GUI

Note The toolbox modular navigation tools are incompatible with standard MATLAB figure window navigation tools. When using these tools in a GUI, suppress the toolbar and menu bar in the figure windows to avoid conflicts between the tools.

The toolbox includes several modular tools that you can use to add navigation aids to a GUI application:

- Scroll Panel
- Overview tool
- Magnification box tool

The Scroll Panel is the primary navigation tool; it is a prerequisite for the other navigation tools. When you display an image in a Scroll Panel, the tool displays only a portion of the image, if it is too big to fit into the figure window. When only a portion of the image is visible, the Scroll Panel adds horizontal and vertical scroll bars, to enable viewing of the parts of the image that are not currently visible.

Once you create a Scroll Panel, you can optionally add the other modular navigation tools: the Overview tool and the Magnification tool. The Overview tool displays a view of the entire image, scaled to fit, with a rectangle superimposed over it that indicates the part of the image that is currently visible in the scroll panel. The Magnification Box displays the current magnification of the image and can be used to change the magnification.

The following sections provide more details.


- "Understanding Scroll Panels" on page 4-18 Adding a scroll panel to an image display changes the relationship of the graphics objects used in the display. This section provides some essential background.
- "Example: Building a Navigation GUI for Large Images" on page 4-20 This section shows how to add a scroll panel to an image display.

Understanding Scroll Panels

When you display an image in a scroll panel, it changes the object hierarchy of your displayed image. This diagram illustrates the typical object hierarchy for an image displayed in an axes object in a figure object.

```
hfia = figure;
himage = imshow('concordaerial.png');
```

The following figure shows this object hierarchy.




Object Hierarchy of Image Displayed in a Figure

When you call the imscrollpanel function to put the target image in a scrollable window, this object hierarchy changes. For example, this code adds a scroll panel to an image displayed in a figure window, specifying the parent of the scroll panel and the target image as arguments. The example suppresses the figure window toolbar and menu bar because they are not compatible with the scroll panel navigation tools.


```
hfig = figure('Toolbar','none',...
              'Menubar', 'none');
himage = imshow('concordaerial.png');
hpanel = imscrollpanel(hfig,himage);
```

The following figure shows the object hierarchy after the call to imscrollpanel. Note how imscrollpanel inserts new objects (shaded in gray) into the hierarchy between the figure object and the axes object containing the image.



Object Hierarchy of Image Displayed in Scroll Panel

The following figure shows how these graphics objects appear in the scrollable image as it displayed on the screen.



Components of a Scroll Panel

Example: Building a Navigation GUI for Large Images

If your work typically requires that you view large images, you might want to create a custom image display function that includes the modular navigation tools.

This example creates a tool that accepts an image as an argument and displays the image in a scroll panel with an Overview tool and a Magnification box.

Note Because the toolbox scrollable navigation is incompatible with standard MATLAB figure window navigation tools, the example suppresses the toolbar and menu bar in the figure window.


function my large image display(im)

```
% Create a figure without toolbar and menubar.
hfig = figure('Toolbar','none',...
              'Menubar', 'none',...
              'Name', 'My Large Image Display Tool',...
              'NumberTitle','off',...
              'IntegerHandle', 'off');
% Display the image in a figure with imshow.
himage = imshow(im)
% Add the scroll panel.
hpanel = imscrollpanel(hfig,himage)
% Position the scroll panel to accommodate the other tools.
set(hpanel, 'Units', 'normalized', 'Position',[0 .1 1 .9])
% Add the Magnification Box.
hMagBox = immagbox(hfig,himage);
% Position the Magnification Box
pos = get(hMagBox, 'Position');
set(hMagBox, 'Position',[0 0 pos(3) pos(4)])
% Add the Overview tool.
hovervw = imoverview(himage)
```

To use the tool, pass it a large image that is already in the MATLAB workspace.

```
big_image = imread('peppers.png');
my large image display(big image)
```

The tool opens a figure window, displaying the image in a scroll panel with the other modular navigation tools: the Overview tool and the Magnification Box tool.



Custom Image Display Tool with Navigation Aids

Making Connections for Interactivity

When you create a modular tool and associate it with a target image, the tool automatically makes the necessary connections to the target image to do its job.

For example, the Pixel Information tool sets up a connection to the target image so that it can display the location and value of the pixel currently under the cursor. The Overview tool sets up a two-way connection to the target image:

• Target image to the Overview tool — If the visible portion of the image changes, by scrolling, panning, or by changing the magnification, the Overview tool changes the size and location of the detail rectangle to the indicate the portion of the image that is now visible.

• Overview tool to the target image — If a user moves the detail rectangle in the Overview tool, the portion of the target image visible in the scroll panel updates.

The modular tools accomplish this interactivity by using callback properties of the graphics objects. For example, the figure object supports a 'WindowButtonMotionFcn' callback that executes whenever the mouse button is depressed.

In addition, some of the modular tools also support an Application Programmer Interface (API). This API is a set of functions that let you get information about the tool as it operates and set up callbacks to get notification of events.

For example, the Magnification Box supports a single API function: setMagnification. You can use this API function to set the magnification value displayed in the Magnification Box. The Magnification box automatically notifies the scroll panel to change the magnification of the image based on the value. The scroll panel also supports an extensive set of API functions; see the imscrollpanel reference page for more information.

Example: Building an Image Comparison Tool


To illustrate how to use callbacks to make the connections required for interactions between tools, this example uses the Scroll Panel API to build a simple image comparison GUI. This custom tool displays two images side-by-side in scroll panels that are synchronized in location and magnification. The custom tool also includes an Overview tool and a Magnification Box.

```
% Display right image
subplot(122)
hImR = imshow(right image);
% Create a scroll panel for left image
hSpL = imscrollpanel(hFig,hImL);
set(hSpL, 'Units', 'normalized',...
    'Position',[0 0.1 .5 0.9])
% Create scroll panel for right image
hSpR = imscrollpanel(hFig,hImR);
set(hSpR, 'Units', 'normalized',...
    'Position',[0.5 0.1 .5 0.9])
% Add a Magnification box
hMagBox = immagbox(hFig,hImL);
pos = get(hMagBox, 'Position');
set(hMagBox, 'Position',[0 0 pos(3) pos(4)])
%% Add an Overview tool
imoverview(hImL)
%% Get APIs from the scroll panels
apiL = iptgetapi(hSpL);
apiR = iptgetapi(hSpR)
% Synchronize left and right scroll panels
apiL.setMagnification(apiR.getMagnification())
apiL.setVisibleLocation(apiR.getVisibleLocation())
% When magnification changes on left scroll panel,
% tell right scroll panel
apiL.addNewMagnificationCallback(apiR.setMagnification);
% When magnification changes on right scroll panel,
% tell left scroll panel
apiR.addNewMagnificationCallback(apiL.setMagnification);
% When location changes on left scroll panel,
% tell right scroll panel
```

```
apiL.addNewLocationCallback(apiR.setVisibleLocation);
% When location changes on right scroll panel,
% tell left scroll panel
apiR.addNewLocationCallback(apiL.setVisibleLocation);
```

The tools sets up a complex interaction between the scroll panels with just a few calls to Scroll Panel API functions. In the code, the tool specifies a callback function to execute every time the magnification changes. The function specified is the setMagnification API function of the other scroll panel. Thus, whenever the magnification changes in one of the scroll panels, the other scroll panel changes its magnification to match. The tool sets up a similar connection for position changes.

The following figure is a sequence diagram that shows the interaction between the two Scroll Panels set up by the comparison tool for both changes in magnification and location.




Scroll Panel Connections in Custom Image Comparison Tool

To use the image comparison tool, pass it two images as arguments.

```
left_image = imread('peppers.png');
right_image = edge(left_image(:,:,1), 'canny');
```

```
my_image_compare_tool(left_image,right_image);
```

The tool opens a figure window, displaying the two images side-by-side, in separate scroll panels. The custom compare tool also includes an Overview tool and a Magnification Box. When you move the detail rectangle in the Overview tool or change the magnification in one image, both images respond.



Custom Image Comparison Tool with Synchronized Scroll Panels

Creating Your Own Modular Tools

Because the toolbox uses an open architecture for the modular interactive tools, you can extend the toolbox by creating your own modular interactive tools, using standard Handle Graphics concepts and techniques. To help you create tools that integrate well with the existing modular interactive tools, the toolbox includes many utility functions that perform commonly needed tasks.

The utility functions can help check the input arguments to your tool, add callback functions to a callback list or remove them from a list, draw a rectangle over an image, and align figure windows in relation to a fixed window. The following table lists these utility functions in alphabetical order. See the function's reference page for more detailed information.

Utility Function	Description
getimagemodel	Retrieve imagemodel objects from image handles
getrangefromclass	Get dynamic range of image based on its class.
imagemodel	Access to properties of an image relevant to its display
imattributes	Return information about image attributes
imgca	Get handle to most recent current axis containing an image
imgcf	Get handle to most recent current figure containing an image
imgetfile	Displays Open Image dialog box
imhandles	Get all image handles within a handle
impositionrect	Create draggable position rectangle
iptaddcallback	Add function handle to a callback list
iptcheckconn	Check validity of connectivity argument
iptcheckhandle	Check validity of image handle argument

Utility Function	Description
iptcheckinput	Check validity of input argument
iptcheckmap	Check validity of colormap argument
iptchecknargin	Check number of input arguments
iptcheckstrs	Check validity of string argument
iptgetapi	Get Application Program Interface (API) for a handle
ipticondir	Return name of directories containing IPT and MATLAB icons
iptnum2ordinal	Convert positive integer to ordinal string
iptremovecallback	Delete function handle from callback list
iptwindowalign	Align figure windows

Spatial Transformations

Transformations (p. 5-11)

This chapter describes the spatial transformation functions in the Image Processing Toolbox. Spatial transformations map pixel locations in an input image to new locations in an output image.

Terminology (p. 5-2)	Provides definitions of image processing terms used in this section
Interpolation (p. 5-3)	Defines interpolation, the process used to estimate the value of a pixel in an output image when that pixel does not appear in the input image
Image Resizing (p. 5-5)	Describes how to use the ${\tt imresize}$ function to change the size of an image
Image Rotation (p. 5-8)	Describes how to use the imrotate function to rotate an image
Image Cropping (p. 5-10)	Describes how to use the imcrop function to extract a rectangular portion of an image
Performing General Spatial	Describes the general spatial transformation capabilities

of the toolbox

Terminology

An understanding of the following terms will help you to use this chapter.

Term	Definition
aliasing	Artifacts in an image that can appear as a result of reducing an image's size. When the size of an image is reduced, original pixels are downsampled to create fewer pixels. Aliasing that occurs as a result of size reduction normally appears as "stair-step" patterns (especially in high contrast images), or as "moire" (ripple-effect) patterns.
antialiasing	Any method for correcting aliasing (see above). The method discussed in this chapter is low-pass filtering (see below).
bicubic interpolation	Output pixel values are calculated from a weighted average of pixels in the nearest 4-by-4 neighborhood.
bilinear interpolation	Output pixel values are calculated from a weighted average of pixels in the nearest 2-by-2 neighborhood.
geometric operation	An operation that modifies the spatial relations between pixels in an image. Examples include resizing (growing or shrinking), rotating, and shearing.
interpolation	The process used to estimate an image value at a location in between image pixels.
nearest-neighbor interpolation	Output pixel values are assigned the value of the pixel that the point falls within. No other pixels are considered.

Interpolation

Interpolation is the process used to estimate an image value at a location in between image pixels. For example, if you resize an image so it contains more pixels than it did originally, the toolbox uses interpolation to determine the values for the additional pixels. The imresize and imrotate geometric functions use two-dimensional interpolation as part of the operations they perform. The improfile image analysis function also uses interpolation. See "Intensity Profile" on page 10-5 for information about this function.

Interpolation Methods

The Image Processing Toolbox provides three interpolation methods:

- Nearest-neighbor interpolation
- Bilinear interpolation
- Bicubic interpolation

The interpolation methods all work in a fundamentally similar way. In each case, to determine the value for an interpolated pixel, they find the point in the input image that the output pixel corresponds to. They then assign a value to the output pixel by computing a weighted average of some set of pixels in the vicinity of the point. The weightings are based on the distance each pixel is from the point.

The methods differ in the set of pixels that are considered:

- For nearest-neighbor interpolation, the output pixel is assigned the value of the pixel that the point falls within. No other pixels are considered.
- For bilinear interpolation, the output pixel value is a weighted average of pixels in the nearest 2-by-2 neighborhood.
- For bicubic interpolation, the output pixel value is a weighted average of pixels in the nearest 4-by-4 neighborhood.

The number of pixels considered affects the complexity of the computation. Therefore the bilinear method takes longer than nearest-neighbor interpolation, and the bicubic method takes longer than bilinear. However, the greater the number of pixels considered, the more accurate the effect is, so there is a tradeoff between processing time and quality.

Image Types

The functions that use interpolation take an argument that specifies the interpolation method. For most of these functions, the default method is nearest-neighbor interpolation. This method produces acceptable results for all image types, and is the only method that is appropriate for indexed images. For intensity and RGB images, however, you should generally specify bilinear or bicubic interpolation, because these methods produce better results than nearest-neighbor interpolation.

For RGB images, interpolation is performed on the red, green, and blue image planes individually.

For binary images, interpolation has effects that you should be aware of. If you use bilinear or bicubic interpolation, the computed values for the pixels in the output image will not all be 0 or 1. The effect on the resulting output image depends on the class of the input image:

- If the class of the input image is double, the output image is a grayscale image of class double. The output image is not binary, because it includes values other than 0 and 1.
- If the class of the input image is uint8, the output image is a binary image of class uint8. The interpolated pixel values are rounded off to 0 and 1 so the output image can be of class uint8.

Note For bicubic interpolation, you might need to clamp doubles to within the [0 1] range.

If you use nearest-neighbor interpolation, the result is always binary, because the values of the interpolated pixels are taken directly from pixels in the input image.

Image Resizing

To change the size of an image, use the imresize function. Using imresize, you can

- Specify the size of the output image
- Specify the interpolation method used
- Specify the filter to use to prevent aliasing

Specifying the Size of the Output Image


Using imresize, you can specify the size of the output image in two ways:

- By specifying the magnification factor to be used on the image
- By specifying the dimensions of the output image

Using the Magnification Factor

To enlarge an image, specify a magnification factor greater than 1. To reduce an image, specify a magnification factor between 0 and 1. For example, the command below increases the size of the image I by 1.25 times.

```
I = imread('circuit.tif');
J = imresize(I,1.25);
imshow(I)
figure, imshow(J)
```






Image Courtesy of Steve Decker and Shujaat Nadeem

Specifying the Size of the Output Image

You can specify the size of the output image by passing a vector that contains the number of rows and columns in the output image. The following command creates an output image, Y, with 100 rows and 150 columns.

Y = imresize(X,[100 150])

Note If the specified size does not produce the same aspect ratio as the input image, the output image is distorted.

Specifying the Interpolation Method

By default, imresize uses nearest-neighbor interpolation to determine the values of pixels in the output image, but you can specify other interpolation methods. This table lists the supported interpolation methods in order of complexity. See "Interpolation" on page 5-3 for more information about these methods.

Argument Value	Interpolation Method
'nearest'	Nearest-neighbor interpolation (the default)
'bilinear'	Bilinear interpolation
'bicubic'	Bicubic interpolation

In this example, imresize uses the bilinear interpolation method.

Y = imresize(X,[100 150],'bilinear')

Using Filters to Prevent Aliasing

Reducing the size of an image can introduce artifacts, such as aliasing, in the output image because information is always lost when you reduce the size of an image. Aliasing appears as ripple patterns (called moiré patterns) in the output image.

When you reduce the size of the image using either bilinear or bicubic interpolation, imresize automatically applies a lowpass filter to the image before interpolation, to limit the impact of aliasing on the output image. You can specify the size of this filter or specify a different filter.

Note Even with lowpass filtering, resizing can introduce artifacts, because information is always lost when you reduce the size of an image.

The imresize function does not apply a lowpass filter if nearest-neighbor interpolation is used. Nearest-neighbor interpolation is primarily used for indexed images, and lowpass filtering is not appropriate for these images.

You can also specify a filter of your own creation. For more information about specifying a filter, see the reference page for imresize.

Image Rotation

To rotate an image, use the imrotate function. imrotate accepts two primary arguments:

- The image to be rotated
- The rotation angle

You specify the rotation angle in degrees. If you specify a positive value, imrotate rotates the image counterclockwise; if you specify a negative value, imrotate rotates the image clockwise. This example rotates the image I 35 degrees in the counterclockwise direction.

```
J = imrotate(I,35);
```

As optional arguments to imrotate, you can also specify

- The interpolation method
- The size of the output image

Specifying the Interpolation Method


By default, imrotate uses nearest-neighbor interpolation to determine the value of pixels in the output image, but you can specify other interpolation methods. This table lists the supported interpolation methods in order of complexity. See "Interpolation" on page 5-3 for more information about these methods.


Argument Value	Interpolation Method
'nearest'	Nearest-neighbor interpolation (the default)
'bilinear'	Bilinear interpolation
'bicubic'	Bicubic interpolation

For example, these commands rotate an image 35° counterclockwise and use bilinear interpolation.

```
I = imread('circuit.tif');
J = imrotate(I,35,'bilinear');
imshow(I)
```

figure, imshow(J)





Specifying the Size of the Output Image

By default, imrotate creates an output image large enough to include the entire original image. Pixels that fall outside the boundaries of the original image are set to 0 and appear as a black background in the output image. If you specify the text string 'crop' as an argument, imrotate crops the output image to be the same size as the input image. (See the reference page for imrotate for an example of cropping.)

Image Cropping


To extract a rectangular portion of an image, use the imcrop function. imcrop accepts two primary arguments:

- The image to be cropped
- The coordinates of a rectangle that defines the crop area

If you call imcrop without specifying the crop rectangle, you can specify the crop rectangle interactively. In this case, the cursor changes to crosshairs when it is over the image. Position the crosshairs over a corner of the crop region and press and hold the left mouse button. When you drag the crosshairs over the image you specify the rectangular crop region. imcrop draws a rectangle around the area you are selecting. When you release the mouse button, imcrop creates a new image from the selected region.

In this example, you display an image and call imcrop. The imcrop function displays the image in a figure window and waits for you to draw the cropping rectangle on the image. In the figure, the rectangle you select is shown in red. The example then calls imshow to view the cropped image.

```
imshow circuit.tif
I = imcrop;
imshow(I);
```





Performing General Spatial Transformations

To perform general two-dimensional (2-D) spatial transformations, use the imtransform function. (For information about performing advanced transformations, see "Advanced Spatial Transformation Techniques" on page 5-13.)

The imtransform function accepts two primary arguments:

- The image to be transformed
- A spatial transformation structure, called a TFORM, that specifies the type of transformation you want to perform

Specifying the Transformation Type

You specify the type of transformation you want to perform in a TFORM structure. There are two ways to create a TFORM structure:

- Using the maketform function
- Using the cp2tform function

Using maketform

When you use the maketform function, you can specify the type of transformation you want to perform. The following table lists the types of transformations maketform supports in alphabetical order.

Transformation	Description
'affine'	Transformation that can include translation, rotation, scaling, stretching, and shearing. Straight lines remain straight, and parallel lines remain parallel, but rectangles might become parallelograms.
'box'	Special case of an affine transformation where each dimension is shifted and scaled independently.
'composite'	Composition of two or more transformations.

Transformation	Description
'custom'	User-defined transformation, providing the forward and/or inverse functions that are called by imtransform.
'projective'	Transformation in which straight lines remain straight but parallel lines converge toward vanishing points. (The vanishing points can fall inside or outside the image — even at infinity.)

The 'custom' and 'composite' capabilities of maketform allow a virtually limitless variety of spatial transformations to be used with imtransform and/or tformarray.

Using cp2tform

You use cp2tform to create the TFORM when you want to perform a transformation that requires fitting of data points, such as a polynomial transformation. Chapter 6, "Image Registration," explains how to use the cp2tform function to fit a 2-D transformation to a set of control points selected in a pair of images.

Note When used with imtransform, TFORM structures must define a 2-D spatial transformation. If an image contains more than two dimensions, such as an RGB image, the same 2-D transformation is automatically applied to all 2-D planes along the higher dimensions. To define an n-dimensional transformation, use the tformarray function.

Performing the Transformation

Once you define the transformation in a TFORM struct, you can perform the transformation by calling imtransform.

For example, this code uses imtransform to perform a projective transformation of a checkerboard image.

```
I = checkerboard(20,1,1);
figure; imshow(I)
T = maketform('projective',[1 1; 41 1; 41 41; 1 41],...
              [5 5; 40 5; 35 30; -10 30]);
R = makeresampler('cubic', 'circular');
K = imtransform(I,T,R,'Size',[100 100],'XYScale',1);
figure, imshow(K)
```





Original image

Transformed imaae

The imtransform function options let you control many aspects of the transformation. For example, note how the transformed image appears to contain multiple copies of the original image. This is accomplished by using the 'Size' option, to make the output image larger than the input image, and then specifying a padding method that extends the input image by repeating the pixels in a circular pattern. The Image Processing Toolbox Image Transformation demos provide more examples of using the imtransform function, and related functions, to perform different types of spatial transformations.

Advanced Spatial Transformation Techniques

The following functions, when used in combination, provide a vast array of options for defining and working with 2-D, N-D, and mixed-D spatial transformations:

- maketform
- fliptform

- tformfwd
- tforminv
- findbounds
- makeresampler
- tformarray
- imtransform

The imtransform, findbounds, and tformarray functions use the tformfwd and tforminv functions internally to encapsulate the forward transformations needed to determine the extent of an output image or array and/or to map the output pixels/array locations back to input locations. You can use tformfwd and tforminv to explore the geometric effects of a transformation by applying them to points and lines and plotting the results. They support a consistent handling of both image and pointwise data.

The previous example, "Performing the Transformation" on page 5-13, used the makeresampler function with a standard interpolation method. You can also use it to obtain special effects or custom processing. For example, you could specify your own separable filtering/interpolation kernel, build a custom resampler around the MATLAB interp2 or interp3 functions, or even implement an advanced antialiasing technique.

And, as noted, you can use tformarray to work with arbitrary-dimensional array transformations. The arrays do not even need to have the same dimensions. The output can have either a lower or higher number of dimensions than the input.

For example, if you are sampling 3-D data on a 2-D slice or manifold, the input array might have a lower dimensionality. The output dimensionality might be higher, for example, if you combine multiple 2-D transformations into a single 2-D to 3-D operation.

Image Registration

This chapter describes the image registration capabilities of the Image Processing Toolbox. Image registration is the process of aligning two or more images of the same scene. Image registration is often used as a preliminary step in other image processing applications.

Terminology (p. 6-2)	Provides definitions of image processing terms used in this section
Registering an Image (p. 6-4)	Steps you through an example of the image registration process
Types of Supported Transformations (p. 6-12)	Lists the types of supported transformations
Selecting Control Points (p. 6-14)	Describes how to use the Control Point Selection Tool (cpselect) to select control points in pairs of images
Using Correlation to Improve Control Points (p. 6-31)	Describes how to use the cpcorr function to fine-tune your control point selections

Terminology

An understanding of the following terms will help you to use this chapter.

Term	Definition
aligned image	Output image after registration has been performed. The output image is derived by applying a transformation to the input image (see below) that brings it into alignment with the base image (see below).
base image	Image against which you compare the image to be registered. It is also often called the <i>reference</i> image.
control point pairs	Matching locations, also referred to as <i>landmarks</i> , in the input image and the base image.
distortion	Differences in one image as compared to another of the same subject. These differences might have occurred as a result of terrain relief and other changes in perspective when imaging the same scene from different viewpoints. Lens and other internal sensor distortions, or differences between sensors and sensor types, can also cause distortion.
global transformation	Transformation in which a single mathematical expression applies to an entire image.
input image	Image that you want to register. It is often called the <i>observed</i> image.

Term	Definition
local transformation	Transformation in which different mathematical expressions (usually differing in parameters rather than form) apply to different regions within an image.
spatial transformation	Mapping of locations of points in one image to new locations in another image.

6

Registering an Image

Image registration is the process of aligning two or more images of the same scene. Typically, one image, called the base image, is considered the reference to which the other images, called input images, are compared. The object of image registration is to bring the input image into alignment with the base image by applying a spatial transformation to the input image.

A spatial transformation maps locations in one image to new locations in another image. (For more details, see Chapter 5, "Spatial Transformations.") Determining the parameters of the spatial transformation needed to bring the images into alignment is key to the image registration process.


Image registration is often used as a preliminary step in other image processing applications. For example, you can use image registration to align satellite images of the earth's surface or images created by different medical diagnostic modalities (MRI and SPECT). After registration, you can compare features in the images to see how a river has migrated, how an area is flooded, or to see if a tumor is visible in an MRI or SPECT image.

Point Mapping

The Image Processing Toolbox provides tools to support point mapping to determine the parameters of the transformation required to bring an image into alignment with another image. In point mapping, you pick points in a pair of images that identify the same feature or landmark in the images. Then, a spatial mapping is inferred from the positions of these control points.

Note You might need to perform several iterations of this process, experimenting with different types of transformations, before you achieve a satisfactory result. In some cases, you might perform successive registrations, removing gross global distortions first, and then removing smaller local distortions in subsequent passes.

The following figure provides a graphic illustration of this process. This process is best understood by looking at an example. See "Example: Registering to a Digital Orthophoto" on page 6-5 for an extended example.



Overview of Image Registration Process

Example: Registering to a Digital Orthophoto

This example illustrates the steps involved in performing image registration using point mapping. These steps include:

- 1 Read the images into the MATLAB workspace.
- **2** Specify control point pairs n the images.
- 3 Save the control point pairs.

6

- **4** Fine-tune the control points using cross-correlation. (This is an optional step.)
- **5** Specify the type of transformation to be used and infer its parameters from the control point pairs.
- **6** Transform the unregistered image to bring it into alignment.

To illustrate this process, the example registers a digital aerial photograph to a digital orthophoto covering the same area. Both images are centered on the business district of West Concord, Massachusetts.

The aerial image is geometrically uncorrected: it includes camera perspective, terrain and building relief, and internal (lens) distortions, and it does not have any particular alignment or registration with respect to the earth.

The orthophoto, supplied by the Massachusetts Geographic Information System (MassGIS), has been orthorectified to remove camera, perspective, and relief distortions (via a specialized image transformation process). It is also georegistered (and geocoded)—the columns and rows of the digital orthophoto image are aligned to the axes of the Massachusetts State Plane coordinate system, each pixel center corresponds to a definite geographic location, and every pixel is 1 meter square in map units.

Step 1: Read the Images into MATLAB

In this example, the base image is westconcordorthophoto.png, the MassGIS georegistered orthophoto. It is a panchromatic (grayscale) image. The image to be registered is westconcordaerial.png, a digital aerial photograph supplied by mPower3/Emerge, and is a visible-color RGB image.

```
orthophoto = imread('westconcordorthophoto.png');
figure, imshow(orthophoto)
unregistered = imread('westconcordaerial.png');
figure, imshow(unregistered)
```

You do not have to read the images into the MATLAB workspace. The cpselect function accepts file specifications for grayscale images. However, if you want to use cross-correlation to tune your control point positioning, the images must be in the workspace.





Aerial Photo Image

Image Courtesy of mPower3/Emerge

Orthophoto Image

Image Courtesy of MassGIS

Step 2: Choose Control Points in the Images

The toolbox provides an interactive tool, called the Control Point Selection Tool, that you can use to pick pairs of corresponding control points in both images. Control points are landmarks that you can find in both images, like a road intersection, or a natural feature.


To start this tool, enter cpselect at the MATLAB prompt, specifying as arguments the input and base images.

Note The unregistered image is an RGB image. Because the Control Point Selection Tool only accepts grayscale images, the example passes only one plane of the color image to cpselect.

cpselect(unregistered(:,:,1),orthophoto)

6

The cpselect function displays two views of both the input image and the base image in which you can pick control points by pointing and clicking. For more information, see "Selecting Control Points" on page 6-14. This figure shows the Control Point Selection Tool with four pairs of control points selected. The number of control point pairs you pick is at least partially determined by the type of transformation you want to perform (specified in Step 5). See "Types of Supported Transformations" on page 6-12 for information about the minimum number of points required by each transformation.



Step 3: Save the Control Point Pairs to the MATLAB Workspace

In the Control Point Selection Tool, click the **File** menu and choose the **Save Points to Workspace** option. See "Saving Control Points" on page 6-29 for more information.

For example, the Control Point Selection Tool returns the following set of control points in the input image. These values represent spatial coordinates; the left column are *x*-coordinates, the right column are *y*-coordinates.

```
input_points =
  120.7086   93.9772
  319.2222   78.9202
  127.9838   291.6312
  352.0729   281.1445
```

Step 4: Fine-Tune the Control Point Pair Placement

This is an optional step that uses cross-correlation to adjust the position of the control points you selected with cpselect. See "Using Correlation to Improve Control Points" on page 6-31 for more information.

Note cpcorr can only adjust points for images that are the same scale and have the same orientation. Because the Concord image is rotated in relation to the base image, cpcorr cannot tune the control points. When it cannot tune the points, cpcorr returns the input points unmodified.

Step 5: Specify the Type of Transformation and Infer Its Parameters

In this step, you pass the control points to the cp2tform function that determines the parameters of the transformation needed to bring the image into alignment. cp2tform is a data-fitting function that determines the transformation based on the geometric relationship of the control points. cp2tform returns the parameters in a geometric transformation structure, called a TFORM structure.

When you use cp2tform, you must specify the type of transformation you want to perform. The cp2tform function can infer the parameters for five types of

transformations. You must choose which transformation will correct the type of distortion present in the input image. See "Types of Supported" Transformations" on page 6-12 for more information. Images can contain more than one type of distortion.

The predominant distortion in the aerial image of West Concord (the input image) results from the camera perspective. Ignoring terrain relief, which is minor in this area, image registration can correct for this using a projective transformation. The projective transformation also rotates the image into alignment with the map coordinate system underlying the base digital orthophoto image. (Given sufficient information about the terrain and camera, you could correct these other distortions at the same time by creating a composite transformation with maketform. See "Performing General Spatial Transformations" on page 5-11 for more information.)

```
mytform = cp2tform(input points,base points,'projective');
```

Step 6: Transform the Unregistered Image

As the final step in image registration, transform the input image to bring it into alignment with the base image. You use imtransform to perform the transformation, passing it the input image and the TFORM structure, which defines the transformation. imtransform returns the transformed image. For more information about using imtransform, see Chapter 5, "Spatial Transformations."

```
registered = imtransform(unregistered, mytform)
```

Note imtransform applies the transformation defined in mytform, which is based on control points picked in only one plane of the RGB image, to all three planes of the input image.

Compare the transformed image to the base image to see how the registration came out. $\,$







Orthophoto Image



Types of Supported Transformations

The cp2tform function can infer the parameters for six types of transformations. This table lists the transformations in order of complexity, with examples of each type of distortion.

The first four transformations, 'linear conformal', 'affine', 'projective', and 'polynomial' are global transformations. In these transformations, a single mathematical expression applies to an entire image. The last two transformations, 'piecewise linear' and 'lwm' (local weighted mean), are local transformations. In these transformations, different mathematical expressions apply to different regions within an image.

When exploring how different transformations affect the images you are working with, try the global transformations first. If these transformations are not satisfactory, try the local transformations: the piecewise linear transformation first and then the local weighted mean transformation.

Transformation Type	Description	Minimum Control Points	Example
'linear conformal'	Use this transformation when shapes in the input image are unchanged, but the image is distorted by some combination of translation, rotation, and scaling. Straight lines remain straight, and parallel lines are still parallel.	2 pairs	32 * \$*
'affine'	Use this transformation when shapes in the input image exhibit shearing. Straight lines remain straight, and parallel lines remain parallel, but rectangles become parallelograms.	3 pairs	<i>***</i>

'projective'	Use this transformation when the scene appears tilted. Straight lines remain straight, but parallel lines converge toward vanishing points (which might or might not fall within the image).	4 pairs	**
'polynomial'	Use this transformation when objects in the image are curved. The higher the order of the polynomial, the better the fit, but the result can contain more curves than the base image.	6 pairs (order 2) 10 pairs (order 3) 16 pairs (order 4)	32 27
'piecewise linear'	Use this transformation when parts of the image appear distorted differently.	4 pairs	88
'lwm'	Use this transformation (local weighted mean), when the distortion varies locally and piecewise linear is not sufficient.	6 pairs (12 pairs recommended)	88



Selecting Control Points

The toolbox includes an interactive tool that enables you to specify control points in the images you want to register. The tool displays the images side by side. When you are satisfied with the number and placement of the control points, you can save the control points.


Using the Control Point Selection Tool

To specify control points in a pair of images you want to register, use the Control Point Selection Tool, cpselect. The tool displays the image you want to register, called the *input* image, next to the image you want to compare it to, called the *base* image or *reference* image.

Specifying control points is a four-step process:

- 1 Start the tool, specifying the input image and the base image.
- 2 View the images, looking for visual elements that you can identify in both images. cpselect provides many ways to navigate around the image, panning and zooming to view areas of the image in more detail.
- **3** Specify matching control point pairs in the input image and the base image.
- **4** Save the control points in the MATLAB workspace.

The following figure shows the default appearance of the tool when you first start it.



Control Point Selection Tool

Starting the Control Point Selection Tool

To use the Control Point Selection Tool, enter the cpselect command at the MATLAB prompt. As arguments, specify the image you want to register (the input image), and the image you want to compare it to (the base image).

To illustrate, this code fragment reads an image into a variable, moon_base, in the MATLAB workspace. It then creates another version of the image with a



deliberate size distortion, called moon_input. This is the image that needs registration to remove the size distortion. The code then starts the cpselect tool, specifying the two images.


```
moon_base = imread('moon.tif');
moon_input = imresize(moon_base, 1.2);
cpselect(moon_input, moon_base);
```

The cpselect command has other optional arguments. For example, you can restart a control point selection session by including a cpstruct structure as the third argument. For more information about restarting sessions, see "Saving Control Points" on page 6-29. For complete details, see the cpselect reference page.

Default Views of the Images

When the Control Point Selection Tool starts, it contains four image display windows. The top two windows are called the **Detail** windows. These windows show a closeup view of a portion of the images you are working with. The input image is on the left and the base image is on the right. The two windows at the bottom of the interface are called the **Overview** windows. These windows show the images in their entirety, at the largest scale that fits the window. The input overview image is on the left and the base overview image is on the right.

Superimposed on the image in the **Overview** windows is a rectangle, called the detail rectangle. This rectangle defines the part of the image that is visible in the **Detail** window. By default, at startup, the detail rectangle covers one quarter of the entire image and is positioned over the center of the image.



Viewing the Images

By default, cpselect displays the entire base and input images in the **Overview** windows and displays a closeup view of a portion of these images in the **Detail** windows. However, to find visual elements that are common to both images, you might want to change the section of the image displayed in the detail view or zoom in on a part of the image to view it in more detail. The following sections describe the different ways to change your view of the images:

- "Using Scroll Bars to View Other Parts of an Image" on page 6-18
- \bullet "Using the Detail Rectangle to Change the View" on page 6-18
- \bullet "Panning the Image Displayed in the Detail Window" on page 6-18
- "Zooming In and Out on an Image" on page 6-19
- \bullet "Specifying the Magnification of the Images" on page 6-20

 "Locking the Relative Magnification of the Input and Base Images" on page 6-21

Using Scroll Bars to View Other Parts of an Image

To view parts of an image that are not visible in the **Detail** or **Overview** windows, use the scroll bars provided in each window.

As you scroll the image in the **Detail** window, note how the detail rectangle moves over the image in the **Overview** window. The position of the detail rectangle always shows the portion of the image in the **Detail** window.

Using the Detail Rectangle to Change the View

To get a closer view of any part of the image, move the detail rectangle in the Overview window over that section of the image. cpselect displays that section of the image in the **Detail** window at a higher magnification than the overview window.

To move the detail rectangle,

- 1 Click the Default Cursor button | in the toolbar.
- **2** Move the pointer into the detail rectangle. The cursor changes to the fleur shape, \clubsuit .
- **3** Press and hold the mouse button to drag the detail rectangle anywhere on the image.

Note As you move the detail rectangle over the image in the **Overview** window, the view of the image displayed in the **Detail** window changes.

Panning the Image Displayed in the Detail Window

To change the section of the image displayed in the **Detail** window, use the pan tool to move the image in the window.

To use the pan tool,

1 Click the Drag Images to Pan button | in the toolbar.

- 2 Move the pointer over the image in the **Detail** window. The cursor changes to the fleur shape, ...
- 3 Press and hold the mouse button and drag the image in the **Detail** window.


Note As you move the image in the **Detail** window, the detail rectangle in the **Overview** window moves.

Zooming In and Out on an Image

To enlarge an image to get a closer look or shrink an image to see the whole image in context, use the Zoom buttons on the button bar. (You can also zoom in or out on an image by changing the magnification. See "Specifying the Magnification of the Images" on page 6-20 for more information.)

To zoom in or zoom out on the base or input images,

1 Click the appropriate magnifying glass button.



2 Move the pointer over the image you want to zoom in or out on. The cursor changes to crosshairs, +.

You can zoom in or out on either the input or the base images, in either the **Detail** or **Overview** windows. To keep the relative magnifications of the base and input images synchronized, click the **Lock ratio** check box. See "Locking the Relative Magnification of the Input and Base Images" on page 6-21 for more information.

Note If you zoom in close on the image displayed in the **Overview** window, the detail rectangle might no longer be visible.

You can use the zoom tool in two ways:

- Position the cursor over a location in the image and click the mouse. With each click, cpselect changes the magnification of the image by a preset amount. (See "Specifying the Magnification of the Images" on page 6-20 for a list of some of these magnifications.) cpselect centers the new view of the image on the spot where you clicked.
- Alternatively, you can position the cursor over a location in the image and, while pressing and holding the mouse button, draw a rectangle defining the area you want to zoom in or out on. cpselect magnifies the image so that the chosen section fills the **Detail** window, cpselect resizes the detail rectangle in the **Overview** window as well.

Note When you zoom in or out on an image, notice how the magnification value changes.

Specifying the Magnification of the Images


To enlarge an image to get a closer look or to shrink an image to see the whole image in context, use the magnification edit box. (You can also use the Zoom buttons to enlarge or shrink an image. See "Zooming In and Out on an Image" on page 6-19 for more information.)

To change the magnification of an image,

1 Move the cursor into the magnification edit box of the window you want to change. The cursor changes to the text entry cursor.

Note Each **Detail** window and **Overview** window has its own magnification edit box.


2 Type a new value in the magnification edit box and press **Enter**, or click the menu associated with the edit box and choose from a list of preset magnifications. cpselect changes the magnification of the image and displays the new view in the appropriate window.



Locking the Relative Magnification of the Input and Base Images

To keep the relative magnification of the input and base images automatically synchronized in the **Detail** or **Overview** windows, click the **Lock Ratio** check box. The two **Detail** windows and the two **Overview** windows each have their own **Lock ratio** check boxes.

When the **Lock Ratio** check box is selected, cpselect changes the magnification of *both* the input and base images when you zoom in or out on either one of the images or specify a magnification value for either of the images.



6

Specifying Matching Control Point Pairs

The primary function of the Control Point Selection Tool is to enable you to pick control points in the image to be registered, the input image, and the image to which you are comparing it, the base image. When you start cpselect, the point selection tool is enabled, by default.

You specify control points by pointing and clicking in the input and base images, in either the **Detail** or the **Overview** windows. Each point you specify in the input image must have a match in the base image. The following sections describe the ways you can use the Control Point Selection Tool to choose control point pairs:

- "Picking Control Point Pairs Manually"
- "Using Control Point Prediction" on page 6-24

This section also describes how to move control points after you've created them and how to delete control points.

Picking Control Point Pairs Manually

To specify a pair of control points in your images,


- 1 Click the Control Point Selection button ⊕ . Control point selection mode is active by default.
- 2 Position the cursor over a feature you have visually selected in any of the images displayed. The cursor changes to a pointing finger, .
 - You can pick control points in either of the **Detail** windows, input or base, or in either of the **Overview** windows, input or base. You also can work in either direction: input-to-base image, or base-to-input image.
- 3 Click the mouse button. cpselect places a control point symbol at the position you specified, in both the **Detail** window and the **Overview** window. (The appearance of the control point symbol indicates its current state. Initially, control points are in an active, unmatched state. See "Control Point States" on page 6-26 for more information.

Note Depending on where in the image you pick control points, the symbol for the point might be visible in the **Overview** window, but not in the **Detail** window.

- **4** To create the match for this control point, move the cursor into the corresponding **Detail** or **Overview** window. For example, if you started in an input window, move the cursor to a base window.
- 5 Click the mouse button. cpselect places a control point symbol at the position you specified, in both the **Detail** and **Overview** windows. Because this control point completes a pair, the appearance of this symbol indicates an active, matched state. Note that the appearance of the first control point you selected (in step 3) also changes to an active, matched state.

You pick pairs of control points by moving from a view of the input image to a view of the base image, or vice versa. You can pick several control points in one view of the image, and then move to the corresponding window to locate their matches. To match an unmatched control point, select it to make it active, and then pick a point in the corresponding view window. When you select a match for a control point, the symbols for both points change to indicate their matched state. You can move or delete control points after you create them.

The following figure illustrates control points in several states.




Using Control Point Prediction

Instead of picking matching control points by moving the cursor between corresponding **Detail** or **Overview** windows, you can let the Control Point Selection Tool estimate the match for the control points you specify, automatically. The Control Point Selection Tool determines the position of the matching control point based on the geometric relationship of the previously selected control points.

Note By default, the Control Point Selection Tool does not include predicted points in the set of valid control points returned in input_points or base_points. To include predicted points, you must accept them by selecting the points and fine-tuning their position with the cursor. When you move a predicted point, the Control Point Selection Tool changes the symbol to indicate that it has changed to a standard control point. For more information, see "Moving Control Points" on page 6-27.

To illustrate point prediction, this figure shows four control points selected in the input image, where the points form the four corners of a square. (The control points selections in the figure do not attempt to identify any landmarks in the image.) The figure shows the picking of a fourth point, in the left window, and the corresponding predicted point in the right window. Note how the Control Point Selection Tool places the predicted point at the same location relative to the other control points, forming the bottom right corner of the square.



Note Because the Control Point Selection Tool predicts control point locations based on the locations of the previous control points, you cannot use point prediction until you have a minimum of two pairs of matched points. Until this minimum is met, the Control Point Prediction button is disabled.

6


To use control point prediction,

- 1 Click the Control Point Prediction button ⊕⊕ |.

You can pick control points in either of the **Detail** windows, input or base, or in either of the **Overview** windows, input or base. You also can work in either direction: input-to-base image or base-to-input image.

3 Click either mouse button. The Control Point Selection Tool places a control point symbol at the position you specified and places another control point symbol for a matching point in all the other windows. The symbol for the predicted point contains the letter "P," indicating that it's a predicted control point.

This figure illustrates predicted points in active unmatched, matched, and predicted states. For a complete description of all point states, see "Control Point States" on page 6-26.



Control Point States

The appearance of control point symbols indicates their current state. When you first pick a control point, its state is active and unmatched. When you pick

the match for a control point, the appearance of both symbols changes to indicate their matched status.

This table lists all the possible control point states with their symbols. cpselect displays this list in a separate window called a **Legend**. The Legend is visible by default, but you can control its visibility using the **Legend** option from the **View** menu.

Control Point States

Symbol	State	Description
	Active unmatched	The point is currently selected but does not have a matching point. This is the initial state of most points.
	Active matched	The point is currently selected and has a matching point.
	Active predicted	The point is a predicted point. If you move its position, the point changes to active matched state.
•	Unmatched	The point is not selected and it is unmatched. You must select it before you can create its matching point.
+	Matched	The point has a matching point.
•	Predicted	This point was added by cpselect during point prediction.

Moving Control Points

To move a control point,

- Click the Control Point Selection button or the Default Cursor button
- 2 Position the cursor over the control point you want to move.
- **3** Press and hold the mouse button and drag the control point. The state of the control point changes to active when you move it.




If you move a predicted control point, the state of the control point changes to a regular (nonpredicted) control point.

Deleting Control Points


To delete a control point, and optionally its matching point,

- 1 Click the Control Point Selection button ⊕ or the Default Cursor button .
- **2** Click the control point you want to delete. Its state changes to active. If the control point has a match, both points become active.
- **3** Delete the point (or points) using one of these methods:
 - Pressing the **Backspace** key
 - Pressing the **Delete** key
 - Choosing one of the delete options from the **Edit** menu
 Using this menu you can delete individual points or pairs of matched points, in the input or base images.



Undoing and Redoing Control Point Selections

You can undo a deletion or series of deletions using the **Undo Delete** option on the cpselect **Edit** menu.




After undoing a deletion, you can delete the points again using the **Redo** option, also on the **Edit** menu.

Saving Control Points

After you specify control point pairs, you must save them in the MATLAB workspace to make them available for the next step in image registration, processing by cp2tform.

To save control points to the MATLAB workspace,

- 1 Select **File** on the Control Point Selection Tool menu bar.
- **2** Choose the **Save Points to Workspace** option. The Control Point Selection Tool displays this dialog box:



By default, the Control Point Selection Tool saves the *x*-coordinates and *y*-coordinates that specify the locations of the control points you selected in two arrays named input_points and base_points, although you can specify other names. These are *n*-by-2 arrays, where *n* is the number of valid control point pairs you selected. For example, this is an example of the input_points array if you picked four pairs of control points. The values in the left column represent the *x*-coordinates; the values in the right column represent the *y*-coordinates.


```
input_points =
215.6667   262.3333
225.7778   311.3333
156.5556   340.1111
270.8889   368.8889
```

Whenever you exit the Control Point Selection Tool, it asks if you want to save your control points.



Saving Your Control Point Selection Session

To save the current state of the Control Point Selection Tool, select the Structure with all points check box in the Save Points to Workspace dialog box.



cpstruct =

This option saves the positions of all the control points you specified and their current states in a costruct structure.

```
inputPoints: [4x2 double]
    basePoints: [4x2 double]
inputBasePairs: [4x2 double]
           ids: [4x1 double]
  inputIdPairs: [4x2 double]
```

baseIdPairs: [4x2 double] isInputPredicted: [4x1 double] isBasePredicted: [4x1 double]

You can use the costruct to restart a control point selection session at the point where you left off.

This option is useful if you are picking many points over a long time and want to preserve unmatched and predicted points when you resume work. The Control Point Selection Tool does not include unmatched and predicted points in the input points and base points arrays.

To extract the arrays of valid control point coordinates from a cpstruct, use the cpstruct2pairs function.

Using Correlation to Improve Control Points

You might want to fine-tune the control points you selected using cpselect. Using cross-correlation, you can sometimes improve the points you selected by eye using the Control Point Selection Tool.

To use cross-correlation, pass sets of control points in the input and base images, along with the images themselves, to the cpcorr function.

```
input_pts_adj = cpcorr(input_points, base_points, input, base);
```

The cpcorr function defines 11-by-11 regions around each control point in the input image and around the matching control point in the base image, and then calculates the correlation between the values at each pixel in the region. Next, the cpcorr function looks for the position with the highest correlation value and uses this as the optimal position of the control point. The cpcorr function only moves control points up to 4 pixels based on the results of the cross-correlation.

Note Features in the two images must be at the same scale and have the same orientation. They cannot be rotated relative to each other.

If cpcorr cannot correlate some of the control points, it returns their values in input_points unmodified.

Linear Filtering and Filter Design

The Image Processing Toolbox provides a number of functions for designing and implementing two-dimensional linear filters for image data. This chapter describes these functions and how to use them effectively.

Terminology (p. 7-2) Provides definitions of image processing terms used in

this section

Linear Filtering (p. 7-4) Provides an explanation of linear filtering and how it is

implemented in the toolbox. This topic describes filtering

in terms of the spatial domain, and is accessible to

anyone doing image processing.

Filter Design (p. 7-17) Discusses designing two-dimensional finite impulse

response (FIR) filters. This section assumes you are

familiar with working in the frequency domain.

Terminology

An understanding of the following terms will help you to use this chapter. Note that this table includes brief definitions of terms related to filter design; a detailed discussion of these terms and the theory behind filter design is outside the scope of this user's guide.

Term	Definition
convolution	Neighborhood operation in which each output pixel is a weighted sum of neighboring input pixels. The weights are defined by the convolution kernel. Image processing operations implemented with convolution include smoothing, sharpening, and edge enhancement.
convolution kernel	Matrix of weights used to perform convolution. A convolution kernel is a correlation kernel that has been rotated 180 degrees.
correlation	Neighborhood operation in which each output pixel is a weighted sum of neighboring input pixels. The weights are defined by the correlation kernel. Correlation is closely related mathematically to convolution.
correlation kernel	Matrix of weights used to perform correlation. The filter design functions in the Image Processing Toolbox return correlation kernels. A correlation kernel is a convolution kernel that has been rotated 180 degrees.
FIR filter	Filter whose response to a single point, or impulse, has finite extent. FIR stands for finite impulse response. An FIR filter can be implemented using convolution. All filter design functions in the Image Processing Toolbox return FIR filters.
frequency response	Mathematical function describing the gain of a filter in response to different input frequencies.
neighborhood operation	Operation in which each output pixel is computed from a set of neighboring input pixels. Convolution, dilation, and median filtering are examples of neighborhood operations.

Term	Definition
ripples	Oscillations around a constant value. The frequency response of a practical filter often has ripples where the frequency response of an ideal filter is flat.
window method	Filter design method that multiples the ideal impulse response by a window function, which tapers the ideal impulse response. The resulting filter's frequency response approximates a desired frequency response.

Linear Filtering

Filtering is a technique for modifying or enhancing an image. For example, you can filter an image to emphasize certain features or remove other features.

Filtering is a *neighborhood operation*, in which the value of any given pixel in the output image is determined by applying some algorithm to the values of the pixels in the neighborhood of the corresponding input pixel. A pixel's neighborhood is some set of pixels, defined by their locations relative to that pixel. (See Chapter 14, "Neighborhood and Block Operations," for a general discussion of neighborhood operations.)

Linear filtering is filtering in which the value of an output pixel is a linear combination of the values of the pixels in the input pixel's neighborhood.

This section discusses linear filtering in MATLAB and the Image Processing Toolbox. It includes

- A description of filtering, using convolution and correlation
- A description of how to perform filtering using the imfilter function
- A discussion about using predefined filter types

See "Filter Design" on page 7-17 for information about how to design filters.

Convolution

Linear filtering of an image is accomplished through an operation called *convolution*. In convolution, the value of an output pixel is computed as a weighted sum of neighboring pixels. The matrix of weights is called the *convolution kernel*, also known as the *filter*.

For example, suppose the image is

```
A = [17]
                        15
     23
                7
                   14
                        16
             13
                   20
                        22
     10
          12
               19
                   21
                         3
              25
     11
          18
                         9]
```

and the convolution kernel is


$$h = [8 \quad 1 \quad 6 \\ 3 \quad 5 \quad 7 \\ 4 \quad 9 \quad 2]$$

The following figure shows how to compute the (2,4) output pixel using these steps:

- **1** Rotate the convolution kernel 180 degrees about its center element.
- **2** Slide the center element of the convolution kernel so that it lies on top of the (2,4) element of A.
- **3** Multiply each weight in the rotated convolution kernel by the pixel of A underneath.
- **4** Sum the individual products from step 3.

Hence the (2,4) output pixel is

$$1 \cdot 2 + 8 \cdot 9 + 15 \cdot 4 + 7 \cdot 7 + 14 \cdot 5 + 16 \cdot 3 + 13 \cdot 6 + 20 \cdot 1 + 22 \cdot 8 = 575$$



Computing the (2,4) Output of Convolution


Correlation

The operation called *correlation* is closely related to convolution. In correlation, the value of an output pixel is also computed as a weighted sum of neighboring pixels. The difference is that the matrix of weights, in this case called the *correlation kernel*, is not rotated during the computation. The following figure shows how to compute the (2,4) output pixel of the correlation of A, assuming h is a correlation kernel instead of a convolution kernel, using these steps:

- 1 Slide the center element of the correlation kernel so that lies on top of the (2,4) element of A.
- **2** Multiply each weight in the correlation kernel by the pixel of A underneath.
- **3** Sum the individual products from step 3.

The (2,4) output pixel from the correlation is

$$1 \cdot 8 + 8 \cdot 1 + 15 \cdot 6 + 7 \cdot 3 + 14 \cdot 5 + 16 \cdot 7 + 13 \cdot 4 + 20 \cdot 9 + 22 \cdot 2 = 585$$




Computing the (2,4) Output of Correlation

Filtering Using imfilter

Filtering of images, either by correlation or convolution, can be performed using the toolbox function imfilter. This example filters an image with a 5-by-5 filter containing equal weights. Such a filter is often called an *averaging filter*.

```
I = imread('coins.png');
h = ones(5,5) / 25;
I2 = imfilter(I,h);
imshow(I), title('Original Image');
figure, imshow(I2), title('Filtered Image')
```





Original Image

Filtered Image

Data Types

The imfilter function handles data types similarly to the way the image arithmetic functions do, as described in "Image Arithmetic Saturation Rules" on page 2-28. The output image has the same data type, or numeric class, as the input image. The imfilter function computes the value of each output pixel using double-precision, floating-point arithmetic. If the result exceeds the range of the data type, the imfilter function truncates the result to that data type's allowed range. If it is an integer data type, imfilter rounds fractional values.

Because of the truncation behavior, you might sometimes want to consider converting your image to a different data type before calling imfilter. In this example, the output of imfilter has negative values when the input is of class double.

Notice that the result has negative values. Now suppose A is of class uint8, instead of double.

```
A = uint8(magic(5));
imfilter(A,h)
ans =
    24
            0
                   0
                                 0
                         14
     5
            0
                   9
                          9
                                 0
     6
            9
                  14
                          9
                                 0
    12
            9
                   9
                          0
                                 0
    18
           14
                   0
                          0
                                 0
```

Since the input to imfilter is of class uint8, the output also is of class uint8, and so the negative values are truncated to 0. In such cases, it might be appropriate to convert the image to another type, such as a signed integer type, single, or double, before calling imfilter.

Correlation and Convolution Options


The imfilter function can perform filtering using either correlation or convolution. It uses correlation by default, because the filter design functions, described in "Filter Design" on page 7-17, and the fspecial function, described in "Using Predefined Filter Types" on page 7-15, produce correlation kernels.

However, if you want to perform filtering using convolution instead, you can pass the string 'conv' as an optional input argument to imfilter. For example:

```
A = magic(5);
h = [-1 \ 0 \ 1]
imfilter(A,h)
                  % filter using correlation
ans =
    24
          -16
                         14
                                -8
                 - 16
     5
          -16
                  9
                          9
                               -14
     6
            9
                  14
                          9
                               -20
    12
            9
                   9
                        -16
                               -21
                                -2
    18
           14
                 -16
                        -16
imfilter(A,h,'conv')
                          % filter using convolution
ans =
   - 24
           16
                  16
                        -14
                                 8
     - 5
           16
                  -9
                         -9
                                14
    -6
           -9
                 -14
                         -9
                                20
    - 12
           -9
                  - 9
                         16
                                21
    - 18
          -14
                  16
                         16
                                 2
```


Boundary Padding Options

When computing an output pixel at the boundary of an image, a portion of the convolution or correlation kernel is usually off the edge of the image, as illustrated in the following figure.



When the Values of the Kernel Fall Outside the Image

The imfilter function normally fills in these off-the-edge image pixels by assuming that they are 0. This is called zero padding and is illustrated in the following figure.



Zero Padding of Outside Pixels

When you filter an image, zero padding can result in a dark band around the edge of the image, as shown in this example.

```
I = imread('eight.tif');
h = ones(5,5) / 25;
I2 = imfilter(I,h);
imshow(I), title('Original Image');
figure, imshow(I2), title('Filtered Image with Black Border')
```






Original Image

Filtered Image with Black Border

To eliminate the zero-padding artifacts around the edge of the image, imfilter offers an alternative boundary padding method called *border replication*. In border replication, the value of any pixel outside the image is determined by replicating the value from the nearest border pixel. This is illustrated in the following figure.



Replicated Boundary Pixels

To filter using border replication, pass the additional optional argument 'replicate' to imfilter.

```
I3 = imfilter(I,h,'replicate');
figure, imshow(I3);
title('Filtered Image with Border Replication')
```



Filtered Image with Border Replication

The imfilter function supports other boundary padding options, such as 'circular' and 'symmetric'. See the reference page for imfilter for details.

Multidimensional Filtering

The imfilter function can handle both multidimensional images and multidimensional filters. A convenient property of filtering is that filtering a three-dimensional image with a two-dimensional filter is equivalent to filtering each plane of the three-dimensional image individually with the same two-dimensional filter. This example shows how easy it is to filter each color plane of a truecolor image with the same filter:

1 Read in an RGB image and display it.

```
rgb = imread('peppers.png');
imshow(rgb);
```



2 Filter the image and display it.

```
h = ones(5,5)/25;
rgb2 = imfilter(rgb,h);
figure, imshow(rgb2)
```



Relationship to Other Filtering Functions

MATLAB has several two-dimensional and multidimensional filtering functions. The function filter2 performs two-dimensional correlation, conv2 performs two-dimensional convolution, and convn performs multidimensional

convolution. Each of these filtering functions always converts the input to double, and the output is always double. These other filtering functions always assume the input is zero padded, and they do not support other padding options.

In contrast, the imfilter function does not convert input images to double. The imfilter function also offers a flexible set of boundary padding options, as described in "Boundary Padding Options" on page 7-10.

Using Predefined Filter Types

The fspecial function produces several kinds of predefined filters, in the form of correlation kernels. After creating a filter with fspecial, you can apply it directly to your image data using imfilter. This example illustrates applying an *unsharp masking* filter to an intensity image. The unsharp masking filter has the effect of making edges and fine detail in the image more crisp.

```
I = imread('moon.tif');
h = fspecial('unsharp');
I2 = imfilter(I,h);
imshow(I), title('Original Image')
figure, imshow(I2), title('Filtered Image')
```







Filtered Image

Filter Design

This section describes working in the frequency domain to design filters. Topics discussed include

- Finite impulse response (FIR) filters, the class of linear filter that the toolbox supports
- The frequency transformation method, which transforms a one-dimensional FIR filter into a two-dimensional FIR filter
- The frequency sampling method, which creates a filter based on a desired frequency response
- The windowing method, which multiplies the ideal impulse response with a window function to generate the filter
- Creating the desired frequency response matrix
- Computing the frequency response of a filter

This section assumes you are familiar with working in the frequency domain. This topic is discussed in many signal processing and image processing textbooks.

Note Most of the design methods described in this section work by creating a two-dimensional filter from a one-dimensional filter or window created using functions from the Signal Processing Toolbox. Although this toolbox is not required, you might find it difficult to design filters in the Image Processing Toolbox if you do not have the Signal Processing Toolbox as well.

FIR Filters

The Image Processing Toolbox supports one class of linear filter, the two-dimensional finite impulse response (FIR) filter. FIR filters have several characteristics that make them ideal for image processing in the MATLAB environment:

- FIR filters are easy to represent as matrices of coefficients.
- Two-dimensional FIR filters are natural extensions of one-dimensional FIR filters.

- There are several well-known, reliable methods for FIR filter design.
- FIR filters are easy to implement.
- FIR filters can be designed to have linear phase, which helps prevent distortion.

Another class of filter, the infinite impulse response (IIR) filter, is not as suitable for image processing applications. It lacks the inherent stability and ease of design and implementation of the FIR filter. Therefore, this toolbox does not provide IIR filter support.


Frequency Transformation Method


The frequency transformation method transforms a one-dimensional FIR filter into a two-dimensional FIR filter. The frequency transformation method preserves most of the characteristics of the one-dimensional filter, particularly the transition bandwidth and ripple characteristics. This method uses a *transformation matrix*, a set of elements that defines the frequency transformation.

The toolbox function ftrans2 implements the frequency transformation method. This function's default transformation matrix produces filters with nearly circular symmetry. By defining your own transformation matrix, you can obtain different symmetries. (See Jae S. Lim, *Two-Dimensional Signal and Image Processing*, 1990, for details.)

The frequency transformation method generally produces very good results, as it is easier to design a one-dimensional filter with particular characteristics than a corresponding two-dimensional filter. For instance, the next example designs an optimal equiripple one-dimensional FIR filter and uses it to create a two-dimensional filter with similar characteristics. The shape of the one-dimensional frequency response is clearly evident in the two-dimensional response.

```
b = remez(10,[0 0.4 0.6 1],[1 1 0 0]);
h = ftrans2(b);
[H,w] = freqz(b,1,64,'whole');
colormap(jet(64))
plot(w/pi-1,fftshift(abs(H)))
figure, freqz2(h,[32 32])
```






One-Dimensional Frequency Response (left) and Corresponding Two-Dimensional Frequency Response (right)


Frequency Sampling Method

The frequency sampling method creates a filter based on a desired frequency response. Given a matrix of points that define the shape of the frequency response, this method creates a filter whose frequency response passes through those points. Frequency sampling places no constraints on the behavior of the frequency response between the given points; usually, the response ripples in these areas.

The toolbox function fsamp2 implements frequency sampling design for two-dimensional FIR filters. fsamp2 returns a filter h with a frequency response that passes through the points in the input matrix Hd. The example below creates an 11-by-11 filter using fsamp2 and plots the frequency response of the resulting filter. (The freqz2 function in this example calculates the two-dimensional frequency response of a filter. See "Computing the Frequency Response of a Filter" on page 7-23 for more information.)

```
Hd = zeros(11,11); Hd(4:8,4:8) = 1;
[f1,f2] = freqspace(11,'meshgrid');
mesh(f1,f2,Hd), axis([-1 1 -1 1 0 1.2]), colormap(jet(64))
h = fsamp2(Hd);
```





Desired Two-Dimensional Frequency Response (left) and Actual Two-Dimensional Frequency Response (right)

Notice the ripples in the actual frequency response, compared to the desired frequency response. These ripples are a fundamental problem with the frequency sampling design method. They occur wherever there are sharp transitions in the desired response.

You can reduce the spatial extent of the ripples by using a larger filter. However, a larger filter does not reduce the height of the ripples, and requires more computation time for filtering. To achieve a smoother approximation to the desired frequency response, consider using the frequency transformation method or the windowing method.

Windowing Method

The windowing method involves multiplying the ideal impulse response with a window function to generate a corresponding filter. Like the frequency sampling method, the windowing method produces a filter whose frequency response approximates a desired frequency response. The windowing method, however, tends to produce better results than the frequency sampling method.

The toolbox provides two functions for window-based filter design, fwind1 and fwind2. fwind1 designs a two-dimensional filter by using a two-dimensional


window that it creates from one or two one-dimensional windows that you specify. fwind2 designs a two-dimensional filter by using a specified two-dimensional window directly.

fwind1 supports two different methods for making the two-dimensional windows it uses:

- Transforming a single one-dimensional window to create a two-dimensional window that is nearly circularly symmetric, by using a process similar to rotation
- Creating a rectangular, separable window from two one-dimensional windows, by computing their outer product

The example below uses fwind1 to create an 11-by-11 filter from the desired frequency response Hd. Here, the hamming function from the Signal Processing Toolbox is used to create a one-dimensional window, which fwind1 then extends to a two-dimensional window.

```
Hd = zeros(11,11); Hd(4:8,4:8) = 1;
[f1,f2] = freqspace(11,'meshgrid');
mesh(f1,f2,Hd), axis([-1 1 -1 1 0 1.2]), colormap(jet(64))
h = fwind1(Hd,hamming(11));
figure, freqz2(h,[32 32]), axis([-1 1 -1 1 0 1.2])
```




Desired Two-Dimensional Frequency Response (left) and Actual Two-Dimensional Frequency Response (right)

Creating the Desired Frequency Response Matrix

The filter design functions fsamp2, fwind2, and fwind2 all create filters based on a desired frequency response magnitude matrix. You can create an appropriate desired frequency response matrix using the freqspace function. freqspace returns correct, evenly spaced frequency values for any size response. If you create a desired frequency response matrix using frequency points other than those returned by freqspace, you might get unexpected results, such as nonlinear phase.

For example, to create a circular ideal lowpass frequency response with cutoff at 0.5, use

```
[f1,f2] = freqspace(25,'meshgrid');
Hd = zeros(25,25); d = sqrt(f1.^2 + f2.^2) < 0.5;
Hd(d) = 1;
mesh(f1,f2,Hd)</pre>
```



Ideal Circular Lowpass Frequency Response

Note that for this frequency response, the filters produced by fsamp2, fwind1, and fwind2 are real. This result is desirable for most image processing applications. To achieve this in general, the desired frequency response should be symmetric about the frequency origin (f1 = 0, f2 = 0).


Computing the Frequency Response of a Filter

The freqz2 function computes the frequency response for a two-dimensional filter. With no output arguments, freqz2 creates a mesh plot of the frequency response. For example, consider this FIR filter,

h =[0.1667	0.6667	0.1667
0.6667	-3.3333	0.6667
0.1667	0.6667	0.1667];

This command computes and displays the 64-by-64 point frequency response of h.

freqz2(h)



Frequency Response of a Two-Dimensional Filter

To obtain the frequency response matrix H and the frequency point vectors f1 and f2, use output arguments

$$[H,f1,f2] = freqz2(h);$$

freqz2 normalizes the frequencies f1 and f2 so that the value 1.0 corresponds to half the sampling frequency, or π radians.

For a simple m-by-n response, as shown above, freqz2 uses the two-dimensional fast Fourier transform function fft2. You can also specify vectors of arbitrary frequency points, but in this case freqz2 uses a slower algorithm.

See "Fourier Transform" on page 8-3 for more information about the fast Fourier transform and its application to linear filtering and filter design.

Transforms

The usual mathematical representation of an image is a function of two spatial variables: f(x, y). The value of the function at a particular location (x, y) represents the intensity of the image at that point. The term transform refers to an alternative mathematical representation of an image.

This chapter defines several important transforms and shows examples of their application to image processing.

m · 1 (0.0)	TO 11 1 C 11 C 1
Terminology (p. 8-2)	Provides definitions of image processing terms used in
10111111010g,y (p. 0 2)	1 To vides definitions of image processing terms asea in

this section

Fourier Transform (p. 8-3) Defines the Fourier transform and some of its

applications in image processing

Discrete Cosine Transform (p. 8-17) Describes the discrete cosine transform (DCT) of an

image and its application, particularly in image

compression

Radon Transform (p. 8-21) Describes how the Image Processing Toolbox radon

function computes *projections* of an image matrix along

specified directions

Fan-Beam Projection Data (p. 8-36) Describes how the Image Processing Toolbox radon

function computes *projections* of an image matrix along

specified directions

Terminology

An understanding of the following terms will help you to use this chapter. Note that this table includes brief definitions of terms related to transforms; a detailed discussion of these terms and the theory behind transforms is outside the scope of this user's guide.

Term	Definition	
discrete transform	Transform whose input and output values are discrete samples, making it convenient for computer manipulation. Discrete transforms implemented by MATLAB and the Image Processing Toolbox include the discrete Fourier transform (DFT) and the discrete cosine transform (DCT).	
frequency domain	Domain in which an image is represented by a sum of periodic signals with varying frequency.	
inverse transform	Operation that when performed on a transformed image produces the original image.	
spatial domain	Domain in which an image is represented by intensities at given points in space. This is the most common representation for image data.	
transform	Alternative mathematical representation of an image. For example, the Fourier transform is a representation of an image as a sum of complex exponentials of varying magnitudes, frequencies, and phases. Transforms are useful for a wide range of purposes, including convolution, enhancement, feature detection, and compression.	

Fourier Transform

The Fourier transform is a representation of an image as a sum of complex exponentials of varying magnitudes, frequencies, and phases. The Fourier transform plays a critical role in a broad range of image processing applications, including enhancement, analysis, restoration, and compression.

This section includes the following subsections:

- "Definition of Fourier Transform"
- "Discrete Fourier Transform" on page 8-8, including a discussion of fast Fourier transform
- "Applications of the Fourier Transform" on page 8-11 (sample applications using Fourier transforms)

Definition of Fourier Transform

If f(m, n) is a function of two discrete spatial variables m and n, then the *two-dimensional Fourier transform* of f(m, n) is defined by the relationship

$$F(\omega_1, \omega_2) = \sum_{m = -\infty}^{\infty} \sum_{n = -\infty}^{\infty} f(m, n) e^{-j\omega_1 m} e^{-j\omega_2 n}$$

The variables ω_1 and ω_2 are frequency variables; their units are radians per sample. $F(\omega_1, \omega_2)$ is often called the *frequency-domain* representation of f(m,n). $F(\omega_1, \omega_2)$ is a complex-valued function that is periodic both in ω_1 and ω_2 , with period 2π . Because of the periodicity, usually only the range $-\pi \leq \omega_1, \omega_2 \leq \pi$ is displayed. Note that F(0,0) is the sum of all the values of f(m,n). For this reason, F(0,0) is often called the *constant component* or DC component of the Fourier transform. (DC stands for direct current; it is an electrical engineering term that refers to a constant-voltage power source, as opposed to a power source whose voltage varies sinusoidally.)


The inverse two-dimensional Fourier transform is given by

$$f(m,n) = \frac{1}{4\pi^2} \int_{\omega_1 = -\pi}^{\pi} \int_{\omega_2 = -\pi}^{\pi} F(\omega_1, \omega_2) e^{j\omega_1 m} e^{j\omega_2 n} d\omega_1 d\omega_2$$

Roughly speaking, this equation means that f(m,n) can be represented as a sum of an infinite number of complex exponentials (sinusoids) with different frequencies. The magnitude and phase of the contribution at the frequencies (ω_1,ω_2) are given by $F(\omega_1,\omega_2)$.


Visualizing the Fourier Transform

To illustrate, consider a function f(m, n) that equals 1 within a rectangular region and 0 everywhere else. To simplify the diagram, f(m, n) is shown as a continuous function, even though the variables m and n are discrete.



Rectangular Function


The following figure shows, as a mesh plot, the magnitude of the Fourier transform, $|F(\omega_1,\omega_2)|$, of the rectangular function shown in the preceding figure. The mesh plot of the magnitude is a common way to visualize the Fourier transform.



Magnitude Image of a Rectangular Function

The peak at the center of the plot is F(0,0), which is the sum of all the values in f(m,n). The plot also shows that $F(\omega_1,\omega_2)$ has more energy at high horizontal frequencies than at high vertical frequencies. This reflects the fact that horizontal cross sections of f(m,n) are narrow pulses, while vertical cross sections are broad pulses. Narrow pulses have more high-frequency content than broad pulses.


Another common way to visualize the Fourier transform is to display $\log |F(\omega_1,\omega_2)|$ as an image, as shown.



Log of the Fourier Transform of a Rectangular Function

Using the logarithm helps to bring out details of the Fourier transform in regions where $F(\omega_1, \omega_2)$ is very close to 0.

Examples of the Fourier transform for other simple shapes are shown below.



Fourier Transforms of Some Simple Shapes

Discrete Fourier Transform

Working with the Fourier transform on a computer usually involves a form of the transform known as the discrete Fourier transform (DFT). There are two principal reasons for using this form:

- The input and output of the DFT are both discrete, which makes it convenient for computer manipulations.
- There is a fast algorithm for computing the DFT known as the fast Fourier transform (FFT).

The DFT is usually defined for a discrete function f(m,n) that is nonzero only over the finite region $0 \le m \le M-1$ and $0 \le n \le N-1$. The two-dimensional M-by-N DFT and inverse M-by-N DFT relationships are given by

$$F(p,q) = \sum_{m=0}^{M-1} \sum_{n=0}^{N-1} f(m,n)e^{-j(2\pi/M)pm} e^{-j(2\pi/N)qn} \qquad p = 0, 1, ..., M-1$$

$$q = 0, 1, ..., N-1$$

$$f(m,n) = \frac{1}{MN} \sum_{p=0}^{M-1} \sum_{q=0}^{N-1} F(p,q) e^{j(2\pi/M)pm} e^{j(2\pi/N)qn} \qquad m = 0, 1, ..., M-1$$

$$n = 0, 1, ..., N-1$$

The values F(p,q) are the DFT coefficients of f(m,n). The zero-frequency coefficient, F(0,0), is often called the "DC component." DC is an electrical engineering term that stands for direct current. (Note that matrix indices in MATLAB always start at 1 rather than 0; therefore, the matrix elements f(1,1) and F(1,1) correspond to the mathematical quantities f(0,0) and F(0,0), respectively.)

The MATLAB functions fft, fft2, and fftn implement the fast Fourier transform algorithm for computing the one-dimensional DFT, two-dimensional DFT, and N-dimensional DFT, respectively. The functions ifft, ifft2, and ifftn compute the inverse DFT.

Relationship to the Fourier Transform

The DFT coefficients F(p,q) are samples of the Fourier transform $F(\omega_1,\omega_2)$.

$$F(p,q) = F(\omega_1, \omega_2) \Big|_{\substack{\omega_1 = 2\pi p/M \\ \omega_2 = 2\pi q/N}} p = 0, 1, ..., M-1$$

Example


1 Construct a matrix f that is similar to the function f(m,n) in the example in "Definition of Fourier Transform" on page 8-3. Remember that f(m,n) is equal to 1 within the rectangular region and 0 elsewhere. Use a binary image to represent f(m,n).

```
f = zeros(30,30);
f(5:24,13:17) = 1;
imshow(f,'notruesize')
```



2 Compute and visualize the 30-by-30 DFT of f with these commands.

```
F = fft2(f);
F2 = log(abs(F));
imshow(F2,[-1 5],'notruesize'); colormap(jet); colorbar
```



Discrete Fourier Transform Computed Without Padding


This plot differs from the Fourier transform displayed in "Visualizing the Fourier Transform" on page 8-4. First, the sampling of the Fourier transform is much coarser. Second, the zero-frequency coefficient is displayed in the upper left corner instead of the traditional location in the center.

3 To obtain a finer sampling of the Fourier transform, add zero padding to f when computing its DFT. The zero padding and DFT computation can be performed in a single step with this command.

```
F = fft2(f,256,256);
```

This command zero-pads f to be 256-by-256 before computing the DFT.

```
imshow(log(abs(F)),[-1 5]); colormap(jet); colorbar
```



Discrete Fourier Transform Computed with Padding

4 The zero-frequency coefficient, however, is still displayed in the upper left corner rather than the center. You can fix this problem by using the function fftshift, which swaps the quadrants of F so that the zero-frequency coefficient is in the center.

```
F = fft2(f,256,256);
F2 = fftshift(F);
imshow(log(abs(F2)),[-1 5]); colormap(jet); colorbar
```

The resulting plot is identical to the one shown in "Visualizing the Fourier Transform" on page 8-4.

Applications of the Fourier Transform


This section presents a few of the many image processing-related applications of the Fourier transform.

Frequency Response of Linear Filters

The Fourier transform of the impulse response of a linear filter gives the frequency response of the filter. The function freqz2 computes and displays a

filter's frequency response. The frequency response of the Gaussian convolution kernel shows that this filter passes low frequencies and attenuates high frequencies.

```
h = fspecial('gaussian');
freqz2(h)
```



Frequency Response of a Gaussian Filter

See "Linear Filtering and Filter Design" on page 7-1 for more information about linear filtering, filter design, and frequency responses.

Fast Convolution

A key property of the Fourier transform is that the multiplication of two Fourier transforms corresponds to the convolution of the associated spatial functions. This property, together with the fast Fourier transform, forms the basis for a fast convolution algorithm.

Note The FFT-based convolution method is most often used for large inputs. For small inputs it is generally faster to use imfilter.

To illustrate, this example performs the convolution of A and B, where A is an M-by-N matrix and B is a P-by-Q matrix:

1 Create two matrices.

```
A = magic(3);

B = ones(3);
```

2 Zero-pad A and B so that they are at least (M+P-1)-by-(N+Q-1). (Often A and B are zero-padded to a size that is a power of 2 because fft2 is fastest for these sizes.) The example pads the matrices to be 8-by-8.

```
A(8,8) = 0;

B(8,8) = 0;
```

- **3** Compute the two-dimensional DFT of A and B using fft2.
- **4** Multiply the two DFTs together.
- **5** Compute the inverse two-dimensional DFT of the result using ifft2.

The following code performs steps 3, 4, and 5 in the procedure.

```
C = ifft2(fft2(A).*fft2(B));
```

6 Extract the nonzero portion of the result and remove the imaginary part caused by roundoff error.

```
C = C(1:5,1:5);
C = real(C)
C =
    8.0000
              9.0000
                        15.0000
                                    7.0000
                                              6.0000
   11.0000
             17.0000
                        30.0000
                                   19.0000
                                             13.0000
   15.0000
             30.0000
                        45.0000
                                   30.0000
                                             15.0000
    7.0000
             21.0000
                        30.0000
                                   23.0000
                                              9.0000
    4.0000
             13.0000
                        15.0000
                                   11.0000
                                              2.0000
```

Locating Image Features

The Fourier transform can also be used to perform correlation, which is closely related to convolution. Correlation can be used to locate features within an image; in this context correlation is often called *template matching*.

This example illustrates how to use correlation to locate occurrences of the letter "a" in an image containing text:

1 Read in the sample image.

```
bw = imread('text.png');
```

2 Create a template for matching by extracting the letter "a" from the image.

```
a = bw(32:45,88:98);
```

You can also create the template image by using the interactive version of imcrop, using the pixval function to determine the coordinates of features in an image.

The following figure shows both the original image and the template.

```
imshow(bw);
figure, imshow(a);
```



Image (left) and the Template to Correlate (right)

3 Compute the correlation of the template image a with the original image bw by rotating the template image by 180° and then using the FFT-based convolution technique described in "Fast Convolution" on page 8-12. (Convolution is equivalent to correlation if you rotate the convolution kernel by 180°.) To match the template to the image, use the fft2 and ifft2 functions.

```
C = real(ifft2(fft2(bw) .* fft2(rot90(a,2),256,256)));
```

The following image shows the result of the correlation. Bright peaks in the image correspond to occurrences of the letter.

figure, imshow(C,[]) % Scale image to appropriate display range.




Correlated Image

max(C(:))

4 To view the locations of the template in the image, find the maximum pixel value and then define a threshold value that is less than this maximum. The locations of these peaks are indicated by the white spots in the thresholded correlation image. (To make the locations easier to see in this figure, the thresholded image has been dilated to enlarge the size of the points.)

```
ans =
   68.0000
thresh = 60; % Use a threshold that's a little less than max.
figure, imshow(C > thresh)% Display showing pixels over
threshold.
```



Correlated, Thresholded Image Showing Template Locations

Discrete Cosine Transform

The discrete cosine transform (DCT) represents an image as a sum of sinusoids of varying magnitudes and frequencies. The dct2 function in the Image Processing Toolbox computes the two-dimensional discrete cosine transform (DCT) of an image. The DCT has the property that, for a typical image, most of the visually significant information about the image is concentrated in just a few coefficients of the DCT. For this reason, the DCT is often used in image compression applications. For example, the DCT is at the heart of the international standard lossy image compression algorithm known as JPEG. (The name comes from the working group that developed the standard: the Joint Photographic Experts Group.)

The two-dimensional DCT of an M-by-N matrix A is defined as follows.

$$B_{pq} = \alpha_p \alpha_q \sum_{m=0}^{M-1} \sum_{n=0}^{N-1} A_{mn} \cos \frac{\pi (2m+1)p}{2M} \cos \frac{\pi (2n+1)q}{2N}, \quad 0 \le p \le M-1$$

$$\alpha_p = \begin{cases} 1/\sqrt{M}, & p = 0 \\ \sqrt{2/M}, & 1 \le p \le M - 1 \end{cases} \qquad \alpha_q = \begin{cases} 1/\sqrt{N}, & q = 0 \\ \sqrt{2/N}, & 1 \le q \le N - 1 \end{cases}$$

The values B_{pq} are called the DCT coefficients of A. (Note that matrix indices in MATLAB always start at 1 rather than 0; therefore, the MATLAB matrix elements A(1,1) and B(1,1) correspond to the mathematical quantities A_{00} and B_{00} , respectively.)

The DCT is an invertible transform, and its inverse is given by


$$A_{mn} = \sum_{p=0}^{M-1} \sum_{q=0}^{N-1} \alpha_p \alpha_q B_{pq} \cos \frac{\pi (2m+1)p}{2M} \cos \frac{\pi (2n+1)q}{2N}, \quad 0 \le m \le M-1$$

$$\alpha_p = \begin{cases} 1/\sqrt{M}, & p = 0 \\ \sqrt{2/M}, & 1 \le p \le M-1 \end{cases} \qquad \alpha_q = \begin{cases} 1/\sqrt{N}, & q = 0 \\ \sqrt{2/N}, & 1 \le q \le N-1 \end{cases}$$

The inverse DCT equation can be interpreted as meaning that any M-by-N matrix A can be written as a sum of MN functions of the form

$$\alpha_p\alpha_q\cos\frac{\pi(2m+1)p}{2M}\cos\frac{\pi(2n+1)q}{2N},\quad \begin{array}{l} 0\leq p\leq M-1\\ 0\leq q\leq N-1 \end{array}$$

These functions are called the *basis functions* of the DCT. The DCT coefficients B_{pq} , then, can be regarded as the *weights* applied to each basis function. For 8-by-8 matrices, the 64 basis functions are illustrated by this image.



The 64 Basis Functions of an 8-by-8 Matrix

Horizontal frequencies increase from left to right, and vertical frequencies increase from top to bottom. The constant-valued basis function at the upper left is often called the DC basis function, and the corresponding DCT coefficient B_{00} is often called the DC coefficient.

The DCT Transform Matrix

The Image Processing Toolbox offers two different ways to compute the DCT. The first method is to use the function dct2. dct2 uses an FFT-based algorithm for speedy computation with large inputs. The second method is to use the DCT transform matrix, which is returned by the function dctmtx and might be more

efficient for small square inputs, such as 8-by-8 or 16-by-16. The M-by-M transform matrix T is given by

$$T_{pq} = \begin{cases} \frac{1}{\sqrt{M}} & p = 0, \quad 0 \le q \le M - 1 \\ \sqrt{\frac{2}{M}} \cos \frac{\pi(2q+1)p}{2M} & 1 \le p \le M - 1, \quad 0 \le q \le M - 1 \end{cases}$$

For an M-by-M matrix A, T*A is an M-by-M matrix whose columns contain the one-dimensional DCT of the columns of A. The two-dimensional DCT of A can be computed as B=T*A*T'. Since T is a real orthonormal matrix, its inverse is the same as its transpose. Therefore, the inverse two-dimensional DCT of B is given by T'*B*T.

DCT and Image Compression

In the JPEG image compression algorithm, the input image is divided into 8-by-8 or 16-by-16 blocks, and the two-dimensional DCT is computed for each block. The DCT coefficients are then quantized, coded, and transmitted. The JPEG receiver (or JPEG file reader) decodes the quantized DCT coefficients, computes the inverse two-dimensional DCT of each block, and then puts the blocks back together into a single image. For typical images, many of the DCT coefficients have values close to zero; these coefficients can be discarded without seriously affecting the quality of the reconstructed image.

The example code below computes the two-dimensional DCT of 8-by-8 blocks in the input image, discards (sets to zero) all but 10 of the 64 DCT coefficients in each block, and then reconstructs the image using the two-dimensional inverse DCT of each block. The transform matrix computation method is used.

```
0 0
                       0
                                  0];
B2 = blkproc(B,[8 8],'P1.*x',mask);
I2 = blkproc(B2,[8 8],'P1*x*P2',T',T);
imshow(I), figure, imshow(I2)
```






Image Courtesy of MIT

Although there is some loss of quality in the reconstructed image, it is clearly recognizable, even though almost 85% of the DCT coefficients were discarded. To experiment with discarding more or fewer coefficients, and to apply this technique to other images, try running the demo function dctdemo.

Radon Transform


The radon function in the Image Processing Toolbox computes projections of an image matrix along specified directions. A projection of a two-dimensional function f(x,y) is a set of line integrals. The radon function computes the line integrals from multiple sources along parallel paths, or beams, in a certain direction. The beams are spaced 1 pixel unit apart. To represent an image, the radon function takes multiple, parallel-beam projections of the image from different angles by rotating the source around the center of the image. The following figure shows a single projection at a specified rotation angle.



Parallel-Beam Projection at Rotation Angle Theta

Note For information about creating projection data from line integrals along paths that radiate from a single source, called fan-beam projections, see "Fan-Beam Projection Data" on page 8-36. To convert parallel-beam projection data to fan-beam projection data, use the para2fan function.

For example, the line integral of f(x,y) in the vertical direction is the projection of f(x,y) onto the x-axis; the line integral in the horizontal direction is the projection of f(x,y) onto the y-axis. The following figure shows horizontal and vertical projections for a simple two-dimensional function.



Horizontal and Vertical Projections of a Simple Function


Projections can be computed along any angle θ . In general, the Radon transform of f(x,y) is the line integral of f parallel to the y'-axis

$$R_{\theta}(x') = \int_{-\infty}^{\infty} f(x' \cos \theta - y' \sin \theta, \, x' \sin \theta + y' \cos \theta) \, \, dy'$$

where

$$\begin{bmatrix} x' \\ y' \end{bmatrix} = \begin{bmatrix} \cos \theta & \sin \theta \\ -\sin \theta & \cos \theta \end{bmatrix} \begin{bmatrix} x \\ y \end{bmatrix}$$

The following figure illustrates the geometry of the Radon transform.



Geometry of the Radon Transform

Plotting the Radon Transform

You can compute the Radon transform of an image I for the angles specified in the vector theta using the radon function with this syntax.

$$[R,xp] = radon(I,theta);$$

The columns of R contain the Radon transform for each angle in theta. The vector xp contains the corresponding coordinates along the x'-axis. The center pixel of I is defined to be floor((size(I)+1)/2); this is the pixel on the x'-axis corresponding to x'=0.

The commands below compute and plot the Radon transform at 0° and 45° of an image containing a single square object. xp is the same for all projection angles.


```
I = zeros(100,100);

I(25:75, 25:75) = 1;

imshow(I)
```




```
[R,xp] = radon(I,[0 45]);
figure; plot(xp,R(:,1)); title('R_{0^0} (x\prime)')
```



Radon Transform of a Square Function at 0 Degrees

```
figure; plot(xp,R(:,2)); title('R_{45^o} (x\prime)')
```




Radon Transform of a Square Function at 45 Degrees

Viewing the Radon Transform as an Image

The Radon transform for a large number of angles is often displayed as an image. In this example, the Radon transform for the square image is computed at angles from 0° to 180° , in 1° increments.

```
theta = 0:180;
[R,xp] = radon(I,theta);
imagesc(theta,xp,R);
title('R_{\theta} (X\prime)');
xlabel('\theta (degrees)');
ylabel('X\prime');
set(gca,'XTick',0:20:180);
colormap(hot);
colorbar
```



Radon Transform Using 180 Projections

Using the Radon Transform to Detect Lines

The Radon transform is closely related to a common computer vision operation known as the Hough transform. You can use the radon function to implement a form of the Hough transform used to detect straight lines. The steps are

1 Compute a binary edge image using the edge function.

```
I = fitsread('solarspectra.fts');
I = mat2gray(I);
BW = edge(I);
imshow(I), figure, imshow(BW)
```






Image Courtesy of Ann Walker
Original Image



Edge Image

2 Compute the Radon transform of the edge image.


```
theta = 0:179;
[R,xp] = radon(BW,theta);
figure, imagesc(theta, xp, R); colormap(hot);
xlabel('\theta (degrees)'); ylabel('x\prime');
title('R_{\theta} (x\prime)');
colorbar
```



Radon Transform of an Edge Image

3 Find the locations of strong peaks in the Radon transform matrix. The locations of these peaks correspond to the locations of straight lines in the original image.

In the following figure, the strongest peaks in R correspond to $\theta=1^\circ$ and x'=-80. The line perpendicular to that angle and located at x'=-80 is shown below, superimposed in red on the original image. The Radon transform geometry is shown in black. Notice that the other strong lines parallel to the red line also appear as peaks at $\theta=1^\circ$ in the transform. Also, the lines perpendicular to this line appear as peaks at $\theta=91^\circ$.



Radon Transform Geometry and the Strongest Peak (Red)

Inverse Radon Transform

The iradon function performs the inverse Radon transform, which is commonly used in tomography applications. This transform inverts the Radon transform (which was introduced in the previous section), and can therefore be used to reconstruct images from projection data.

As described in "Radon Transform" on page 8-21, given an image I and a set of angles theta, the radon function can be used to calculate the Radon transform.

```
R = radon(I, theta);
```

The function iradon can then be called to reconstruct the image I.


```
IR = iradon(R, theta);
```

In the example above, projections are calculated from the original image I. In most application areas, there is no *original image* from which projections are formed. For example, in X-ray absorption tomography, projections are formed by measuring the attenuation of radiation that passes through a physical specimen at different angles. The original image can be thought of as a cross section through the specimen, in which intensity values represent the density of the specimen. Projections are collected using special purpose hardware, and then an internal image of the specimen is reconstructed by iradon. This allows for noninvasive imaging of the inside of a living body or another opaque object.

iradon reconstructs an image from parallel-beam projections. In *parallel-beam geometry*, each projection is formed by combining a set of line integrals through an image at a specific angle.

The following figure illustrates how parallel-beam geometry is applied in X-ray absorption tomography. Note that there is an equal number of n emitters and n sensors. Each sensor measures the radiation emitted from its corresponding emitter, and the attenuation in the radiation gives a measure of the integrated density, or mass, of the object. This corresponds to the line integral that is calculated in the Radon transform.

The parallel-beam geometry used in the figure is the same as the geometry that was described in "Radon Transform" on page 8-21. f(x,y) denotes the brightness of the image and $R_{\mathbf{A}}(x')$ is the projection at angle theta.



Parallel-Beam Projections Through an Object

Another geometry that is commonly used is fan-beam geometry, in which there is one source and n sensors. For more information, see "Fan-Beam Projection Data" on page 8-36. To convert parallel-beam projection data into fan-beam projection data, use the para2fan function.

Improving the Results

iradon uses the *filtered backprojection* algorithm to compute the inverse Radon transform. This algorithm forms an approximation of the image I based on the projections in the columns of R. A more accurate result can be obtained by using

more projections in the reconstruction. As the number of projections (the length of theta) increases, the reconstructed image IR more accurately approximates the original image I. The vector theta must contain monotonically increasing angular values with a constant incremental angle $\Delta\theta$. When the scalar $\Delta\theta$ is known, it can be passed to iradon instead of the array of theta values. Here is an example.

```
IR = iradon(R,Dtheta);
```

The filtered backprojection algorithm filters the projections in R and then reconstructs the image using the filtered projections. In some cases, noise can be present in the projections. To remove high frequency noise, apply a window to the filter to attenuate the noise. Many such windowed filters are available in iradon. The example call to iradon below applies a Hamming window to the filter. See the iradon reference page for more information.

```
IR = iradon(R,theta,'Hamming');
```

iradon also enables you to specify a normalized frequency, D, above which the filter has zero response. D must be a scalar in the range [0,1]. With this option, the frequency axis is rescaled so that the whole filter is compressed to fit into the frequency range [0,D]. This can be useful in cases where the projections contain little high-frequency information but there is high-frequency noise. In this case, the noise can be completely suppressed without compromising the reconstruction. The following call to iradon sets a normalized frequency value of 0.85.

```
IR = iradon(R, theta, 0.85);
```

Example: Reconstructing an Image from Parallel Projection Data

The commands below illustrate how to reconstruct an image from parallel projection data. The test image is the Shepp-Logan head phantom, which can be generated by the Image Processing Toolbox function phantom. The phantom image illustrates many of the qualities that are found in real-world tomographic imaging of human heads. The bright elliptical shell along the exterior is analogous to a skull, and the many ellipses inside are analogous to brain features.

1 Create a Shepp-Logan head phantom image.

```
P = phantom(256);
imshow(P)
```




2 Compute the Radon transform of the phantom brain for three different sets of theta values. R1 has 18 projections, R2 has 36 projections, and R3 has 90 projections.

```
theta1 = 0:10:170; [R1,xp] = radon(P,theta1);
theta2 = 0:5:175; [R2,xp] = radon(P,theta2);
theta3 = 0:2:178; [R3,xp] = radon(P,theta3);
```

3 Display a plot of one of the Radon transforms of the Shepp-Logan head phantom. The following figure shows R3, the transform with 90 projections.

```
figure, imagesc(theta3,xp,R3); colormap(hot); colorbar
xlabel('\theta'); ylabel('x\prime');
```



Radon Transform of Head Phantom Using 90 Projections


Note how some of the features of the input image appear in this image of the transform. The first column in the Radon transform corresponds to a projection at 0° that is integrating in the vertical direction. The centermost column corresponds to a projection at 90° , which is integrating in the horizontal direction. The projection at 90° has a wider profile than the projection at 0° due to the larger vertical semiaxis of the outermost ellipse of the phantom.

4 Reconstruct the head phantom image from the projection data created in step 2 and display the results.

```
I1 = iradon(R1,10);
I2 = iradon(R2,5);
I3 = iradon(R3,2);
imshow(I1)
figure, imshow(I2)
```

figure, imshow(I3)


The following figure shows the results of all three reconstructions. Notice how image I1, which was reconstructed from only 18 projections, is the least accurate reconstruction. Image I2, which was reconstructed from 36 projections, is better, but it is still not clear enough to discern clearly the small ellipses in the lower portion of the image. I3, reconstructed using 90 projections, most closely resembles the original image. Notice that when the number of projections is relatively small (as in I1 and I2), the reconstruction can include some artifacts from the back projection.



Inverse Radon Transforms of the Shepp-Logan Head Phantom

Fan-Beam Projection Data

The fanbeam function in the Image Processing Toolbox computes *projections* of an image matrix along specified directions. A projection of a two-dimensional function f(x,y) is a set of line integrals. The fanbeam function computes the line integrals along paths that radiate from a single source, forming a fan shape. To represent an image, the fanbeam function takes multiple projections of the image from different angles by rotating the source around the center of the image. The following figure shows a single fan-beam projection at a specified rotation angle.



Fan-Beam Projection at Rotation Angle Theta

This section

- Describes how to use the fanbeam function to generate fan-beam projection data
- Describes how to reconstruct an image from fan-beam projection data
- Shows an example that creates a fan-beam projection of an image and then reconstructs the image from the fan-beam projection data

Note For information about creating projection data from line integrals along parallel paths, see "Radon Transform" on page 8-21. To convert fan-beam projection data to parallel-beam projection data, use the fan2para function.

Computing Fan-Beam Projection Data


To compute fan-beam projection data, use the fanbeam function. You specify as arguments an image and the distance between the vertex of the fan-beam projections and the center of rotation (the center pixel in the image). The fanbeam function determines the number of beams, based on the size of the image and the settings of fanbeam parameters.

By default, fanbeam positions the sensors along an arc at distance D from the center of rotation, and spaces the sensors at 1 degree intervals. Using the FanSensorSpacing parameter, you can specify a different angle between each beam. Using the FanSensorGeometry parameter, you can optionally specify that fanbeam position sensors along a straight line, rather than an arc. With this geometry, you specify the spacing between sensors in pixels. In this case, only the sensor aligned with the center pixel is distance D from the center of rotation.

fanbeam takes projections at different angles by rotating the source around the center pixel at 1 degree intervals. Using the FanRotationIncrement parameter you can specify a different rotation angle increment.


The following figures illustrate both these geometries.

The first figure illustrates geometry used by the fanbeam function when FanSensorGeometry is set to 'arc' (the default). Note how you specify the distance between sensors by specifying the angular spacing of the beams.



Fan-Beam Projection with Arc Geometry

The following figure illustrates geometry used by the fanbeam function when FanSensorGeometry is set to 'line'. In this figure, note how you specify the position of the sensors by specifying the distance between them in pixels.



Fan-Beam Projection with Line Geometry

Reconstructing an Image from Fan-Beam Projection Data

To reconstruct an image from fan-beam projection data, use the ifanbeam function. With this function, you specify as arguments the projection data and the distance between the vertex of the fan-beam projections and the center of rotation when the projection data was created. For example, this code recreates the image I from the projection data P and distance D.

I = ifanbeam(P,D);

By default, the ifanbeam function assumes that the fan-beam projection data was created using the arc fan sensor geometry, with beams spaced at 1 degree angles and projections taken at 1 degree increments over a full 360 degree range. As with the fanbeam function, you can use ifanbeam parameters to specify other values for these characteristics of the projection data. Use the same values for these parameters that were used when the projection data was created. For more information about these parameters, see "Computing Fan-Beam Projection Data" on page 8-37.

The ifanbeam function converts the fan-beam projection data to parallel-beam projection data with the fan2para function, and then calls the iradon function to perform the image reconstruction. For this reason, the ifanfeam function supports certain iradon parameters, which it passes to the iradon function. See "Inverse Radon Transform" on page 8-29 for more information about the iradon function.

Working with Fan-Beam Projection Data

The commands below illustrate how to use fanbeam and ifanbeam to form projections from a sample image and then reconstruct the image from the projections. The test image is the Shepp-Logan head phantom, which can be generated by the Image Processing Toolbox function phantom. The phantom image illustrates many of the qualities that are found in real-world tomographic imaging of human heads.

1 Generate the test image and display it.

```
P = phantom(256);
imshow(P)
```




2 Compute fan-beam projection data of the test image, using the FanSensorSpacing parameter to vary the sensor spacing. The example uses the fanbeam arc geometry, so you specify the spacing between sensors by specifying the angular spacing of the beams. The first call spaces the beams at 2 degrees; the second at 1 degree; and the third at 0.25 degrees. In each call, the distance between the center of rotation and vertex of the projections is constant at 250 pixels. In addition, fanbeam rotates the projection around the center pixel at 1 degree increments.

```
D = 250;
dsensor1 = 2;
F1 = fanbeam(P,D,'FanSensorSpacing',dsensor1);
dsensor2 = 1;
F2 = fanbeam(P,D,'FanSensorSpacing',dsensor2);
dsensor3 = 0.25
[F3, sensor_pos3, fan_rot_angles3] = fanbeam(P,D,...'FanSensorSpacing',dsensor3);
```


3 Plot the projection data F3. Because fanbeam calculates projection data at rotation angles from 0 to 360 degrees, the same patterns occur at an offset of 180 degrees. The same features are being sampled from both sides. Compare this plot to the plot of the parallel-beam projection data of the head phantom on page 8-34.

```
figure, imagesc(fan_rot_angles3, sensor_pos3, F3)
colormap(hot); colorbar
xlabel('Fan Rotation Angle (degrees)')
ylabel('Fan Sensor Position (degrees)')
```



4 Reconstruct the image from the fan-beam projection data using ifanbeam. In each reconstruction, match the fan sensor spacing with the spacing used when the projection data was created in step 2. The example uses the OutputSize parameter to constrain the output size of each reconstruction to be the same as the size of the original image |P|.

The following figure shows the result of each transform. Note how the quality of the reconstruction gets better as the number of beams in the projection increases. The first image, Ifan1, was created using 2 degree spacing of the beams; the second image, ifan2, was created using 1 degree spacing of the beams; the third image, ifan3, was created using 0.25 spacing of the beams.



Reconstruction of the Head Phantom Image from Fan-Beam Projections

Morphological Operations

Morphology is a technique of image processing based on shapes. The value of each pixel in the output image is based on a comparison of the corresponding pixel in the input image with its neighbors. By choosing the size and shape of the neighborhood, you can construct a morphological operation that is sensitive to specific shapes in the input image.

This chapter describes the Image Processing Toolbox morphological functions. You can use these functions to perform common image processing tasks, such as contrast enhancement, noise removal, thinning, skeletonization, filling, and segmentation.

Terminology (p. 9-2) Provides definitions of image processing terms used in

this section

Dilation and Erosion (p. 9-4) Defines the two fundamental morphological operations,

dilation and erosion, and some of the morphological image processing operations that are based on

combinations of these operations

Morphological Reconstruction (p. 9-19) Describes morphological reconstruction and the toolbox

functions that use this type of processing

Distance Transform (p. 9-37) Describes how to use the bwdist function to compute the

distance transform of an image

Objects, Regions, and Feature

Measurement (p. 9-40)

'1 ,

Describes functions that return information about a

binary image

Lookup Table Operations (p. 9-44) Describes functions that perform lookup table operations

Terminology

An understanding of the following terms will help you to use this chapter.

Term	Definition	
background	In a binary image, pixels that are off, i.e., set to the value are considered the background. When you view a binary image, the background pixels appear black.	
connectivity	Criteria that describe how pixels in an image form a connected group. For example, a connected component is "8-connected" if diagonally adjacent pixels are considered to be touching; otherwise, it is "4-connected." The toolbox supports 2-D as well as multidimensional connectivities. See "Pixel Connectivity" on page 9-23 for more information.	
foreground	In a binary image, pixels that are on, i.e., set to the value 1, are considered the foreground. When you view a binary image the foreground pixels appear white.	
global maxima	Highest regional maxima in the image. See the entry for regional maxima in this table for more information.	
global minima	Lowest regional minima in the image. See the entry for regional minima in this table for more information.	
morphology	A broad set of image processing operations that process images based on shapes. Morphological operations apply a structuring element to an input image, creating an output image of the same size. The most basic morphological operations are dilation and erosion.	
neighborhood	Set of pixels that are defined by their locations relative to the pixel of interest. A neighborhood can be defined by a structuring element or by specifying a connectivity.	
object	Set of pixels in a binary image that form a connected group. I the context of this chapter, "object" and "connected component" are equivalent.	

Term	Definition	
packed binary image	Method of compressing binary images that can speed up the processing of the image.	
regional maxima	Connected set of pixels of constant intensity from which it is impossible to reach a point with higher intensity without first descending; that is, a connected component of pixels with the same intensity value, t , surrounded by pixels that all have a value less than t .	
regional minima	Connected set of pixels of constant intensity from which it is impossible to reach a point with lower intensity without first ascending; that is, a connected component of pixels with the same intensity value, t , surrounded by pixels that all have a value greater than t .	
structuring element	Matrix used to define a neighborhood shape and size for morphological operations, including dilation and erosion. It consists of only 0's and 1's and can have an arbitrary shape and size. The pixels with values of 1 define the neighborhood.	

Dilation and Erosion

Dilation and erosion are two fundamental morphological operations. Dilation adds pixels to the boundaries of objects in an image, while erosion removes pixels on object boundaries. The number of pixels added or removed from the objects in an image depends on the size and shape of the *structuring element* used to process the image.

The following sections

- Provide important background information about how the dilation and erosion functions operate
- Describe structuring elements and how to create them
- Describe how to perform a morphological dilation
- Describe how to perform a morphological erosion
- Describe some of the common operations that are based on dilation and erosion
- Describe toolbox functions that are based on dilation and erosion

To view an extended example that uses morphological processing to solve an image processing problem, see the Image Processing Toolbox watershed segmentation demo.


Understanding Dilation and Erosion

In the morphological dilation and erosion operations, the state of any given pixel in the output image is determined by applying a rule to the corresponding pixel and its neighbors in the input image. The rule used to process the pixels defines the operation as a dilation or an erosion. This table lists the rules for both dilation and erosion.

	•	-·I -·		- •
Riilac	tor	Dilation	and	Fracian
KUICS	101	PHAIICH	GIIG	


Operation	Rule
Dilation	The value of the output pixel is the <i>maximum</i> value of all the pixels in the input pixel's neighborhood. In a binary image, if any of the pixels is set to the value 1, the output pixel is set to 1.
Erosion	The value of the output pixel is the <i>minimum</i> value of all the pixels in the input pixel's neighborhood. In a binary image, if any of the pixels is set to 0, the output pixel is set to 0.

The following figure illustrates the dilation of a binary image. Note how the structuring element defines the neighborhood of the pixel of interest, which is circled. (See "Structuring Elements" on page 9-7 for more information.) The dilation function applies the appropriate rule to the pixels in the neighborhood and assigns a value to the corresponding pixel in the output image. In the figure, the morphological dilation function sets the value of the output pixel to 1 because one of the elements in the neighborhood defined by the structuring element is on.



Morphological Dilation of a Binary Image

The following figure illustrates this processing for a grayscale image. The figure shows the processing of a particular pixel in the input image. Note how the function applies the rule to the input pixel's neighborhood and uses the highest value of all the pixels in the neighborhood as the value of the corresponding pixel in the output image.



Morphological Dilation of a Grayscale Image

Processing Pixels at Image Borders (Padding Behavior)

Morphological functions position the origin of the structuring element, its center element, over the pixel of interest in the input image. For pixels at the edge of an image, parts of the neighborhood defined by the structuring element can extend past the border of the image.

To process border pixels, the morphological functions assign a value to these undefined pixels, as if the functions had padded the image with additional rows and columns. The value of these padding pixels varies for dilation and erosion operations. The following table describes the padding rules for dilation and erosion for both binary and grayscale images.

Rules for Padding Images

Operation	Rule
Dilation	Pixels beyond the image border are assigned the minimum value afforded by the data type.
	For binary images, these pixels are assumed to be set to 0. For grayscale images, the minimum value for uint8 images is 0.
Erosion	Pixels beyond the image border are assigned the <i>maximum</i> value afforded by the data type.
	For binary images, these pixels are assumed to be set to 1. For grayscale images, the maximum value for uint8 images is 255.

Note By using the minimum value for dilation operations and the maximum value for erosion operations, the toolbox avoids *border effects*, where regions near the borders of the output image do not appear to be homogeneous with the rest of the image. For example, if erosion padded with a minimum value, eroding an image would result in a black border around the edge of the output image.

Structuring Elements

An essential part of the dilation and erosion operations is the structuring element used to probe the input image. Two-dimensional, or *flat*, structuring elements consist of a matrix of 0's and 1's, typically much smaller than the image being processed. The center pixel of the structuring element, called the *origin*, identifies the pixel of interest — the pixel being processed. The pixels in the structuring element containing 1's define the *neighborhood* of the structuring element. These pixels are also considered in dilation or erosion processing. Three-dimensional, or *nonflat*, structuring elements use 0's and 1's to define the extent of the structuring element in the *x*- and *y*-planes and add height values to define the third dimension.


The Origin of a Structuring Element

The morphological functions use this code to get the coordinates of the origin of structuring elements of any size and dimension.

```
origin = floor((size(nhood)+1)/2)
```

(In this code nhood is the neighborhood defining the structuring element. Because structuring elements are MATLAB objects, you cannot use the size of the STREL object itself in this calculation. You must use the STREL getnhood method to retrieve the neighborhood of the structuring element from the STREL object. For information about other STREL object methods, see the strel function reference page.)

For example, the following illustrates a diamond-shaped structuring element.



Origin of a Diamond-Shaped Structuring Element

Creating a Structuring Element

The toolbox dilation and erosion functions accept structuring element objects, called STRELs. You use the strel function to create STRELs of any arbitrary size and shape. The strel function also includes built-in support for many common shapes, such as lines, diamonds, disks, periodic lines, and balls.

Note You typically choose a structuring element the same size and shape as the objects you want to process in the input image. For example, to find lines in an image, create a linear structuring element.

For example, this code creates a flat, diamond-shaped structuring element.

```
se = strel('diamond',3)
se =
Flat STREL object containing 25 neighbors.
Decomposition: 3 STREL objects containing a total of 13 neighbors
Neighborhood:
     0
            0
                  0
                                      0
                                             0
     0
            0
                  1
                         1
                                1
                                      0
                                             0
     0
                         1
                                             0
     1
            1
                         1
                                1
                                             1
     0
                                             0
     0
            0
                  1
                         1
                                1
                                      0
                                             0
```

Structuring Element Decomposition

To enhance performance, the strel function might break structuring elements into smaller pieces, a technique known as *structuring element decomposition*.

O

For example, dilation by an 11-by-11 square structuring element can be accomplished by dilating first with a 1-by-11 structuring element, and then with an 11-by-1 structuring element. This results in a theoretical speed improvement of a factor of 5.5, although in practice the actual speed improvement is somewhat less.

Structuring element decompositions used for the 'disk' and 'ball' shapes are approximations; all other decompositions are exact. Decomposition is not used with an arbitrary structuring element unless it is a flat structuring element whose neighborhood is all 1's.

To view the sequence of structuring elements used in a decomposition, use the STREL getsequence method. The getsequence function returns an array of the structuring elements that form the decomposition. For example, here are the structuring elements created in the decomposition of a diamond-shaped structuring element.

```
sel = strel('diamond',4)
sel =
Flat STREL object containing 41 neighbors.
Decomposition: 3 STREL objects containing a total of 13 neighbors
```

Neigh	borho	od:					
J	0	0	0	0	1	0	C
	0	0	0	1	1	1	C
	0	0	1	1	1	1	1
	0	1	1	1	1	1	1
	1	1	1	1	1	1 1	1
	0	0	1	1	1	1	1
	0	0	0	1	1	1	0
	0	0	0	0	1	0	C
seq =	=	equence		ects			
seq(1 ans = Flat	=	object	t conta	aining	5	neighbors	
Neigh	nborho	od:					
	0	1	0				
	1	1	1				
	0	1	0				
seq(2 ans =	=						
Flat	STREL	object	conta	aining	4	neighbors	•
Neigh	borho	od:					
	0	1	0				
	1	0	1				
	0	1	0				
seq(3	3)						
ans =							
Flat	STREL	object	conta	aining	4	neighbors	•
Neigh	borho	od:					
	0	0	1	0	0		

0

0 0

1

0

0

0	0	0	0	0
1	0	0	0	1
0	0	0	0	0
0	0	1	0	0

Dilating an Image

To dilate an image, use the imdilate function. The imdilate function accepts two primary arguments:

- The input image to be processed (grayscale, binary, or packed binary image)
- A structuring element object, returned by the strel function, or a binary matrix defining the neighborhood of a structuring element

imdilate also accepts two optional arguments: PADOPT and PACKOPT. The PADOPT argument affects the size of the output image. The PACKOPT argument identifies the input image as packed binary. (See the bwpack reference page for information about binary image packing.)

This example dilates a simple binary image containing one rectangular object.

BW =	zeros ((9,10)	;							
BW(4:	6,4:7)	= 1								
BW =										
	0	0	0	0	0	0	0	0	0	0
	0	0	0	0	0	0	0	0	0	0
	0	0	0	0	0	0	0	0	0	0
	0	0	0	1	1	1	1	0	0	0
	0	0	0	1	1	1	1	0	0	0
	0	0	0	1	1	1	1	0	0	0
	0	0	0	0	0	0	0	0	0	0
	0	0	0	0	0	0	0	0	0	0
	0	0	0	0	0	0	0	0	0	0

To expand all sides of the foreground component, the example uses a 3-by-3 square structuring element object. (For more information about using the strel function, see "Structuring Elements" on page 9-7.)

```
SE = strel('square',3)
SE =
Flat STREL object containing 3 neighbors.
```

Neighborl	hood:	
1	1	1
1	1	1
1	1	1

To dilate the image, pass the image BW and the structuring element SE to the imdilate function. Note how dilation adds a rank of 1's to all sides of the foreground object.

BW2	= im	dilate	e(BW,	SE)						
BW2	2 =									
	0	0	0	0	0	0	0	0	0	0
	0	0	0	0	0	0	0	0	0	0
	0	0	1	1	1	1	1	1	0	0
	0	0	1	1	1	1	1	1	0	0
	0	0	1	1	1	1	1	1	0	0
	0	0	1	1	1	1	1	1	0	0
	0	0	1	1	1	1	1	1	0	0
	0	0	0	0	0	0	0	0	0	0
	0	0	0	0	0	0	0	0	0	0

Eroding an Image

To erode an image, use the imerode function. The imerode function accepts two primary arguments:

- The input image to be processed (grayscale, binary, or packed binary image)
- A structuring element object, returned by the strel function, or a binary matrix defining the neighborhood of a structuring element

imerode also accepts three optional arguments: PADOPT, PACKOPT, and ${\tt M}.$

The PADOPT argument affects the size of the output image. The PACKOPT argument identifies the input image as packed binary. If the image is packed binary, M identifies the number of rows in the original image. (See the bwpack reference page for more information about binary image packing.)

The following example erodes the binary image circbw.tif:

1 Read the image into the MATLAB workspace.

```
BW1 = imread('circbw.tif');
```

2 Create a structuring element. The following code creates a diagonal structuring element object. (For more information about using the strel function, see "Structuring Elements" on page 9-7.)

```
SE = strel('arbitrary',eye(5));
SE=
```

Flat STREL object containing 5 neighbors.

Neighborhood:


1	0	0	0	0
0	1	0	0	0
0	0	1	0	0
0	0	0	1	0
0	0	0	0	1

3 Call the imerode function, passing the image BW and the structuring element SE as arguments.

```
BW2 = imerode(BW1,SE);
```

Notice the diagonal streaks on the right side of the output image. These are due to the shape of the structuring element.

```
imshow(BW1)
figure, imshow(BW2)
```





Eroded Image

Combining Dilation and Erosion

Dilation and erosion are often used in combination to implement image processing operations. For example, the definition of a morphological *opening* of an image is an erosion followed by a dilation, using the same structuring element for both operations. The related operation, morphological *closing* of an image, is the reverse: it consists of dilation followed by an erosion with the same structuring element.

The following section uses imdilate and imerode to illustrate how to implement a morphological opening. Note, however, that the toolbox already includes the imopen function, which performs this processing. The toolbox includes functions that perform many common morphological operations. See "Dilation- and Erosion-Based Functions" on page 9-16 for a complete list.

Morphological Opening

You can use morphological opening to remove small objects from an image while preserving the shape and size of larger objects in the image. For example, you can use the imopen function to remove all the circuit lines from the original circuit image, circbw.tif, creating an output image that contains only the rectangular shapes of the microchips.

To morphologically open the image, perform these steps:

1 Read the image into the MATLAB workspace.

```
BW1 = imread('circbw.tif');
```

2 Create a structuring element.

```
SE = strel('rectangle',[40 30]);
```

The structuring element should be large enough to remove the lines when you erode the image, but not large enough to remove the rectangles. It should consist of all 1's, so it removes everything but large contiguous patches of foreground pixels.

3 Erode the image with the structuring element.

```
BW2 = imerode(BW1,SE);
imshow(BW2)
```

This removes all the lines, but also shrinks the rectangles.



4 To restore the rectangles to their original sizes, dilate the eroded image using the same structuring element, SE.

```
BW3 = imdilate(BW2,SE);
imshow(BW3)
```



Dilation- and Erosion-Based Functions

This section describes two common image processing operations that are based on dilation and erosion:

- Skeletonization
- Perimeter determination

This table lists other functions in the toolbox that perform common morphological operations that are based on dilation and erosion. For more information about these functions, see their reference pages.

Dilation- and Erosion-Based Functions

Function	Morphological Definition
bwhitmiss	Logical AND of an image, eroded with one structuring element, and the image's complement, eroded with a second structuring element.
imbothat	Subtracts the original image from a morphologically closed version of the image. Can be used to find intensity troughs in an image.
imclose	Dilates an image and then erodes the dilated image using the same structuring element for both operations.


Dilation-	and Fra	ssion-Ra	sed Fu	nctions
	uliu Lit	J31011-DU	seu i u	IICIIOIIS


Function	Morphological Definition (Continued)
imopen	Erodes an image and then dilates the eroded image using the same structuring element for both operations.
imtophat	Subtracts a morphologically opened image from the original image. Can be used to enhance contrast in an image.

Skeletonization

To reduce all objects in an image to lines, without changing the essential structure of the image, use the bwmorph function. This process is known as *skeletonization*.

```
BW1 = imread('circbw.tif');
BW2 = bwmorph(BW1, 'skel', Inf);
imshow(BW1)
figure, imshow(BW2)
```





original image

Skeletonization of Image

Perimeter Determination


The bwperim function determines the perimeter pixels of the objects in a binary image. A pixel is considered a perimeter pixel if it satisfies both of these criteria:


• The pixel is on.

 \bullet One (or more) of the pixels in its neighborhood is off.

For example, this code finds the perimeter pixels in a binary image of a circuit board.

```
BW1 = imread('circbw.tif');
BW2 = bwperim(BW1);
imshow(BW1)
figure, imshow(BW2)
```





Perimeters Determined

Morphological Reconstruction

Morphological reconstruction is another major part of morphological image processing. Based on dilation, morphological reconstruction has these unique properties:

- Processing is based on two images, a marker and a mask, rather than one image and a structuring element.
- Processing repeats until stability; i.e., the image no longer changes.
- Processing is based on the concept of connectivity, rather than a structuring element.

This section

- Provides background information about morphological reconstruction and describes how to use the imreconstruct function
- Describes how pixel connectivity affects morphological reconstruction
- Describes how to use the imfill function, which is based on morphological reconstruction
- Describes a group of functions, all based on morphological reconstruction, that process image extrema, i.e., the areas of high and low intensity in images

Marker and Mask

Morphological reconstruction processes one image, called the *marker*, based on the characteristics of another image, called the *mask*. The high points, or peaks, in the marker image specify where processing begins. The processing continues until the image values stop changing.

To illustrate morphological reconstruction, consider this simple image. It contains two primary regions, the blocks of pixels containing the values 14 and 18. The background is primarily all set to 10, with some pixels set to 11.

A = [10]	10	10	10	10	10	10	10	10	10;
10	14	14	14	10	10	11	10	11	10;
10	14	14	14	10	10	10	11	10	10;
10	14	14	14	10	10	11	10	11	10;
10	10	10	10	10	10	10	10	10	10;
10	11	10	10	10	18	18	18	10	10;
10	10	10	11	10	18	18	18	10	10;
10	10	11	10	10	18	18	18	10	10;
10	11	10	11	10	10	10	10	10	10;
10	10	10	10	10	10	11	10	10	10];

To morphologically reconstruct this image, perform these steps:

1 Create a marker image. As with the structuring element in dilation and erosion, the characteristics of the marker image determine the processing performed in morphological reconstruction. The peaks in the marker image should identify the location of objects in the mask image that you want to emphasize.

One way to create a marker image is to subtract a constant from the mask image, using imsubtract.

```
marker = imsubtract(A,2)
marker =
      8
              8
                     8
                             8
                                     8
                                             8
                                                     8
                                                             8
                                                                     8
                                                                            8
      8
             12
                     12
                            12
                                     8
                                             8
                                                     9
                                                             8
                                                                     9
                                                                            8
      8
             12
                     12
                            12
                                     8
                                             8
                                                     8
                                                             9
                                                                     8
                                                                            8
      8
             12
                                     8
                                             8
                                                     9
                                                             8
                                                                     9
                                                                            8
                     12
                            12
      8
              8
                     8
                             8
                                     8
                                             8
                                                     8
                                                             8
                                                                     8
                                                                            8
      8
              9
                     8
                             8
                                     8
                                            16
                                                    16
                                                            16
                                                                     8
                                                                            8
      8
                             9
                                     8
                                                                            8
              8
                     8
                                            16
                                                                     8
                                                    16
                                                            16
      8
              8
                     9
                             8
                                     8
                                            16
                                                                     8
                                                                            8
                                                    16
                                                            16
      8
                                                                            8
              9
                      8
                             9
                                     8
                                             8
                                                     8
                                                             8
                                                                     8
      8
              8
                      8
                             8
                                     8
                                             8
                                                     9
                                                             8
                                                                     8
                                                                            8
```


Call the imreconstruct function to morphologically reconstruct the image. In the output image, note how all the intensity fluctuations except the intensity peak have been removed.

<pre>recon = imreconstruct(marker, mask)</pre>									
recon =									
10	10	10	10	10	10	10	10	10	10
10	12	12	12	10	10	10	10	10	10
10	12	12	12	10	10	10	10	10	10
10	12	12	12	10	10	10	10	10	10
10	10	10	10	10	10	10	10	10	10
10	10	10	10	10	16	16	16	10	10
10	10	10	10	10	16	16	16	10	10
10	10	10	10	10	16	16	16	10	10
10	10	10	10	10	10	10	10	10	10
10	10	10	10	10	10	10	10	10	10

Understanding Morphological Reconstruction

Morphological reconstruction can be thought of conceptually as repeated dilations of the marker image until the contour of the marker image fits under the mask image. In this way, the peaks in the marker image "spread out", or dilate.

This figure illustrates this processing in 1-D. Each successive dilation is constrained to lie underneath the mask. When further dilation ceases to change the image, processing stops. The final dilation is the reconstructed image. (Note: the actual implementation of this operation in the toolbox is done much more efficiently. See the imreconstruct reference page for more details.) The figure shows the successive dilations of the marker.



Repeated Dilations of Marker Image, Constrained by Mask

Pixel Connectivity

Morphological processing starts at the peaks in the marker image and spreads throughout the rest of the image based on the connectivity of the pixels. Connectivity defines which pixels are connected to other pixels.

For example, this binary image contains one foreground object—all the pixels that are set to 1. If the foreground is 4-connected, the image has one background object, and all the pixels are set to 0. However, if the foreground is 8-connected, the foreground makes a closed loop and the image has two separate background objects: the pixels in the loop and the pixels outside the loop.

0	0	0	0	0	0	0	0
0	1	1	1	1	1	0	0
0	1	0	0	0	1	0	0
0	1	0	0	0	1	0	0
0	1	0	0	0	1	0	0
0	1	1	1	1	0	0	0
0	0	0	0	0	0	0	0
0	0	0	0	0	0	0	0

Defining Connectivity in an Image

The following table lists all the standard two- and three-dimensional connectivities supported by the toolbox. See these sections for more information:

- "Choosing a Connectivity"
- "Specifying Custom Connectivities"

Supported Connectivities

Two-Dimensio	nal Connectivities	
4-connected	Pixels are connected if their edges touch. This means that a pair of adjoining pixels are part of the same object only if they are both on and are connected along the horizontal or vertical direction.	A P
8-connected	Pixels are connected if their edges or corners touch. This means that if two adjoining pixels are on, they are part of the same object, regardless of whether they are connected along the horizontal, vertical, or diagonal direction.	
Three-Dimensi	onal Connectivities	1
6-connected	Pixels are connected if their faces touch.	6 faces
18-connected	Pixels are connected if their faces or edges touch.	6 faces + 12 edges
26-connected	Pixels are connected if their faces, edges, or corners touch.	6 faces + 12 edges + 8 corners

Choosing a Connectivity

The type of neighborhood you choose affects the number of objects found in an image and the boundaries of those objects. For this reason, the results of many morphology operations often differ depending upon the type of connectivity you specify.

For example, if you specify a 4-connected neighborhood, this binary image contains two objects; if you specify an 8-connected neighborhood, the image has one object.

0	0	0	0	0	0
0	1	1	0	0	0
0	1	1	0	0	0
0	0	0	1	1	0
0	0	0	1	1	0

Specifying Custom Connectivities

You can also define custom neighborhoods by specifying a 3-by-3-by-...-by-3 array of 0's and 1's. The 1-valued elements define the connectivity of the neighborhood relative to the center element.

For example, this array defines a "North/South" connectivity that has the effect of breaking up an image into independent columns.

Note Connectivity arrays must be symmetric about their center element. Also, you can use a 2-D connectivity array with a 3-D image; the connectivity affects each "page" in the 3-D image.

Flood-Fill Operations

The imfill function performs a *flood-fill* operation on binary and grayscale images. For binary images, imfill changes connected background pixels (0's) to foreground pixels (1's), stopping when it reaches object boundaries. For grayscale images, imfill brings the intensity values of dark areas that are surrounded by lighter areas up to the same intensity level as surrounding pixels. (In effect, imfill removes regional minima that are not connected to the image border. See "Finding Areas of High or Low Intensity" for more information.) This operation can be useful in removing irrelevant artifacts from images.

This section includes information about

- Specifying the connectivity in flood-fill operations
- Specifying the starting point for binary image fill operations
- Filling holes in binary or grayscale images

Specifying Connectivity

For both binary and grayscale images, the boundary of the fill operation is determined by the connectivity you specify.

Note imfill differs from the other object-based operations in that it operates on *background* pixels. When you specify connectivity with imfill, you are specifying the connectivity of the background, not the foreground.

The implications of connectivity can be illustrated with this matrix.

BW = [0	0	0	0	0	0	0	0;
	0	1	1	1	1	1	0	0;
	0	1	0	0	0	1	0	0;
	0	1	0	0	0	1	0	0;
	0	1	0	0	0	1	0	0;
	0	1	1	1	1	0	0	0;
	0	0	0	0	0	0	0	0;
	0	0	0	0	0	0	0	0];

If the background is 4-connected, this binary image contains two separate background elements (the part inside the loop and the part outside). If the

background is 8-connected, the pixels connect diagonally, and there is only one background element.

Specifying the Starting Point

For binary images, you can specify the starting point of the fill operation by passing in the location subscript or by using imfill in interactive mode, selecting starting pixels with a mouse. See the reference page for imfill for more information about using imfill interactively.

For example, if you call imfill, specifying the pixel BW(4,3) as the starting point, imfill only fills the inside of the loop because, by default, the background is 4-connected.

imfill(BW,[4 3	3])					
ans =							
0	0	0	0	0	0	0	0
0	1	1	1	1	1	0	0
0	1	1	1	1	1	0	0
0	1	1	1	1	1	0	0
0	1	1	1	1	1	0	0
0	1	1	1	1	0	0	0
0	0	0	0	0	0	0	0
0	0	0	0	0	0	0	0

If you specify the same starting point, but use an 8-connected background connectivity, imfill fills the entire image.

BW,[4 3	3],8)					
1	1	1	1	1	1	1
1	1	1	1	1	1	1
1	1	1	1	1	1	1
1	1	1	1	1	1	1
1	1	1	1	1	1	1
1	1	1	1	1	1	1
1	1	1	1	1	1	1
1	1	1	1	1	1	1
	1 1 1 1 1 1 1	3W, [4 3], 8) 1				

Filling Holes


A common use of the flood-fill operation is to fill holes in images. For example, suppose you have an image, binary or grayscale, in which the foreground objects represent spheres. In the image, these objects should appear as disks, but instead are donut shaped because of reflections in the original photograph. Before doing any further processing of the image, you might want to first fill in the "donut holes" using imfill.

Because the use of flood-fill to fill holes is so common, imfill includes special syntax to support it for both binary and grayscale images. In this syntax, you just specify the argument 'holes'; you do not have to specify starting locations in each hole.

To illustrate, this example fills holes in a grayscale image of a spinal column.

```
[X,map] = imread('spine.tif');
I = ind2gray(X,map);
Ifill = imfill(I,'holes');
imshow(I);figure, imshow(Ifill)
```





Original After Filling Holes

Finding Peaks and Valleys

Grayscale images can be thought of in three dimensions: the *x*- and *y*-axes represent pixel positions and the *z*-axis represents the intensity of each pixel. In this interpretation, the intensity values represent elevations, as in a topographical map. The areas of high intensity and low intensity in an image, peaks and valleys in topographical terms, can be important morphological features because they often mark relevant image objects.

For example, in an image of several spherical objects, points of high intensity could represent the tops of the objects. Using morphological processing, these maxima can be used to identify objects in an image.


This section covers these topics:

- "Understanding the Maxima and Minima Functions"
- "Finding Areas of High or Low Intensity" on page 9-30
- "Suppressing Minima and Maxima" on page 9-31
- "Imposing a Minimum" on page 9-33

Understanding the Maxima and Minima Functions

An image can have multiple regional maxima or minima but only a single global maximum or minimum. Determining image peaks or valleys can be used to create marker images that are used in morphological reconstruction.

This figure illustrates the concept in 1-D.



Finding Areas of High or Low Intensity

The toolbox includes functions that you can use to find areas of high or low intensity in an image:

- The imregionalmax and imregionalmin functions identify *all* regional minima or maxima.
- The imextendedmax and imextendedmin functions identify all regional minima or maxima that are greater than or less than a specified threshold.

The functions accept a grayscale image as input and return a binary image as output. In the output binary image, the regional minima or maxima are set to 1; all other pixels are set to 0.

For example, this simple image contains two primary regional maxima, the blocks of pixels containing the value 13 and 18, and several smaller maxima, set to 11.

A = [10]	10	10	10	10	10	10	10	10	10;
10	13	13	13	10	10	11	10	11	10;
10	13	13	13	10	10	10	11	10	10;
10	13	13	13	10	10	11	10	11	10;
10	10	10	10	10	10	10	10	10	10;
10	11	10	10	10	18	18	18	10	10;
10	10	10	11	10	18	18	18	10	10;
10	10	11	10	10	18	18	18	10	10;
10	11	10	11	10	10	10	10	10	10;
10	10	10	10	10	10	11	10	10	10];

The binary image returned by imregionalmax pinpoints all these regional maxima.

B = imre	egiona:	lmax(A	.)						
B =									
0	0	0	0	0	0	0	0	0	0
0	1	1	1	0	0	1	0	1	0
0	1	1	1	0	0	0	1	0	0
0	1	1	1	0	0	1	0	1	0
0	0	0	0	0	0	0	0	0	0
0	1	0	0	0	1	1	1	0	0
0	0	0	1	0	1	1	1	0	0
0	0	1	0	0	1	1	1	0	0
0	1	0	1	0	0	0	0	0	0
0	0	0	0	0	0	1	0	0	0

You might want only to identify areas of the image where the change in intensity is extreme; that is, the difference between the pixel and neighboring pixels is greater than (or less than) a certain threshold. For example, to find only those regional maxima in the sample image, A, that are at least two units higher than their neighbors, use imextendedmax.

	imexte	ndedma	x(A,2)							
B =										
	0	0	0	0	0	0	0	0	0	0
	0	1	1	1	0	0	0	0	0	0
	0	1	1	1	0	0	0	0	0	0
	0	1	1	1	0	0	0	0	0	0
	0	0	0	0	0	0	0	0	0	0
	0	0	0	0	0	1	1	1	0	0
	0	0	0	0	0	1	1	1	0	0
	0	0	0	0	0	1	1	1	0	0
	0	0	0	0	0	0	0	0	0	0
	0	0	0	0	0	0	0	0	0	0

Suppressing Minima and Maxima

In an image, every small fluctuation in intensity represents a regional minimum or maximum. You might only be interested in significant minima or maxima and not in these smaller minima and maxima caused by background texture.

To remove the less significant minima and maxima but retain the significant minima and maxima, use the imhmax or imhmin function. With these functions,

you can specify a contrast criteria or threshold level, h, that suppresses all maxima whose height is less than h or whose minima are greater than h.

Note The imregionalmin, imregionalmax, imextendedmin, and imextendedmax functions return a binary image that marks the locations of the regional minima and maxima in an image. The imhmax and imhmin functions produce an altered image.


For example, this simple image contains two primary regional maxima, the blocks of pixels containing the value 14 and 18, and several smaller maxima, set to 11.

A = [10]	10	10	10	10	10	10	10	10	10;
10	14	14	14	10	10	11	10	11	10;
10	14	14	14	10	10	10	11	10	10;
10	14	14	14	10	10	11	10	11	10;
10	10	10	10	10	10	10	10	10	10;
10	11	10	10	10	18	18	18	10	10;
10	10	10	11	10	18	18	18	10	10;
10	10	11	10	10	18	18	18	10	10;
10	11	10	11	10	10	10	10	10	10;
10	10	10	10	10	10	11	10	10	10];

To eliminate all regional maxima except the two significant maxima, use imhmax, specifying a threshold value of 2. Note that imhmax only affects the maxima; none of the other pixel values are changed. The two significant maxima remain, although their heights are reduced.

В =	imhma	x(A,2)							
В =										
	10	10	10	10	10	10	10	10	10	10
	10	12	12	12	10	10	10	10	10	10
	10	12	12	12	10	10	10	10	10	10
	10	12	12	12	10	10	10	10	10	10
	10	10	10	10	10	10	10	10	10	10
	10	10	10	10	10	16	16	16	10	10
	10	10	10	10	10	16	16	16	10	10
	10	10	10	10	10	16	16	16	10	10
	10	10	10	10	10	10	10	10	10	10
	10	10	10	10	10	10	10	10	10	10

This figure takes the second row from the sample image to illustrate in 1-D how imhmax changes the profile of the image.



Imposing a Minimum

You can emphasize specific minima (dark objects) in an image using the imimposemin function. The imimposemin function uses morphological reconstruction to eliminate all minima from the image except the minima you specify.

To illustrate the process of imposing a minimum, this code creates a simple image containing two primary regional minima and several other regional minima.

```
mask = uint8(10*ones(10,10));
mask(6:8,6:8) = 2;
mask(2:4,2:4) = 7;
```

```
mask(3,3) = 5;
mask(2,9) = 9
mask(3,8) = 9
mask(9,2) = 9
mask(8,3) = 9
mask = 10
               10
                      10
                             10
                                    10
                                            10
                                                   10
                                                          10
                                                                 10
                                                                        10
        10
                7
                       7
                               7
                                     10
                                            10
                                                   10
                                                          10
                                                                  9
                                                                        10
        10
                7
                       6
                              7
                                            10
                                                   10
                                                           9
                                     10
                                                                 10
                                                                        10
        10
                7
                       7
                              7
                                                          10
                                     10
                                            10
                                                   10
                                                                 10
                                                                        10
        10
               10
                      10
                             10
                                     10
                                            10
                                                   10
                                                          10
                                                                 10
                                                                        10
                                                    2
                                                           2
        10
               10
                      10
                             10
                                     10
                                             2
                                                                 10
                                                                        10
        10
               10
                      10
                             10
                                     10
                                             2
                                                    2
                                                           2
                                                                 10
                                                                        10
        10
                                             2
                                                    2
                                                           2
               10
                       9
                             10
                                     10
                                                                 10
                                                                        10
        10
                9
                                            10
                                                   10
                                                          10
                                                                 10
                      10
                             10
                                     10
                                                                        10
```

Creating a Marker Image

To obtain an image that emphasizes the two deepest minima and removes all others, create a marker image that pinpoints the two minima of interest. You can create the marker image by explicitly setting certain pixels to specific values or by using other morphological functions to extract the features you want to emphasize in the mask image.

This example uses imextendedmin to get a binary image that shows the locations of the two deepest minima.


marker = i	mexten	dedmin	(mask,	1)					
marker = 0	0	0	0	0	0	0	0	0	0
0	0	0	0	0	0	0	0	0	0
0	0	1	0	0	0	0	0	0	0
0	0	0	0	0	0	0	0	0	0
0	0	0	0	0	0	0	0	0	0
0	0	0	0	0	1	1	1	0	0
0	0	0	0	0	1	1	1	0	0
0	0	0	0	0	1	1	1	0	0
0	0	0	0	0	0	0	0	0	0
0	0	0	0	0	0	0	0	0	0

Applying the Marker Image to the Mask

Now use imimposemin to create new minima in the mask image at the points specified by the marker image. Note how imimposemin sets the values of pixels specified by the marker image to the lowest value supported by the datatype (0 for uint8 values). imimposemin also changes the values of all the other pixels in the image to eliminate the other minima.

```
I = imimposemin(mask,marker)
I =
     11
             11
                     11
                             11
                                     11
                                             11
                                                    11
                                                            11
                                                                    11
                                                                            11
     11
              8
                      8
                              8
                                     11
                                             11
                                                    11
                                                            11
                                                                    11
                                                                            11
              8
                              8
     11
                      0
                                     11
                                             11
                                                    11
                                                            11
                                                                    11
                                                                            11
     11
              8
                      8
                              8
                                                    11
                                     11
                                             11
                                                            11
                                                                    11
                                                                            11
     11
             11
                     11
                             11
                                     11
                                             11
                                                     11
                                                            11
                                                                    11
                                                                            11
     11
             11
                     11
                                     11
                                              0
                                                      0
                                                              0
                                                                    11
                             11
                                                                            11
     11
             11
                     11
                             11
                                     11
                                              0
                                                      0
                                                              0
                                                                    11
                                                                            11
                                                      0
                                                              0
     11
             11
                     11
                             11
                                     11
                                              0
                                                                    11
                                                                            11
     11
             11
                     11
                             11
                                     11
                                             11
                                                     11
                                                            11
                                                                    11
                                                                            11
     11
             11
                     11
                             11
                                     11
                                             11
                                                    11
                                                            11
                                                                    11
                                                                            11
```

This figure illustrates in 1-D how imimposemin changes the profile of row 2 of the image.



Imposing a Minimum

Distance Transform

The distance transform provides a metric or measure of the separation of points in the image. The Image Processing Toolbox provides a function, bwdist, that calculates the distance between each pixel that is set to off (0) and the nearest nonzero pixel for binary images.

The bwdist function supports several distance metrics, listed in the following table.

Distance Metrics

Distance Metric	Description	Illustration	
Euclidean	The Euclidean distance is the straight-line distance between two pixels.		
City Block	The city block distance metric measures the path between the pixels based on a 4-connected neighborhood. Pixels whose edges touch are 1 unit apart; pixels diagonally touching are 2 units apart.	0 0 0 0 2 1 2 1 2 1 1 1 2 1	1 2



Distance Metrics (Continued)

Distance Metric	Description	Illustration					
Chessboard	The chessboard distance metric measures the path between the pixels based on an 8-connected neighborhood. Pixels whose edges or corners touch are 1 unit apart.	0					
Quasi-Euclidean	The quasi-Euclidean metric measures the total Euclidean distance along a set of horizontal, vertical, and diagonal line segments.	0 0 0 0 0 0 0 2.8 2.2 2.0 2.2 2.8 2.2 1.4 1.0 1.4 2.2 2.0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0					

This example creates a binary image containing two intersecting circular objects.

```
center1 = -10;
center2 = -center1;
dist = sqrt(2*(2*center1)^2);
radius = dist/2 * 1.4;
lims = [floor(center1-1.2*radius) ceil(center2+1.2*radius)];
[x,y] = meshgrid(lims(1):lims(2));
bw1 = sqrt((x-center1).^2 + (y-center1).^2) \le radius;
bw2 = sqrt((x-center2).^2 + (y-center2).^2) \le radius;
bw = bw1 \mid bw2;
figure, imshow(bw), title('bw')
```



To compute the distance transform of the complement of the binary image, use the bwdist function. In the image of the distance transform, note how the centers of the two circular areas are white.

```
D = bwdist(~bw);
figure, imshow(D,[]), title('Distance transform of ~bw')
```



Objects, Regions, and Feature Measurement

The toolbox includes several functions that return information about the features in a binary image, including

- Connected-component labeling, and using the label matrix to get statistics about an image
- Selecting objects in a binary image
- Finding the area of the foreground of a binary image
- Finding the Euler number of a binary image

Connected-Component Labeling

The bwlabel and the bwlabeln functions perform *connected-component labeling*, which is a method for identifying each object in a binary image. The bwlabel function supports 2-D inputs only; the bwlabeln function supports inputs of any dimension.

These functions return a matrix, called a *label matrix*. A label matrix is an image, the same size as the input image, in which the objects in the input image are distinguished by different integer values in the output matrix. For example, bwlabel can identify the objects in this binary image.

BW = [0	0	0	0	0	0	0	0;
0	1	1	0	0	1	1	1;
0	1	1	0	0	0	1	1;
0	1	1	0	0	0	0	0;
0	0	0	1	1	0	0	0;
0	0	0	1	1	0	0	0;
0	0	0	1	1	0	0	0;
0	0	0	0	0	0	0	0];

Χ	=	bwlabe	el(BW,4	1)					
Χ	=								
		0	0	0	0	0	0	0	0
		0	1	1	0	0	3	3	3
		0	1	1	0	0	0	3	3
		0	1	1	0	0	0	0	0
		0	0	0	2	2	0	0	0
		0	0	0	2	2	0	0	0
		0	0	0	2	2	0	0	0
		0	0	0	0	0	0	0	0


In the output matrix, the 1's represent one object, the 2's a second object, and the 3's a third. (If you had used 8-connected neighborhoods (the default), there would be only two objects, because the first and second objects would be a single object, connected along the diagonal.)

Viewing a Label Matrix

The label matrix returned by bwlabel or bwlabeln is of class double; it is not a binary image. One way to view it is to display it as a pseudocolor indexed image, using label2rgb. In the pseudocolor image, each number that identifies an object in the label matrix is used as an index value into the associated colormap matrix. When you view a label matrix as an RGB image, the objects in the image are easier to distinguish.

To illustrate this technique, this example uses label2rgb to view the label matrix X. The call to label2rgb specifies one of the standard MATLAB colormaps, jet. The third argument, 'k', specifies the background color (black).

```
X = bwlabel(BW1,4);
RGB = label2rgb(X, @jet, 'k');
imshow(RGB,'notruesize')
```



Using Color to Distinguish Objects in a Binary Image

Selecting Objects in a Binary Image

You can use the bwselect function to select individual objects in a binary image. You specify pixels in the input image, and bwselect returns a binary image that includes only those objects from the input image that contain one of the specified pixels.

You can specify the pixels either noninteractively or with a mouse. For example, suppose you want to select objects in the image displayed in the current axes. You type

BW2 = bwselect;

The cursor changes to crosshairs when it is over the image. Click the objects you want to select; bwselect displays a small star over each pixel you click. When you are done, press **Return**. bwselect returns a binary image consisting of the objects you selected, and removes the stars.

See the reference page for bwselect for more information.

Finding the Area of the Foreground of a Binary Image

The bwarea function returns the area of a binary image. The area is a measure of the size of the foreground of the image. Roughly speaking, the area is the number of on pixels in the image.

bwarea does not simply count the number of pixels set to on, however. Rather, bwarea weights different pixel patterns unequally when computing the area. This weighting compensates for the distortion that is inherent in representing a continuous image with discrete pixels. For example, a diagonal line of 50 pixels is longer than a horizontal line of 50 pixels. As a result of the weighting bwarea uses, the horizontal line has area of 50, but the diagonal line has area of 62.5.

This example uses bwarea to determine the percentage area increase in circbw.tif that results from a dilation operation.

```
BW = imread('circbw.tif');
SE = ones(5);
BW2 = imdilate(BW,SE);
increase = (bwarea(BW2) - bwarea(BW))/bwarea(BW);
increase =
0.3456
```

See the reference page for bwarea for more information about the weighting pattern.

Finding the Euler Number of a Binary Image

The bweuler function returns the Euler number for a binary image. The Euler number is a measure of the topology of an image. It is defined as the total number of objects in the image minus the number of holes in those objects. You can use either 4- or 8-connected neighborhoods.

This example computes the Euler number for the circuit image, using 8-connected neighborhoods.

```
BW1 = imread('circbw.tif');
eul = bweuler(BW1,8)

eul =
   -85
```

In this example, the Euler number is negative, indicating that the number of holes is greater than the number of objects.

Lookup Table Operations

Certain binary image operations can be implemented most easily through lookup tables. A lookup table is a column vector in which each element represents the value to return for one possible combination of pixels in a neighborhood.

You can use the makelut function to create lookup tables for various operations. makelut creates lookup tables for 2-by-2 and 3-by-3 neighborhoods. This figure illustrates these types of neighborhoods. Each neighborhood pixel is indicated by an x, and the center pixel is the one with a circle.



 x
 x
 x

 x
 x
 x

 x
 x
 x

2-by-2 neighborhood

3-by-3 neighborhood

For a 2-by-2 neighborhood, there are 16 possible permutations of the pixels in the neighborhood. Therefore, the lookup table for this operation is a 16-element vector. For a 3-by-3 neighborhood, there are 512 permutations, so the lookup table is a 512-element vector.

Once you create a lookup table, you can use it to perform the desired operation by using the applylut function.

The example below illustrates using lookup table operations to modify an image containing text. You begin by writing a function that returns 1 if three or more pixels in the 3-by-3 neighborhood are 1; otherwise, it returns 0. You then call makelut, passing in this function as the first argument, and using the second argument to specify a 3-by-3 lookup table.

```
f = inline('sum(x(:)) >= 3');
lut = makelut(f,3);
```

lut is returned as a 512-element vector of 1's and 0's. Each value is the output from the function for one of the 512 possible permutations.

You then perform the operation using applylut.

```
BW1 = imread('text.png');
BW2 = applylut(BW1,lut);
imshow(BW1)
figure, imshow(BW2)
```





Image Before and After Applying Lookup Table Operation

For information about how applylut maps pixel combinations in the image to entries in the lookup table, see the reference page for applylut.

Note You cannot use makelut and applylut for neighborhoods of sizes other than 2-by-2 or 3-by-3. These functions support only 2-by-2 and 3-by-3 neighborhoods, because lookup tables are not practical for neighborhoods larger than 3-by-3. For example, a lookup table for a 4-by-4 neighborhood would have 65,536 entries.

Analyzing and Enhancing Images

This chapter describes the Image Processing Toolbox functions that support a range of standard image processing operations for analyzing and enhancing images.

Terminology (p. 10-2) Provides definitions of image processing terms used in

this section

Pixel Values and Statistics (p. 10-3) Describes the toolbox functions that return information

about the data values that make up an image

Image Analysis (p. 10-13) Describes the toolbox functions that return information

about the structure of an image

Texture Analysis (p. 10-26) Describes the toolbox functions that return information

about the texture of an image

Intensity Adjustment (p. 10-36) Describes the toolbox functions used to improve an image

by intensity adjustment

Noise Removal (p. 10-49) Describes the toolbox functions used to improve an image

by removing noise

Terminology

An understanding of the following terms will help you to use this chapter.

Term	Definition						
adaptive filter	Filter whose properties vary across an image depending on the local characteristics of the image pixels.						
contour	Path in an image along which the image intensity values are equal to a constant.						
edge	Curve that follows a path of rapid change in image intensity. Edges are often associated with the boundaries of objects in a scene. Edge detection is used to identify the edges in an image.						
property	Quantitative measurement of an image or image region. Examples of image region properties include centroid, bounding box, and area.						
histogram	Graph used in image analysis that shows the distribution of intensities in an image. You can use the information in a histogram to choose an appropriate enhancement operation. For example, if an image histogram shows that the range of intensity values is small, you can use an intensity adjustment function to spread the values across a wider range.						
noise	Errors in the image acquisition process that result in pixel values that do not reflect the true intensities of the real scene.						
profile	Set of intensity values taken from regularly spaced points along a line segment or multiline path in an image. For points that do not fall on the center of a pixel, the intensity values are interpolated.						
quadtree decomposition	Image analysis technique that partitions an image into homogeneous blocks.						

Pixel Values and Statistics

The Image Processing Toolbox provides several functions that return information about the data values that make up an image. These functions return information about image data in various forms, including

- Data values for selected pixels (pixval, impixel)
- Data values along a path in an image (improfile)
- Contour plot of the image data (imcontour)
- Histogram of the image data (imhist)
- Summary statistics for the image data (mean2, std2, corr2)
- Feature measurements for image regions (regionprops)

Pixel Selection

The toolbox includes two functions that provide information about the values of pixels in an image.

- The pixval function interactively displays the data values for pixels as you move the cursor over the image. pixval can also display the Euclidean distance between two pixels.
- The impixel function returns the data values for a selected pixel or set of pixels. You can supply the coordinates of the pixels as input arguments, or you can select pixels using a mouse.

Note You can also get pixel value information interactively using the Image Tool — see "Getting Information about the Pixels in an Image" on page 3-22.

Getting Pixel Information with pixval

To use pixval, you first display an image and then enter the pixval command. pixval installs a black bar at the bottom of the figure, which displays the (x,y) coordinates for whatever pixel the cursor is currently over and the color data for that pixel.

If you click the image and hold down the mouse button while you move the cursor, pixval also displays the Euclidean distance between the point you

clicked and the current cursor location, pixval draws a line between these points to indicate the distance being measured. When you release the mouse button, the line and the distance display disappear.

Getting Pixel Information with impixel

impixel provides pixel information in a variable in the MATLAB workspace.

If you call impixel with no input arguments, the function associates itself with the image in the current axes. The cursor changes to crosshairs when it is over the image. You can then click the pixels of interest; impixel displays a small star over each pixel you select. When you are done selecting pixels, press **Return**. impixel returns the color values for the selected pixels, and the stars disappear.

This example illustrates how to use impixel:

1 Display an image.

imshow cance.tif

2 Call impixel to select points.

vals = impixel

Click several points in the image to select pixels. When you are finished selecting points, press **Return**.



The impixel function returns the pixel values in vals.

vals =

0.1294	0.1294	0.1294
0.5176	0	0
0.7765	0.6118	0.4196

Intensity Profile

The improfile function calculates and plots the intensity values along a line segment or a multiline path in an image. You can supply the coordinates of the line segments as input arguments, or you can define the desired path using a mouse. In either case, improfile uses interpolation to determine the values of equally spaced points along the path. (By default, improfile uses nearest-neighbor interpolation, but you can specify a different method. For more information, see "Interpolation" on page 5-3.) improfile works best with intensity and RGB images.

For a single line segment, improfile plots the intensity values in a two-dimensional view. For a multiline path, improfile plots the intensity values in a three-dimensional view.

If you call improfile with no arguments, the cursor changes to crosshairs when it is over the image. You can then specify line segments by clicking the endpoints; improfile draws a line between each two consecutive points you select. When you finish specifying the path, press Return. improfile displays the plot in a new figure.

In this example, you call improfile and specify a single line with the mouse. In this figure, the line is shown in red, and is drawn from top to bottom.

```
I = fitsread('solarspectra.fts');
imshow(I,[]);
improfile
```





Image Courtesy of Ann Walker

improfile displays a plot of the data along the line. Notice the peaks and valleys and how they correspond to the light and dark bands in the image.



Plot Produced by improfile


The example below shows how improfile works with an RGB image. Use imshow to display the image in a figure window. Call improfile without any arguments and trace a line segment in the image interactively. In the figure, the black line indicates a line segment drawn from top to bottom. Double-click to end the line segment.

imshow peppers.png
improfile



RGB Image with Line Segment Drawn with improfile

The improfile function displays a plot of the intensity values along the line segment. The plot includes separate lines for the red, green, and blue intensities. In the plot, notice how low the blue values are at the beginning of the plot where the line traverses the orange pepper.



Plot of Intensity Values Along a Line Segment in an RGB Image

Image Contours

You can use the toolbox function imcontour to display a contour plot of the data in an intensity image. This function is similar to the contour function in MATLAB, but it automatically sets up the axes so their orientation and aspect ratio match the image.

This example displays an intensity image of grains of rice and a contour plot of the image data:


1 Read an intensity image and display it.

```
I = imread('rice.png');
imshow(I)
```



2 Display a contour plot of the intensity image.

figure, imcontour(I,3)



You can use the clabel function to label the levels of the contours. See the description of clabel in the MATLAB Function Reference for details.

Image Histogram

An image histogram is a chart that shows the distribution of intensities in an indexed or intensity image. The image histogram function imhist creates this plot by making n equally spaced bins, each representing a range of data values. It then calculates the number of pixels within each range.


The following example displays an image of grains of rice and a histogram based on 64 bins. The histogram shows a peak at around 100, corresponding to the dark gray background in the image. For information about how to modify an image by changing the distribution of its histogram, see "Adjusting Intensity Values to a Specified Range" on page 10-37.

1 Read image and display it.



2 Display histogram of image.

figure, imhist(I)



Summary Statistics

You can compute standard statistics of an image using the mean2, std2, and corr2 functions. mean2 and std2 compute the mean and standard deviation of the elements of a matrix. corr2 computes the correlation coefficient between two matrices of the same size.

These functions are two-dimensional versions of the mean, std, and corrcoef functions described in the MATLAB Function Reference.

Region Property Measurement

You can use the regionprops function to compute properties for image regions. For example, regionprops can measure such properties as the area, center of mass, and bounding box for a region you specify. See the reference page for regionprops for more information.

Image Analysis

Image analysis techniques return information about the structure of an image. This section describes toolbox functions that you can use for these image analysis techniques:

- "Edge Detection"
- "Boundary Tracing" on page 10-15
- "Line Detection Using the Hough Transform" on page 10-19
- "Quadtree Decomposition" on page 10-24

The toolbox also includes functions that return information about the texture of an image. See "Texture Analysis" on page 10-26 for more information.

Edge Detection

You can use the edge function to detect edges, which are those places in an image that correspond to object boundaries. To find edges, this function looks for places in the image where the intensity changes rapidly, using one of these two criteria:

- Places where the first derivative of the intensity is larger in magnitude than some threshold
- Places where the second derivative of the intensity has a zero crossing

edge provides a number of derivative estimators, each of which implements one of the definitions above. For some of these estimators, you can specify whether the operation should be sensitive to horizontal edges, vertical edges, or both. edge returns a binary image containing 1's where edges are found and 0's elsewhere.

The most powerful edge-detection method that edge provides is the Canny method. The Canny method differs from the other edge-detection methods in that it uses two different thresholds (to detect strong and weak edges), and includes the weak edges in the output only if they are connected to strong edges. This method is therefore less likely than the others to be fooled by noise, and more likely to detect true weak edges.

The following example illustrates the power of the Canny edge detector by showing the results of applying the Sobel and Canny edge detectors to the same image:


1 Read image and display it.

```
I = imread('coins.png');
imshow(I)
```



2 Apply the Sobel and Canny edge detectors to the image and display them.

```
BW1 = edge(I,'sobel');
BW2 = edge(I, 'canny');
imshow(BW1)
figure, imshow(BW2)
```







Canny Filter

For an interactive demonstration of edge detection, try running edgedemo.

Boundary Tracing

The toolbox includes two functions you can use to find the boundaries of objects in a binary image:

- bwtraceboundary
- bwboundaries

The bwtraceboundary function returns the row and column coordinates of all the pixels on the border of an object in an image. You must specify the location of a border pixel on the object as the starting point for the trace.

The bwboundaries function returns the row and column coordinates of border pixels of all the objects in an image.

For both functions, the nonzero pixels in the binary image belong to an object and pixels with the value 0 (zero) constitute the background.

The following example uses bwtraceboundary to trace the border of an object in a binary image and then uses bwboundaries to trace the borders of all the objects in the image:


1 Read image and display it.

```
I = imread('coins.png');
imshow(I)
```



2 Convert the image to a binary image. bwtraceboundary and bwboundaries only work with binary images.

```
BW = im2bw(I);
imshow(BW)
```



3 Determine the row and column coordinates of a pixel on the border of the object you want to trace. bwboundary uses this point as the starting location for the boundary tracing.

```
dim = size(BW)
col = round(dim(2)/2)-90;
row = min(find(BW(:,col)))
```

4 Call by by trace boundary to trace the boundary from the specified point. As required arguments, you must specify a binary image, the row and column coordinates of the starting point, and the direction of the first step. The example specifies north ('N'). For information about this parameter, see "Choosing the First Step and Direction for Boundary Tracing" on page 10-18.

```
boundary = bwtraceboundary(BW,[row, col],'N');
```

5 Display the original grayscale image and use the coordinates returned by bwtraceboundary to plot the border on the image.

```
imshow(I)
hold on;
plot(boundary(:,2),boundary(:,1),'g','LineWidth',3);
```






6 To trace the boundaries of all the coins in the image, use the bwboundaries function. By default, bwboundaries finds the boundaries of all objects in an image, including objects inside other objects. In the binary image used in this example, some of the coins contain black areas that bwboundaries interprets as separate objects. To ensure that bwboundaries only traces the coins, use imfill to fill the area inside each coin.

```
BW_filled = imfill(BW, 'holes');
boundaries = bwboundaries(BW filled);
```

bwboundaries returns a cell array, where each cell contains the row/column coordinates for an object in the image.

7 Plot the borders of all the coins on the original grayscale image using the coordinates returned by bwboundaries.

```
for k=1:10
    b = boundaries{k};
    plot(b(:,2),b(:,1),'g','LineWidth',3);
end
```




Choosing the First Step and Direction for Boundary Tracing

For certain objects, you must take care when selecting the border pixel you choose as the starting point and the direction you choose for the first step parameter (north, south, etc.).

For example, if an object contains a hole and you select a pixel on a thin part of the object as the starting pixel, you can trace the outside border of the object or the inside border of the hole, depending on the direction you choose for the first step. For filled objects, the direction you select for the first step parameter is not as important.

To illustrate, this figure shows the pixels traced when the starting pixel is on a thin part of the object and the first step is set to north and south. The connectivity is set to 8 (the default).



Impact of First Step and Direction Parameters on Boundary Tracing

Line Detection Using the Hough Transform

The Image Processing Toolbox includes functions that support the Hough transform.

- hough
- houghpeaks
- houghlines

The hough function implements the Standard Hough Transform (SHT). The Hough transform is designed to detect lines, using the parametric representation of a line:

```
rho = x*cos(theta) + y*sin(theta)
```

The variable rho is the distance from the origin to the line along a vector perpendicular to the line. theta is the angle between the x-axis and this vector. The hough function generates a parameter space matrix whose rows and columns correspond to these rho and theta values, respectively.

The houghpeaks function finds peak values in this space, which represent potential lines in the input image.

The houghlines function finds the endpoints of the line segments corresponding to peaks in the Hough transform and it automatically fills in small gaps.


The following example shows how to use these functions to detect lines in an image.

1 Read an image into the MATLAB workspace.

```
I = imread('circuit.tif');
```


2 For this example, rotate and crop the image.

```
rotI = imrotate(I,33,'crop');
```



3 Find the edges in the image.


BW = edge(rotI, 'canny');



4 Compute the Hough transform of the image using the hough function.


```
[H,theta,rho] = hough(BW);
```

5 Display the transform.



6 Find the peaks in the Hough transform matrix, H, using the houghpeaks function.

```
P = houghpeaks(H, 5, 'threshold', ceil(0.3*max(H(:))));
7 Plot the peaks.
  x = theta(P(:,2));
  y = rho(P(:,1));
  plot(x,y,'s','color','white');
8 Find lines in the image.
  lines = houghlines(BW,theta,rho,P,'FillGap',5,'MinLength',7);
9 Create a plot that superimposes the lines on the original image.
  figure, imshow(rotI), hold on
  \max len = 0;
  for k = 1:length(lines)
     xy = [lines(k).point1; lines(k).point2];
     plot(xy(:,1),xy(:,2),'LineWidth',2,'Color','green');
     % Plot beginnings and ends of lines
     plot(xy(1,1),xy(1,2),'x','LineWidth',2,'Color','yellow');
     plot(xy(2,1),xy(2,2),'x','LineWidth',2,'Color','red');
     % Determine the endpoints of the longest line segment
     len = norm(lines(k).point1 - lines(k).point2);
     if (len > max len)
        \max len = len;
        xy long = xy;
     end
  end
  % highlight the longest line segment
  plot(xy_long(:,1),xy_long(:,2),'LineWidth',2,'Color','cyan');
```



Quadtree Decomposition

Quadtree decomposition is an analysis technique that involves subdividing an image into blocks that are more homogeneous than the image itself. This technique reveals information about the structure of the image. It is also useful as the first step in adaptive compression algorithms.

You can perform quadtree decomposition using the atdecomp function. This function works by dividing a square image into four equal-sized square blocks, and then testing each block to see if it meets some criterion of homogeneity (e.g., if all the pixels in the block are within a specific dynamic range). If a block meets the criterion, it is not divided any further. If it does not meet the criterion, it is subdivided again into four blocks, and the test criterion is applied to those blocks. This process is repeated iteratively until each block meets the criterion. The result might have blocks of several different sizes.

Example: Performing Quadtree Decomposition

To illustrate, this example performs quadtree decomposition on a 512-by-512 intensity image. For an interactive demonstration of quadtree decomposition, run the demo atdemo.

1 Read in the intensity image.

```
I = imread('liftingbody.png');
```

2 Specify the test criteria used to determine the homogeneity of each block in the decomposition. For example, the criterion might be this threshold calculation.

```
max(block(:)) - min(block(:)) \le 0.2
```

You can also supply qtdecomp with a function (rather than a threshold value) for deciding whether to split blocks; for example, you might base the decision on the variance of the block. See the reference page for gtdecomp for more information.

3 Perform this quadtree decomposition by calling the qtdecomp function, specifying the image and the threshold value as arguments.

```
S = qtdecomp(I, 0.27)
```

You specify the threshold as a value between 0 and 1, regardless of the class of I. If I is uint8, gtdecomp multiplies the threshold value by 255 to

determine the actual threshold to use. If I is uint16, qtdecomp multiplies the threshold value by 65535.

qtdecomp first divides the image into four 256-by-256 blocks and applies the test criterion to each block. If a block does not meet the criterion, qtdecomp subdivides it and applies the test criterion to each block. qtdecomp continues to subdivide blocks until until all blocks meet the criterion. Blocks can be as small as 1-by-1, unless you specify otherwise.

qtdecomp returns S as a sparse matrix, the same size as I. The nonzero elements of S represent the upper left corners of the blocks; the value of each nonzero element indicates the block size.

The following figure shows the original image and a representation of its quadtree decomposition. (To see how this representation was created, see the example on the qtdecomp reference page.) Each black square represents a homogeneous block, and the white lines represent the boundaries between blocks. Notice how the blocks are smaller in areas corresponding to large changes in intensity in the image.






Image Courtesy of NASA

Image and a Representation of Its Quadtree Decomposition

Texture Analysis

The toolbox supports a set of functions that you can use for texture analysis. Texture analysis refers to the characterization of regions in an image by their texture content. Texture analysis attempts to quantify intuitive qualities described by terms such as rough, smooth, silky, or bumpy as a function of the spatial variation in pixel intensities. In this sense, the roughness or bumpiness refers to variations in the intensity values, or gray levels.

Texture analysis is used in a variety of applications, including remote sensing, automated inspection, and medical image processing. Texture analysis can be used to find the texture boundaries, called texture segmentation. Texture analysis can be helpful when objects in an image are more characterized by their texture than by intensity, and traditional thresholding techniques cannot be used effectively.

The toolbox provides two types of texture functions:

- Texture filter functions These functions use standard statistical measures to characterize the local texture of an image. See "Texture Filter Functions" on page 10-26 for more information.
- Gray-level co-occurrence matrix These functions characterize the texture of an image by calculating how often pairs of pixel with specific values and in a specified spatial relationship occur in an image and then extracting statistical measures from this matrix. See "Gray-Level Co-occurrence Matrix (GLCM)" on page 10-29 for more information

Texture Filter Functions

The toolbox includes three texture analysis functions that filter an image using standard statistical measures, such as range, standard deviation, and entropy. Entropy is a statistical measure of randomness. These statistics can characterize the texture of an image because they provide information about the local variability of the intensity values of pixels in an image.

For example, in areas with smooth texture, the range of values in the neighborhood around a pixel will be a small value; in areas of rough texture, the range will be larger. Similarly, calculating the standard deviation of pixels in a neighborhood can indicate the degree of variability of pixel values in that region.

The following sections provide additional information about the texture functions:

- "Understanding the Texture Filter Functions" on page 10-27
- "Example: Using the Texture Functions" on page 10-28

Understanding the Texture Filter Functions

The three statistical texture filtering functions are:

rangefilt — Calculates the local range of an image


stdfilt — Calculates the local standard deviation of an image

entropyfilt — Calculates the local entropy of an intensity image

The functions all operate in a similar way: they define a neighborhood around the pixel of interest and calculate the statistic for that neighborhood.

This example shows how the rangefilt function operates on a simple array.

The following figure shows how the value of element B(2,4) was calculated from A(2,4). By default, the rangefilt function uses a 3-by-3 neighborhood but you can specify neighborhoods or different shapes and sizes.



Determining Pixel Values in Range Filtered Output Image

The stdfilt and entropyfilt functions operate similarly, defining a neighborhood around the pixel of interest and calculating the statistic for the neighborhood to determine the pixel value in the output image. The stdfilt function calculates the standard deviation of all the values in the neighborhood.

The entropyfilt function calculates the entropy of the neighborhood and assigns that value to the output pixel. Note that, by default, the entropyfilt function defines a 9-by-9 neighborhood around the pixel of interest. To calculate the entropy of an entire image, use the entropy function.

Example: Using the Texture Functions

The following example illustrates how the texture filter functions can detect regions of texture in an image. In the figure, the background is smooth; very little variation in the gray-level values. In the foreground, the surface contours of the coins exhibit more texture. Thus, in this image, foreground pixels have more variability and thus higher range values. In this case, range filtering makes the edges and contours of the coins more visible.

To see an example of using filtering functions, view the Texture Segmentation Using Texture Filters demo.

1 Read in the image and display it.


```
I = imread('eight.tif');
```

imshow(I)



2 Filter the image with the rangefilt function and display the results. Note how range filtering highlights the edges and surface contours of the coins.

```
K = rangefilt(I);
figure, imshow(K)
```



Gray-Level Co-occurrence Matrix (GLCM)

The texture filter functions provide a statistical view of texture based on the image histogram. These functions can provide useful information about the texture of an image but cannot provide information about shape, i.e. the spatial relationships of pixels in an image.

Another statistical method that considers the spatial relationship of pixels is the grey-level co-occurrence matrix (GLCM), also known as the gray-level spatial dependence matrix. The toolbox provides functions to create a GLCM and derive statistical measurements from it.

This section includes the following topics.

- "Creating a Grav-level Co-occurrence Matrix" on page 10-30
- "Specifying the Offsets" on page 10-31
- "Deriving Statistics from a GLCM" on page 10-32
- "Example: Plotting the Correlation" on page 10-33

Creating a Gray-level Co-occurrence Matrix

To create a GLCM, use the graycomatrix function. The graycomatrix function creates a gray-level co-occurrence matrix (GLCM) by calculating how often a pixel with the intensity (gray-level) value i occurs in a specific spatial relationship to a pixel with the value j. By default, the spatial relationship is defined as the pixel of interest and the pixel to its immediate right (horizontally adjacent), but you can specify other spatial relationships between the two pixels. Each element (i,j) in the resultant glcm is simply the sum of the number of times that the pixel with value i occurred in the specified spatial relationship to a pixel with value *i* in the input image.

Because the processing required to calculate a GLCM for the full dynamic range of an image is prohibitive, graycomatrix scales the input image. By default, graycomatrix uses scaling to reduce the number of intensity values in intensity image from 256 to eight. The number of gray-levels determines the size of the GLCM. To control the number of gray-levels in the GLCM and the scaling of intensity values, using the 'NumLevels' and the 'GrayLimits' parameters of the graycomatrix function. See the graycomatrix reference page for more information.

The gray-level co-occurrence matrix can reveal certain properties about the spatial distribution of the gray levels in the texture image. For example, if most of the entries in the GLCM are concentrated along the diagonal, the texture is coarse with respect to the specified offset. However, you can also derive several statistical measures from the GLCM. See "Deriving Statistics from a GLCM" on page 10-32 for more information.

To illustrate, the following figure shows how graycomatrix calculates the first three values in a GLCM. In the output GLCM, element (1.1) contains the value 1 because there is only one instance in the input image where two, horizontally adjacent pixels have the values 1 and 1, respectively. glcm(1,2) contains the value 2 because there are two instances where two, horizontally adjacent pixels have the values 1 and 2. Element (1,3) in the GLCM has the value 0 because there are no instances of two horizontally adjacent pixels with the value 1 and 3. graycomatrix continues processing the input image, scanning the image for other pixel pairs (i,j) and recording the sum in the corresponding element of the GLCM.

								1	2	3	4	5	6	7	8
1	1	1	5	6	8	GLCM	1	1	2	0	0	1	0	0	0
	2	3	5	7	1	-	2	0	9 0	1	0	1	0	0	0
	4	5	7(1	2	<u></u>	3	8	0	0	0	1	0	0	0
	8	5 (1	2	5		4	0	0	0	0	1	0	0	0
•							5	_1	0	0	0	0	1	2	0
							6	0	0	0	0	0	0	0	1
							7	2	0	0	0	0	0	0	0
							8	0	0	0	0	1	0	0	0

Process Used to Create the GLCM

Specifying the Offsets


By default, the graycomatrix function creates a single GLCM, with the spatial relationship, or *offset*, defined as two horizontally adjacent pixels. However, a single GLCM might not be enough to describe the textural features of the input image. For example, a single horizontal offset might not be sensitive to texture with a vertical orientation. For this reason, graycomatrix can create multiple GLCMs for a single input image.

To create multiple GLCMs, specify an array of offsets to the graycomatrix function. These offsets define pixel relationships of varying direction and distance. For example, you can define an array of offsets that specify four directions (horizontal, vertical, and two diagonals) and four distances. In this case, the input image is represented by 16 GLCMs. When you calculate statistics from these GLCMs, you can take the average.

You specify these offsets as a p-by-2 array of integers. Each row in the array is a two-element vector, [row offset, col offset], that specifies one offset. row offset is the number of rows between the pixel-of-interest and its neighbor. col offset is the number of columns between the pixel-of-interest and its neighbor. This example creates an offset that specifies four directions and 4 distances for each direction. For more information about specifying offsets, see the graycomatrix reference page.

```
offsets = [ 0 1; 0 2; 0 3; 0 4;...
           -1 1; -2 2; -3 3; -4 4;...
           -1 0; -2 0; -3 0; -4 0;...
           -1 -1; -2 -2; -3 -3; -4 -4];
```

The figure illustrates the spatial relationships of pixels that are defined by this array of offsets.



Deriving Statistics from a GLCM

After you create the GLCMs, you can derive several statistics from them using the graycoprops function. These statistics provide information about the texture of an image. The following table lists the statistics you can derive. You specify which statistics you want when you call the graycoprops function. For

detailed information about these statistics, see the graycoprops reference page.


Statistic	Description
Contrast	Measures the local variations in the gray-level co-occurrence matrix.
Correlation	Measures the joint probability occurrence of the specified pixel pairs.
Energy	Provides the sum of squared elements in the GLCM. Also known as uniformity or the angular second moment.
Homogeneity	Measures the closeness of the distribution of elements in the GLCM to the GLCM diagonal.

Example: Plotting the Correlation

This example illustrates how the statistics returned by graycoprops has a direct relationship to the original input image. The example shows how to create a set of GLCMs and derive statistics from them.

1 Read in an intensity image and display it. The example converts the truecolor (RGB) image to a grayscale intensity image and then rotates it 90° for this example.

```
circuitBoard = rot90(rgb2gray(imread('board.tif')));
imshow(circuitBoard)
```



2 Define offsets of varying direction and distance. Because the image contains objects of a variety of shapes and sizes that are arranged in horizontal and vertical directions, the example specifies a set of horizontal offsets that only vary in distance.


```
offsets0 = [zeros(40,1) (1:40)'];
```

- **3** Create the GLCMs. Call the graycomatrix function specifying the offsets. glcms = graycomatrix(circuitBoard, 'Offset', offsets0)
- **4** Derive statistics from the GLCMs using the graycoprops function. The example calculates the contrast and correlation.


```
stats = graycoprops(glcms, 'Contrast Correlation');
```

5 Plot correlation as a function of offset.

```
figure, plot([stats.Correlation]);
title('Texture Correlation as a function of offset');
xlabel('Horizontal Offset')
ylabel('Correlation')
```



The plot contains peaks at offsets 7, 15, 23, and 30. If you examine the input image closely, you can see that certain vertical elements in the image have a periodic pattern that repeat every seven pixels. The following figure shows the upper left corner of the image and points out where this pattern occurs.




Intensity Adjustment

Image enhancement techniques are used to improve an image, where "improve" is sometimes defined objectively (e.g., increase the signal-to-noise ratio), and sometimes subjectively (e.g., make certain features easier to see by modifying the colors or intensities).

Intensity adjustment is an image enhancement technique that maps an image's intensity values to a new range. To illustrate, this figure shows a low-contrast image with its histogram. Notice in the histogram of the image how all the values gather in the center of the range.

```
I = imread('pout.tif');
imshow(I)
figure, imhist(I,64)
```



If you remap the data values to fill the entire intensity range [0, 255], you can increase the contrast of the image. The following sections describe several intensity adjustment techniques, including

- "Adjusting Intensity Values to a Specified Range" on page 10-37
- "Histogram Equalization" on page 10-41
- "Contrast-Limited Adaptive Histogram Equalization" on page 10-43
- "Decorrelation Stretching" on page 10-44

The functions described in this section apply primarily to intensity images. However, some of these functions can be applied to color images as well. For information about how these functions work with color images, see the reference pages for the individual functions.

Adjusting Intensity Values to a Specified Range


You can adjust the intensity values in an image using the imadjust function, where you specify the range of intensity values in the output image.

For example, this code increases the contrast in a low-contrast intensity image by remapping the data values to fill the entire intensity range [0, 255].

```
I = imread('pout.tif');
J = imadjust(I);
imshow(J)
figure, imhist(J,64)
```

This figure displays the adjusted image and its histogram. Notice the increased contrast in the image, and that the histogram now fills the entire range.





Adjusted Image and Its Histogram

Specifying the Adjustment Limits

You can optionally specify the range of the input values and the output values using imadjust. You specify these ranges in two vectors that you pass to imadjust as arguments. The first vector specifies the low- and high-intensity

values that you want to map. The second vector specifies the scale over which you want to map them.

Note Note that you must specify the intensities as values between 0 and 1 regardless of the class of I. If I is uint8, the values you supply are multiplied by 255 to determine the actual values to use; if I is uint16, the values are multiplied by 65535. To learn about an alternative way to set these limits automatically, see "Setting the Adjustment Limits Automatically" on page 10-39.

For example, you can decrease the contrast of an image by narrowing the range of the data. In the example below, the man's coat is too dark to reveal any detail. imadjust maps the range [0,51] in the uint8 input image to [128,255] in the output image. This brightens the image considerably, and also widens the dynamic range of the dark portions of the original image, making it much easier to see the details in the coat. Note, however, that because all values above 51 in the original image are mapped to 255 (white) in the adjusted image, the adjusted image appears washed out.

```
I = imread('cameraman.tif');
J = imadjust(I,[0 \ 0.2],[0.5 \ 1]);
imshow(I)
figure, imshow(J)
```







Image After Remapping and Widening the Dynamic Range

Setting the Adjustment Limits Automatically

To use imadjust, you must typically perform two steps:

- 1 View the histogram of the image to determine the intensity value limits.
- **2** Specify these limits as a fraction between 0.0 and 1.0 so that you can pass them to imadjust in the [low in high in] vector.

For a more convenient way to specify these limits, use the stretchlim function. (The imadjust function uses stretchlim for its simplest syntax, imadjust(I).)

This function calculates the histogram of the image and determines the adjustment limits automatically. The stretchlim function returns these values as fractions in a vector that you can pass as the [low_in high_in] argument to imadjust; for example:

```
I = imread('rice.png');
J = imadjust(I,stretchlim(I),[0 1]);
```

By default, stretchlim uses the intensity values that represent the bottom 1% (0.01) and the top 1% (0.99) of the range as the adjustment limits. By trimming the extremes at both ends of the intensity range, stretchlim makes more room in the adjusted dynamic range for the remaining intensities. But you can specify other range limits as an argument to stretchlim. See the stretchlim reference page for more information.

Gamma Correction


imadjust maps low to bottom, and high to top. By default, the values between low and high are mapped linearly to values between bottom and top. For example, the value halfway between low and high corresponds to the value halfway between bottom and top.

imadjust can accept an additional argument that specifies the *gamma* correction factor. Depending on the value of gamma, the mapping between values in the input and output images might be nonlinear. For example, the value halfway between 10w and high might map to a value either greater than or less than the value halfway between bottom and top.

Gamma can be any value between 0 and infinity. If gamma is 1 (the default), the mapping is linear. If gamma is less than 1, the mapping is weighted toward

higher (brighter) output values. If gamma is greater than 1, the mapping is weighted toward lower (darker) output values.

The figure below illustrates this relationship. The three transformation curves show how values are mapped when gamma is less than, equal to, and greater than 1. (In each graph, the x-axis represents the intensity values in the input image, and the y-axis represents the intensity values in the output image.)



Plots Showing Three Different Gamma Correction Settings

The example below illustrates gamma correction. Notice that in the call to imadjust, the data ranges of the input and output images are specified as empty matrices. When you specify an empty matrix, imadjust uses the default range of [0,1]. In the example, both ranges are left empty; this means that gamma correction is applied without any other adjustment of the data.

```
[X,map] = imread('forest.tif')
I = ind2gray(X, map);
J = imadjust(I,[],[],0.5);
imshow(I)
figure, imshow(J)
```





Image Courtesy of Susan Cohen

Image Before and After Applying Gamma Correction

Histogram Equalization

The process of adjusting intensity values can be done automatically by the histeq function. histeq performs *histogram equalization*, which involves transforming the intensity values so that the histogram of the output image approximately matches a specified histogram. (By default, histeq tries to match a flat histogram with 64 bins, but you can specify a different histogram instead; see the reference page for histeq.)

This example illustrates using histeq to adjust an intensity image. The original image has low contrast, with most values in the middle of the intensity range. histeq produces an output image having values evenly distributed throughout the range.

```
I = imread('pout.tif');
J = histeq(I);
imshow(J)
figure, imhist(J,64)
```







Image After Histogram Equalization with Its Histogram

histeg can return a 1-by-256 vector that shows, for each possible input value, the resulting output value. (The values in this vector are in the range [0,1], regardless of the class of the input image.) You can plot this data to get the transformation curve. For example:

```
I = imread('pout.tif');
[J,T] = histeq(I);
figure,plot((0:255)/255,T);
```



Notice how this curve reflects the histograms in the previous figure, with the input values mostly between 0.3 and 0.6, while the output values are distributed evenly between 0 and 1.

For an interactive demonstration of intensity adjustment, try running imadjdemo.

Contrast-Limited Adaptive Histogram Equalization

As an alternative to using histeq, you can perform contrast-limited adaptive histogram equalization (CLAHE) using the adapthisteq function. While histeq works on the entire image, adapthisteq operates on small regions in the image, called *tiles*. Each tile's contrast is enhanced, so that the histogram of the output region approximately matches a specified histogram. After performing the equalization, adapthisteq combines neighboring tiles using bilinear interpolation to eliminate artificially induced boundaries.

To avoid amplifying any noise that might be present in the image, you can use adapthisteq optional parameters to limit the contrast, especially in homogeneous areas.

To illustrate, this example uses adapthisted to adjust the contrast in an intensity image. The original image has low contrast, with most values in the middle of the intensity range. adapthisted produces an output image having values evenly distributed throughout the range.

```
I = imread('pout.tif');
J = adapthisteq(I);
imshow(I)
figure, imshow(J)
```




Image After CLAHE Equalization with Its Histogram

Decorrelation Stretching

Decorrelation stretching enhances the color separation of an image with significant band-band correlation. The exaggerated colors improve visual interpretation and make feature discrimination easier. You apply decorrelation stretching with the decorretretch function. See "Adding a Linear Contrast Stretch" on page 10-47 on how to add an optional linear contrast stretch to the decorrelation stretch.

The number of color bands, NBANDS, in the image is usually three. But you can apply decorrelation stretching regardless of the number of color bands.

The original color values of the image are mapped to a new set of color values with a wider range. The color intensities of each pixel are transformed into the color eigenspace of the NBANDS-by-NBANDS covariance or correlation matrix, stretched to equalize the band variances, then transformed back to the original color bands.

To define the bandwise statistics, you can use the entire original image or, with the subset option, any selected subset of it. See the decorrstretch reference page.

Simple Decorrelation Stretching

You can apply decorrelation and stretching operations on the library of images available in the imdemos directory. The library includes a LANDSAT image of the Little Colorado River. In this example, you perform a simple decorrelation stretch on this image:

1 The image has seven bands, but just read in the three visible colors:

2 Then perform the decorrelation stretch:


```
B = decorrstretch(A);
```

3 Now view the results:

```
imshow(A); figure; imshow(B)
```

Compare the two images. The original has a strong violet (red-bluish) tint, while the transformed image has a somewhat expanded color range.






Little Colorado River Before (left) and After (right) Decorrelation Stretch

A color band scatterplot of the images shows how the bands are decorrelated and equalized:

```
rA = A(:,:,1); gA = A(:,:,2); bA = A(:,:,3);
figure, plot3(rA(:),gA(:),bA(:),'.'); grid('on')
xlabel('Red (Band 3)'); ylabel('Green (Band 2)'); ...
      zlabel('Blue (Band 1)')
rB = B(:,:,1); gB = B(:,:,2); bB = B(:,:,3);
figure, plot3(rB(:),gB(:),bB(:),'.'); grid('on')
xlabel('Red (Band 3)'); ylabel('Green (Band 2)'); ...
      zlabel('Blue (Band 1)')
```




Color Scatterplot Before (left) and After (right) Decorrelation Stretch

Adding a Linear Contrast Stretch

Now try the same transformation, but with a linear contrast stretch applied after the decorrelation stretch:

imshow(A); C = decorrstretch(A, 'Tol', 0.01); figure; imshow(C)

Compare the transformed image to the original.



Little Colorado River After Decorrelation Stretch Followed by Linear Contrast Stretch

Adding the linear contrast stretch enhances the resulting image by further expanding the color range. In this case, the transformed color range is mapped within each band to a normalized interval between 0.01 and 0.99, saturating 2%.

See the stretchlim function reference page for more about Tol. Without the Tol option, decorrstretch applies no linear contrast stretch.

Note You can apply a linear contrast stretch as a separate operation after performing a decorrelation stretch, using stretchlim and imadjust. This alternative, however, often gives inferior results for uint8 and uint16 images, because the pixel values must be clamped to [0 255] (or [0 65535]). The Tol option in decorrstretch circumvents this limitation.

Noise Removal

Digital images are prone to a variety of types of noise. There are several ways that noise can be introduced into an image, depending on how the image is created. For example:

- If the image is scanned from a photograph made on film, the film grain is a source of noise. Noise can also be the result of damage to the film, or be introduced by the scanner itself.
- If the image is acquired directly in a digital format, the mechanism for gathering the data (such as a CCD detector) can introduce noise.
- Electronic transmission of image data can introduce noise.

The toolbox provides a number of different ways to remove or reduce noise in an image. Different methods are better for different kinds of noise. The methods available include

- "Using Linear Filtering"
- "Using Median Filtering"
- "Using Adaptive Filtering" on page 10-52

To simulate the effects of some of the problems listed above, the toolbox provides the imnoise function, which you can use to *add* various types of noise to an image. The examples in this section use this function.

Using Linear Filtering

You can use linear filtering to remove certain types of noise. Certain filters, such as averaging or Gaussian filters, are appropriate for this purpose. For example, an averaging filter is useful for removing grain noise from a photograph. Because each pixel gets set to the average of the pixels in its neighborhood, local variations caused by grain are reduced.

See "Linear Filtering" on page 7-4 for more information.

Using Median Filtering

Median filtering is similar to using an averaging filter, in that each output pixel is set to an average of the pixel values in the neighborhood of the corresponding input pixel. However, with median filtering, the value of an output pixel is determined by the *median* of the neighborhood pixels, rather

than the mean. The median is much less sensitive than the mean to extreme values (called *outliers*). Median filtering is therefore better able to remove these outliers without reducing the sharpness of the image. The medfilt2 function implements median filtering.

Note Median filtering is a specific case of *order-statistic filtering*, also known as rank filtering. For information about order-statistic filtering, see the reference page for the ordfilt2 function.

The following example compares using an averaging filter and medfilt2 to remove salt and pepper noise. This type of noise consists of random pixels' being set to black or white (the extremes of the data range). In both cases the size of the neighborhood used for filtering is 3-by-3.


1 Read in the image and display it.

```
I = imread('eight.tif');
imshow(I)
```




2 Add noise to it.

```
J = imnoise(I, 'salt & pepper', 0.02);
figure, imshow(J)
```



3 Filter the noisy image with an averaging filter and display the results.

```
K = filter2(fspecial('average',3),J)/255;
figure, imshow(K)
```



4 Now use a median filter to filter the noisy image and display the results. Notice that medfilt2 does a better job of removing noise, with less blurring of edges.

```
L = medfilt2(J,[3 3]);
figure, imshow(K)
figure, imshow(L)
```




Using Adaptive Filtering


The wiener2 function applies a Wiener filter (a type of linear filter) to an image adaptively, tailoring itself to the local image variance. Where the variance is large, wiener2 performs little smoothing. Where the variance is small, wiener2 performs more smoothing.

This approach often produces better results than linear filtering. The adaptive filter is more selective than a comparable linear filter, preserving edges and other high-frequency parts of an image. In addition, there are no design tasks; the wiener2 function handles all preliminary computations and implements the filter for an input image. wiener2, however, does require more computation time than linear filtering.

wiener2 works best when the noise is constant-power ("white") additive noise, such as Gaussian noise. The example below applies wiener2 to an image of Saturn that has had Gaussian noise added. For an interactive demonstration of filtering to remove noise, try running nrfiltdemo.

```
RGB = imread('saturn.png');
I = rgb2gray(RGB);
J = imnoise(I, 'gaussian', 0, 0.005);
K = wiener2(J,[5 5]);
imshow(J)
figure, imshow(K)
```





Original Image Courtesy of NASA

Noisy Version (left) and Filtered Version (right)

Region-Based Processing

This chapter describes operations that you can perform on a selected region of an image.

Terminology (p. 11-2) Provides definitions of image processing terms used in

this section

Specifying a Region of Interest (p. 11-3) Describes how to specify a region of interest using the

roipoly function

Filtering a Region (p. 11-6) Describes how to apply a filter to a region using the

roifilt2 function

Filling a Region (p. 11-9) Describes how to fill a region of interest using the

roifill function

Terminology

An understanding of the following terms will help you to use this section.

Term	Definition
binary mask	Binary image with the same size as the image you want to process. The mask contains 1's for all pixels that are part of the region of interest, and 0's everywhere else.
filling a region	Process that fills a region of interest by interpolating the pixel values from the borders of the region. This process can be used to make objects in an image seem to disappear as they are replaced with values that blend in with the background area.
filtering a region	Process of applying a filter to a region of interest. For example, you can apply an intensity adjustment filter to certain regions of an image.
interpolation	Method used to estimate an image value at a location in between image pixels.
masked filtering	Operation that applies filtering only to the regions of interest in an image that are identified by a binary mask. Filtered values are returned for pixels where the binary mask contains 1's; unfiltered values are returned for pixels where the binary mask contains 0's.
region of interest	Portion of an image that you want to filter or perform some other operation on. You define a region of interest by creating a binary mask. There can be more than one region defined in an image. The regions can be geographic in nature, such as polygons that encompass contiguous pixels, or they can be defined by a range of intensities. In the latter case, the pixels are not necessarily contiguous.

Specifying a Region of Interest

A *region of interest* is a portion of an image that you want to filter or perform some other operation on. You define a region of interest by creating a *binary mask*, which is a binary image with the same size as the image you want to process. The mask contains 1's for all pixels that are part of the region of interest, and 0's everywhere else.

The following subsections discuss methods for creating binary masks:

- "Selecting a Polygon" on page 11-3
- "Other Selection Methods" on page 11-4 (using any binary mask or the roicolor function)

For an interactive demonstration of region-based processing, try running roidemo.

Selecting a Polygon

You can use the roipoly function to specify a polygonal region of interest. If you call roipoly with no input arguments, the cursor changes to crosshairs when it is over the image displayed in the current axes. You can then specify the vertices of the polygon by clicking points in the image with the mouse. When you are done selecting vertices, press **Return**; roipoly returns a binary image of the same size as the input image, containing 1's inside the specified polygon, and 0's everywhere else.


The example below illustrates using the interactive syntax of roipoly to create a binary mask. In the figure, the border of the selected region that was created using a mouse is shown in red.

```
I = imread('pout.tif');
imshow(I)
BW = roipoly;
```



Polygonal Region of Interest Selected Using roipoly

imshow(BW)



Binary Mask Created for the Region Shown in the Preceding Figure

You can also use roipoly noninteractively. See the reference page for roipoly for more information.

Other Selection Methods

roipoly provides an easy way to create a binary mask. However, you can use any binary image as a mask, provided that the binary image is the same size as the image being filtered.

For example, suppose you want to filter the intensity image I, filtering only those pixels whose values are greater than 0.5. You can create the appropriate mask with this command.

$$BW = (I > 0.5);$$

You can also use the poly2mask function to create a binary mask. Unlike the roipoly function, poly2mask does not require an input image. For more information, see the poly2mask reference page.

You can also use the roicolor function to define the region of interest based on a color or intensity range. For more information, see the reference page for roicolor.

Filtering a Region

You can use the roifilt2 function to process a region of interest. When you call roifilt2, you specify an intensity image, a binary mask, and a filter. roifilt2 filters the input image and returns an image that consists of filtered values for pixels where the binary mask contains 1's and unfiltered values for pixels where the binary mask contains 0's. This type of operation is called masked filtering.

Note roifilt2 is best suited to operations that return data in the same range as in the original image, because the output image takes some of its data directly from the input image. Certain filtering operations can result in values outside the normal image data range (i.e., [0,1] for images of class double, [0,255] for images of class uint8, and [0,65535] for images of class uint16). For more information, see the reference page for roifilt2.

Example: Filtering a Region in an Image

This example uses masked filtering to increase the contrast of a specific region of an image:

1 Read in the image.

```
I = imread('pout.tif');
```

2 Create the mask.

This example uses the mask BW created in "Selecting a Polygon" on page 11-3. The region of interest specified by the mask is the logo on the girl's jacket.

3 Create the filter.

```
h = fspecial('unsharp');
```

4 Call roifilt2, specifying the image to be filtered, the mask, and the filter.

```
I2 = roifilt2(h,I,BW);
imshow(I)
figure, imshow(I2)
```





Image Before and After Using an Unsharp Filter on the Region of Interest

Specifying the Filtering Operation

roifilt2 also enables you to specify your own function to operate on the region of interest. This example uses the imadjust function to lighten parts of an image:

1 Read in the image.

```
I = imread('cameraman.tif');
```

2 Create the mask. In this example, the mask is a binary image containing text. The mask image must be cropped to be the same size as the image to be filtered.

```
BW = imread('text.png');
mask = BW(1:256,1:256);
```

3 Create the filter.

```
f = inline('imadjust(x,[],[],0.3)');
```

4 Call roifilt2, specifying the image to be filtered, the mask, and the filter. The resulting image, I2, has the text imprinted on it.

```
I2 = roifilt2(I,mask,f);
imshow(I2)
```



Image Brightened Using a Binary Mask Containing Text

Filling a Region

You can use the roifill function to fill a region of interest, interpolating from the borders of the region. This function is useful for image editing, including removal of extraneous details or artifacts.

roifill performs the fill operation using an interpolation method based on Laplace's equation. This method results in the smoothest possible fill, given the values on the boundary of the region.

As with roipoly, you select the region of interest with the mouse. When you complete the selection, roifill returns an image with the selected region filled in.

This example uses roifill to modify the trees image. The border of the selected region is shown in red on the original image.

```
load trees
I = ind2gray(X,map);
imshow(I)
I2 = roifill;
```



Region of Interest Selected for Filling

imshow(I2)



Region of Interest Shown in the Preceding Figure Has Been Filled

Image Deblurring

This chapter describes how to deblur an image using the toolbox deblurring functions.

Terminology (p. 12-2) Provides definitions of image processing terms used in

this section

Understanding Deblurring (p. 12-3) Defines deblurring and deconvolution

Using the Deblurring Functions Provides step-by-step examples of using deconvwnr,

(p. 12-6) deconvreg, deconvlucy, and deconvblind functions

Avoiding Ringing in Deblurred Images Describes how to use the edgetaper function to avoid

(p. 12-23) "ringing" in deblurred images

Terminology

An understanding of the following terms will help you to use this chapter.

Term	MATLAB Definition
deconvolution	Process of reversing the effect of convolution.
distortion operator	Operator that describes a process causing the acquired image to be different from the original scene. Distortion caused by a point spread function (see below) is just one type of distortion.
optical transfer function (OTF)	In the frequency domain, the OTF describes the response of a linear, position-invariant system to an impulse. The OTF is the Fourier transform of the point spread function (PSF).
point spread function (PSF)	In the spatial domain, the PSF describes the degree to which an optical system blurs (spreads) a point of light. The PSF is the inverse Fourier transform of the OTF.

Understanding Deblurring

This section provides some background on deblurring techniques. The section includes these topics:

- "Causes of Blurring"
- "Deblurring Model"

Causes of Blurring

The blurring, or degradation, of an image can be caused by many factors:

- Movement during the image capture process, by the camera or, when long exposure times are used, by the subject
- Out-of-focus optics, use of a wide-angle lens, atmospheric turbulence, or a short exposure time, which reduces the number of photons captured
- Scattered light distortion in confocal microscopy

Deblurring Model

A blurred or degraded image can be approximately described by this equation g = Hf + n, where

- g The blurred image
- **H** The distortion operator, also called the *point spread function* (PSF). This function, when convolved with the image, creates the distortion.
- f The original true image
- ${f n}$ Additive noise, introduced during image acquisition, that corrupts the image

Note The image **f** really doesn't exist. This image represents what you would have if you had perfect image acquisition conditions.

Importance of the PSF

Based on this model, the fundamental task of deblurring is to deconvolve the blurred image with the PSF that exactly describes the distortion.

Note The quality of the deblurred image is mainly determined by knowledge of the PSF.

To illustrate, this example takes a clear image and deliberately blurs it by convolving it with a PSF. The example uses the fspecial function to create a PSF that simulates a motion blur, specifying the length of the blur in pixels, (LEN=31), and the angle of the blur in degrees (THETA=11). Once the PSF is created, the example uses the imfilter function to convolve the PSF with the original image, I, to create the blurred image, Blurred. (To see how deblurring is the reverse of this process, using the same images, see "Deblurring with the Wiener Filter" on page 12-7.)

```
I = imread('peppers.png');
I = I(60+[1:256],222+[1:256],:); % crop the image
figure; imshow(I); title('Original Image');
```



```
LEN = 31;
THETA = 11;
PSF = fspecial('motion', LEN, THETA); % create PSF
Blurred = imfilter(I,PSF, 'circular', 'conv');
figure; imshow(Blurred); title('Blurred Image');
```



Using the Deblurring Functions

The toolbox includes four deblurring functions, listed here in order of complexity:

deconvwnr Implements deblurring using the Wiener filter Implements deblurring using a regularized filter deconvreq

deconvlucy Implements deblurring using the Lucy-Richardson algorithm

deconvblind Implements deblurring using the blind deconvolution

algorithm

All the functions accept a PSF and the blurred image as their primary arguments. The deconvent function implements a least squares solution. The deconvreg function implements a constrained least squares solution, where you can place constraints on the output image (the smoothness requirement is the default). With either of these functions, you should provide some information about the noise to reduce possible noise amplification during deblurring.

The deconvlucy function implements an accelerated, damped Lucy-Richardson algorithm. This function performs multiple iterations, using optimization techniques and Poisson statistics. With this function, you do not need to provide information about the additive noise in the corrupted image.

The deconvolution implements the blind deconvolution algorithm, which performs deblurring without knowledge of the PSF. When you call deconvblind, you pass as an argument your initial guess at the PSF. The deconvblind function returns a restored PSF in addition to the restored image. The implementation uses the same damping and iterative model as the deconvlucy function.

Note You might need to perform many iterations of the deblurring process, varying the parameters you specify to the deblurring functions with each iteration, until you achieve an image that, based on the limits of your information, is the best approximation of the original scene. Along the way, you must make numerous judgments about whether newly uncovered features in the image are features of the original scene or simply artifacts of the deblurring process.

For information about creating your own deblurring functions, see "Creating Your Own Deblurring Functions" on page 12-22. To avoid "ringing" in a deblurred image, you can use the edgetaper function to preprocess your image before passing it to the deblurring functions. See "Avoiding Ringing in Deblurred Images" on page 12-23 for more information.

Deblurring with the Wiener Filter

Use the deconvent function to deblur an image using the Wiener filter. Wiener deconvolution can be used effectively when the frequency characteristics of the image and additive noise are known, to at least some degree. In the absence of noise, the Wiener filter reduces to the ideal inverse filter.

This example deblurs the blurred image created in "Deblurring Model" on page 12-3, specifying the same PSF function that was used to create the blur. This example illustrates the importance of knowing the PSF, the function that caused the blur. When you know the exact PSF, the results of deblurring can be quite effective.

1 Read an image into the MATLAB workspace. (To speed the deblurring operation, the example also crops the image.)

```
I = imread('peppers.png');
I = I(10+[1:256],222+[1:256],:);
figure;imshow(I);title('Original Image');
```



2 Create a PSF.

```
LEN = 31;
THETA = 11;
PSF = fspecial('motion',LEN,THETA);
```

3 Create a simulated blur in the image.

```
Blurred = imfilter(I,PSF,'circular','conv');
figure; imshow(Blurred);title('Blurred Image');
```



4 Deblur the image.

```
wnr1 = deconvwnr(Blurred, PSF);
figure;imshow(wnr1);
title('Restored, True PSF');
```



Refining the Result

You can affect the deconvolution results by providing values for the optional arguments supported by the deconvent function. Using these arguments you can specify the noise-to-signal power value and/or provide autocorrelation functions to help refine the result of deblurring. To see the impact of these optional arguments, view the Image Processing Toolbox deblurring demos.

Deblurring with a Regularized Filter

Use the deconvreg function to deblur an image using a regularized filter. A regularized filter can be used effectively when limited information is known about the additive noise.

To illustrate, this example simulates a blurred image by convolving a Gaussian filter PSF with an image (using imfilter). Additive noise in the image is simulated by adding Gaussian noise of variance V to the blurred image (using imnoise):

1 Read an image into the MATLAB workspace. The example uses cropping to reduce the size of the image to be deblurred. This is not a required step in deblurring operations.

```
I = imread('tissue.png');
I = I(125+[1:256],1:256,:);
figure; imshow(I); title('Original Image');
```





Image Courtesy Alan W. Partin

2 Create the PSF.

```
PSF = fspecial('gaussian',11,5);
```

3 Create a simulated blur in the image and add noise.


```
Blurred = imfilter(I,PSF,'conv');
V = .02;
BlurredNoisy = imnoise(Blurred, 'gaussian',0,V);
figure;imshow(BlurredNoisy);title('Blurred and Noisy Image');
```



4 Use deconvreg to deblur the image, specifying the PSF used to create the blur and the noise power, NP.

```
NP = V*prod(size(I));
```

```
[reg1 LAGRA] = deconvreg(BlurredNoisy, PSF, NP);
figure, imshow(reg1), title('Restored Image');
```



Refining the Result

You can affect the deconvolution results by providing values for the optional arguments supported by the deconvreg function. Using these arguments you can specify the noise power value, the range over which deconvreg should iterate as it converges on the optimal solution, and the regularization operator to constrain the deconvolution. To see the impact of these optional arguments, view the Image Processing Toolbox deblurring demos.

Deblurring with the Lucy-Richardson Algorithm

Use the deconvlucy function to deblur an image using the accelerated, damped, Lucy-Richardson algorithm. The algorithm maximizes the likelihood that the resulting image, when convolved with the PSF, is an instance of the blurred image, assuming Poisson noise statistics. This function can be effective when you know the PSF but know little about the additive noise in the image.

The deconvlucy function implements several adaptations to the original Lucy-Richardson maximum likelihood algorithm that address complex image restoration tasks. Using these adaptations, you can

- Reduce the effect of noise amplification on image restoration
- Account for nonuniform image quality (e.g., bad pixels, flat-field variation)
- Handle camera read-out and background noise
- Improve the restored image resolution by subsampling

The following sections provide more information about each of these adaptations.

Reducing the Effect of Noise Amplification

Noise amplification is a common problem of maximum likelihood methods that attempt to fit data as closely as possible. After many iterations, the restored image can have a speckled appearance, especially for a smooth object observed at low signal-to-noise ratios. These speckles do not represent any real structure in the image, but are artifacts of fitting the noise in the image too closely.

To control noise amplification, the deconvlucy function uses a damping parameter, DAMPAR. This parameter specifies the threshold level for the deviation of the resulting image from the original image, below which damping occurs. For pixels that deviate in the vicinity of their original values, iterations are suppressed.

Damping is also used to reduce ringing, the appearance of high-frequency structures in a restored image. Ringing is not necessarily the result of noise amplification. See "Avoiding Ringing in Deblurred Images" on page 12-23 for more information.

Accounting for Nonuniform Image Quality

Another complication of real-life image restoration is that the data might include bad pixels, or that the quality of the receiving pixels might vary with time and position. By specifying the WEIGHT array parameter with the deconvlucy function, you can specify that certain pixels in the image be ignored. To ignore a pixel, assign a weight of zero to the element in the WEIGHT array that corresponds to the pixel in the image.

The algorithm converges on predicted values for the bad pixels based on the information from neighborhood pixels. The variation in the detector response from pixel to pixel (the so-called flat-field correction) can also be accommodated by the WEIGHT array. Instead of assigning a weight of 1.0 to the good pixels, you can specify fractional values and weight the pixels according to the amount of the flat-field correction.

Handling Camera Read-Out Noise

Noise in charge coupled device (CCD) detectors has two primary components:

Photon counting noise with a Poisson distribution

• Read-out noise with a Gaussian distribution

The Lucy-Richardson iterations intrinsically account for the first type of noise. You must account for the second type of noise; otherwise, it can cause pixels with low levels of incident photons to have negative values.

The deconvlucy function uses the READOUT input parameter to handle camera read-out noise. The value of this parameter is typically the sum of the read-out noise variance and the background noise (e.g., number of counts from the background radiation). The value of the READOUT parameter specifies an offset that ensures that all values are positive.

Handling Undersampled Images

The restoration of undersampled data can be improved significantly if it is done on a finer grid. The deconvlucy function uses the SUBSMPL parameter to specify the subsampling rate, if the PSF is known to have a higher resolution.

If the undersampled data is the result of camera pixel binning during image acquisition, the PSF observed at each pixel rate can serve as a finer grid PSF. Otherwise, the PSF can be obtained via observations taken at subpixel offsets or via optical modeling techniques. This method is especially effective for images of stars (high signal-to-noise ratio), because the stars are effectively forced to be in the center of a pixel. If a star is centered between pixels, it is restored as a combination of the neighboring pixels. A finer grid redirects the consequent spreading of the star flux back to the center of the star's image.

Example: Using the deconvlucy Function to Deblur an Image

To illustrate a simple use of deconvlucy, this example simulates a blurred, noisy image by convolving a Gaussian filter PSF with an image (using imfilter) and then adding Gaussian noise of variance V to the blurred image (using imnoise):

1 Read an image into the MATLAB workspace. (The example uses cropping to reduce the size of the image to be deblurred. This is not a required step in deblurring operations.)

```
I = imread('board.tif');
I = I(50+[1:256],2+[1:256],:);
figure;imshow(I);title('Original Image');
```



2 Create the PSF.

```
PSF = fspecial('gaussian',5,5);
```

3 Create a simulated blur in the image and add noise.

```
Blurred = imfilter(I,PSF,'symmetric','conv');
V = .002;
BlurredNoisy = imnoise(Blurred, 'gaussian',0,V);
figure;imshow(BlurredNoisy);title('Blurred and Noisy Image');
```



4 Use deconvlucy to restore the blurred and noisy image, specifying the PSF used to create the blur, and limiting the number of iterations to 5 (the default is 10).

Note The deconvlucy function can return values in the output image that are beyond the range of the input image.

```
luc1 = deconvlucy(BlurredNoisy,PSF,5);
figure; imshow(luc1);
title('Restored Image');
```



Refining the Result

The deconvlucy function, by default, performs multiple iterations of the deblurring process. You can stop the processing after a certain number of iterations to check the result, and then restart the iterations from the point where processing stopped. To do this, pass in the input image as a cell array, for example, {BlurredNoisy}. The deconvlucy function returns the output image as a cell array that you can then pass as an input argument to deconvlucy to restart the deconvolution.

The output cell array contains these four elements
--

Element	Description
output{1}	Original input image
output{2}	Image produced by the last iteration
output{3}	Image produced by the next to last iteration
output{4}	Internal information used by deconvlucy to know where to restart the process

The deconvlucy function supports several other optional arguments you can use to achieve the best possible result, such as specifying a damping parameter to handle additive noise in the blurred image. To see the impact of these optional arguments, view the Image Processing Toolbox deblurring demos.

Deblurring with the Blind Deconvolution Algorithm

Use the deconvblind function to deblur an image using the blind deconvolution algorithm. The algorithm maximizes the likelihood that the resulting image, when convolved with the resulting PSF, is an instance of the blurred image, assuming Poisson noise statistics. The blind deconvolution algorithm can be used effectively when no information about the distortion (blurring and noise) is known. The deconvblind function restores the image and the PSF simultaneously, using an iterative process similar to the accelerated, damped Lucy-Richardson algorithm.

The deconvblind function, just like the deconvlucy function, implements several adaptations to the original Lucy-Richardson maximum likelihood algorithm that address complex image restoration tasks. Using these adaptations, you can

- Reduce the effect of noise on the restoration
- Account for nonuniform image quality (e.g., bad pixels)
- Handle camera read-out noise

For more information about these adaptations, see "Deblurring with the Lucy-Richardson Algorithm" on page 12-11. In addition, the deconvblind function supports PSF constraints that can be passed in through a user-specified function.

Example: Using the deconvblind Function to Deblur an Image

To illustrate blind deconvolution, this example creates a simulated blurred image and then uses deconvblind to deblur it. The example makes two passes at deblurring the image to show the effect of certain optional parameters on the deblurring operation:

1 Read an image into the MATLAB workspace.


```
I = imread('cameraman.tif');
figure; imshow(I); title('Original Image');
```



Image Courtesy of MIT

2 Create the PSF.

```
PSF = fspecial('motion',13,45);
figure; imshow(PSF,[],'notruesize'); title('Original PSF');
```



Original PSF

3 Create a simulated blur in the image.

```
Blurred = imfilter(I,PSF,'circ','conv');
figure; imshow(Blurred); title('Blurred Image');
```



4 Deblur the image, making an initial guess at the size of the PSF.


To determine the size of the PSF, examine the blurred image and measure the width of a blur (in pixels) around an obviously sharp object. In the sample blurred image, you can measure the blur near the contour of the man's sleeve. Because the size of the PSF is more important than the values it contains, you can typically specify an array of 1's as the initial PSF.

The following figure shows a restoration where the initial guess at the PSF is the same size as the PSF that caused the blur. In a real application, you

might need to rerun deconvblind, experimenting with PSFs of different sizes, until you achieve a satisfactory result. The restored PSF returned by each deconvolution can also provide valuable hints at the optimal PSF size. See the Image Processing Toolbox deblurring demos for an example.

```
INITPSF = ones(size(PSF));
[J P]= deconvblind(Blurred, INITPSF, 30);
figure; imshow(J); title('Restored Image');
figure; imshow(P,[], 'notruesize');
title('Restored PSF');
```





Restored Image

Restored PSF

Although deconvblind was able to deblur the image to a great extent, the ringing around the sharp intensity contrast areas in the restored image is unsatisfactory. (The example eliminated edge-related ringing by using the 'circular' option with imfilter when creating the simulated blurred image in step 3.)

The next steps in the example repeat the deblurring process, attempting to achieve a better result by

- Eliminating high-contrast areas from the processing
- Specifying a better PSF

5 Create a WEIGHT array to exclude areas of high contrast from the deblurring operation. This can reduce contrast-related ringing in the result.

To exclude a pixel from processing, you create an array of the same size as the original image, and assign the value 0 to the pixels in the array that correspond to pixels in the original image that you want to exclude from processing. (See "Accounting for Nonuniform Image Quality" on page 12-12 for information about WEIGHT arrays.)

To create a WEIGHT array, the example uses a combination of edge detection and morphological processing to detect high-contrast areas in the image. Because the blur in the image is linear, the example dilates the image twice. (For more information about using these functions, see Chapter 9, "Morphological Operations.") To exclude the image boundary pixels (a high-contrast area) from processing, the example uses padarray to assign the value 0 to all border pixels.

```
WEIGHT = edge(I, 'sobel', .28);
se1 = strel('disk',1);
se2 = strel('line', 13, 45);
WEIGHT = ~imdilate(WEIGHT,[se1 se2]);
WEIGHT = padarray(WEIGHT(2:end-1,2:end-1),[2 2]);
figure; imshow(WEIGHT); title('Weight Array');
```



Weight Array


6 Refine the guess at the PSF. The reconstructed PSF P returned by the first pass at deconvolution shows a clear linearity, as shown in the figure in step 4. For the second pass, the example uses a new PSF, P1, which is the same as the restored PSF but with the small amplitude pixels set to 0.

```
P1 = P;
P1(find(P1 < 0.01))=0;
```

7 Rerun the deconvolution, specifying the WEIGHT array and the modified PSF. Note how the restored image has much less ringing around the sharp intensity contrast areas than the result of the first pass (step 4).

```
[J2 P2] = deconvblind(Blurred,P1,50,[],WEIGHT);
figure; imshow(J2);
title('Newly Deblurred Image');
figure; imshow(P2,[],'notruesize');
title('Newly Reconstructed PSF');
```





Newly Deblurred Image

Newly Reconstructed PSF

Refining the Result

The deconvblind function, by default, performs multiple iterations of the deblurring process. You can stop the processing after a certain number of iterations to check the result, and then restart the iterations from the point where processing stopped. To use this feature, you must pass in both the blurred image and the PSF as cell arrays, for example, {Blurred} and {INITPSF}.

The deconvblind function returns the output image and the restored PSF as cell arrays. The output image cell array contains these four elements:

Element	Description
output{1}	Original input image
output{2}	Image produced by the last iteration
output{3}	Image produced by the next to last iteration
output{4}	Internal information used by deconvlucy to know where to restart the process

The PSF output cell array contains similar elements.


The deconvblind function supports several other optional arguments you can use to achieve the best possible result, such as specifying a damping parameter to handle additive noise in the blurred image. To see the impact of these optional arguments, as well as the functional option that allows you to place additional constraints on the PSF reconstruction, see the Image Processing Toolbox deblurring demos.

Creating Your Own Deblurring Functions


All the toolbox deblurring functions perform deconvolution in the frequency domain, where the process becomes a simple matrix multiplication. To work in the frequency domain, the deblurring functions must convert the PSF you provide into an optical transfer function (OTF), using the psf2otf function. The toolbox also provides a function to convert an OTF into a PSF, otf2psf. The toolbox makes these functions available in case you want to create your own deblurring functions. (In addition, to aid this conversion between PSFs and OTFs, the toolbox also makes the padding function padarray available.)

Avoiding Ringing in Deblurred Images

The discrete Fourier transform (DFT), used by the deblurring functions, assumes that the frequency pattern of an image is periodic. This assumption creates a high-frequency drop-off at the edges of images. In the figure, the shaded area represents the actual extent of the image; the unshaded area represents the assumed periodicity.



This high-frequency drop-off can create an effect called *boundary related* ringing in deblurred images. In this figure, note the horizontal and vertical patterns in the image.



To avoid ringing, use the edgetaper function to preprocess your images before passing them to the deblurring functions. The edgetaper function removes the high-frequency drop-off at the edge of an image by blurring the entire image and then replacing the center pixels of the blurred image with the original image. In this way, the edges of the image taper off to a lower frequency.

Color

This chapter describes the toolbox functions that help you work with color image data. Note that "color" includes shades of gray; therefore much of the discussion in this chapter applies to grayscale images as well as color images.

Terminology (p. 13-2)	Provides definitions of image processing terms used in this section
Working with Different Screen Bit Depths (p. 13-3)	Describes how to determine the screen bit depth of your system and provides recommendations if you can change the bit depth
Reducing the Number of Colors in an Image (p. 13-6)	Describes how to use imapprox and rgb2ind to reduce the number of colors in an image, including information about dithering
Converting Color Data Between Color Spaces (p. 13-15)	Defines the concept of image color space and describes how to convert images between color spaces

Terminology

An understanding of the following terms will help you to use this chapter.

Term	Definition
approximation	Method by which the software chooses replacement colors in the event that direct matches cannot be found. The methods of approximation discussed in this chapter are colormap mapping, uniform quantization, and minimum variance quantization.
indexed image	Image whose pixel values are direct indices into an RGB colormap. In MATLAB, an indexed image is represented by an array of class uint8, uint16, or double. The colormap is always an m-by-3 array of class double. This documentation often uses the variable name X to represent an indexed image in memory, and map to represent the colormap.
intensity image	Image consisting of intensity (grayscale) values. In MATLAB, intensity images are represented by an array of class uint8, uint16, or double. While intensity images are not stored with colormaps, MATLAB uses a system colormap to display them. This documentation often uses the variable name I to represent an intensity image in memory. This term is synonymous with the term grayscale.
RGB image	Image in which each pixel is specified by three values — one each for the red, blue, and green components of the pixel's color. In MATLAB, an RGB image is represented by an m-by-n-by-3 array of class uint8, uint16, or double. This documentation often uses the variable name RGB to represent an RGB image in memory.
screen bit depth	Number of bits per screen pixel.
screen color resolution	Number of distinct colors that can be produced by the screen.

Working with Different Screen Bit Depths

Most computer displays use 8, 16, or 24 bits per screen pixel. The number of bits per screen pixel determines the display's *screen bit depth*. The screen bit depth determines the *screen color resolution*, which is how many distinct colors the display can produce.

Regardless of the number of colors your system can display, MATLAB can store and process images with very high bit depths: 2^{24} colors for uint8 RGB images, 2^{48} colors for uint16 RGB images, and 2^{159} for double RGB images. These images are displayed best on systems with 24-bit color, but usually look fine on 16-bit systems as well. (For additional information about how MATLAB handles color, see the MATLAB graphics documentation.)

This section

- Describes how to determine your system's screen bit depth
- Provides guidelines for choosing a screen bit depth

Determining Screen Bit Depth

To determine the bit depth of your system's screen, enter this command at the MATLAB prompt.

```
get(0, 'ScreenDepth')
ans =
32
```

The integer MATLAB returns represents the number of bits per screen pixel:

Value	Screen Bit Depth
8	8-bit displays support 256 colors. An 8-bit display can produce any of the colors available on a 24-bit display, but only 256 distinct colors can appear at one time. (There are 256 shades of gray available, but if all 256 shades of gray are used, they take up all the available color slots.)
16	16-bit displays usually use 5 bits for each color component, resulting in 32 (i.e., 2^5) levels each of red, green, and blue. This supports 32,768 (i.e., 2^{15}) distinct colors (of which 32 are shades of gray). Some systems use the extra bit to increase the number of levels of green that can be displayed. In this case, the number of different colors supported by a 16-bit display is actually 64,536 (i.e. 2^{16}).
24	24-bit displays use 8 bits for each of the three color components, resulting in 256 (i.e., 2^8) levels each of red, green, and blue. This supports 16,777,216 (i.e., 2^{24}) different colors. (Of these colors, 256 are shades of gray. Shades of gray occur where R=G=B.) The 16 million possible colors supported by 24-bit display can render a lifelike image.
32	32-bit displays use 24 bits to store color information and use the remaining 8 bits to store transparency data (alpha channel). For information about how MATLAB supports the alpha channel, see the section "Transparency" in the MATLAB graphics documentation.

Choosing a Screen Bit Depth

Depending on your system, you might be able to choose the screen bit depth you want to use. (There might be tradeoffs between screen bit depth and screen color resolution.) In general, 24-bit display mode produces the best results. If you need to use a lower screen bit depth, 16-bit is generally preferable to 8-bit. However, keep in mind that a 16-bit display has certain limitations, such as

- An image might have finer gradations of color than a 16-bit display can represent. If a color is unavailable, MATLAB uses the closest approximation.
- There are only 32 shades of gray available. If you are working primarily with grayscale images, you might get better display results using 8-bit display mode, which provides up to 256 shades of gray.

For information about reducing the number of colors used by an image, see "Reducing the Number of Colors in an Image" on page 13-6.

Reducing the Number of Colors in an Image

This section describes how to reduce the number of colors in an indexed or RGB image. A discussion is also included about dithering, which is used by the toolbox's color-reduction functions (see below). Dithering is used to increase the apparent number of colors in an image.

The table below summarizes the Image Processing Toolbox functions for color reduction.

Function	Purpose
imapprox	Reduces the number of colors used by an indexed image, enabling you specify the number of colors in the new colormap.
rgb2ind	Converts an RGB image to an indexed image, enabling you to specify the number of colors to store in the new colormap.

On systems with 24-bit color displays, RGB (truecolor) images can display up to 16,777.216 (i.e., 2²⁴) colors. On systems with lower screen bit depths, RGB images are still displayed reasonably well, because MATLAB automatically uses color approximation and dithering if needed.

Indexed images, however, might cause problems if they have a large number of colors. In general, you should limit indexed images to 256 colors for the following reasons:

- On systems with 8-bit display, indexed images with more than 256 colors will need to be dithered or mapped and, therefore, might not display well.
- On some platforms, colormaps cannot exceed 256 entries.
- If an indexed image has more than 256 colors, MATLAB cannot store the image data in a uint8 array, but generally uses an array of class double instead, making the storage size of the image much larger (each pixel uses 64 bits).
- Most image file formats limit indexed images to 256 colors. If you write an indexed image with more than 256 colors (using imwrite) to a format that does not support more than 256 colors, you will receive an error.

Using rgb2ind

rgb2ind converts an RGB image to an indexed image, reducing the number of colors in the process. This function provides the following methods for approximating the colors in the original image:

- Quantization
 - Uniform quantization
 - Minimum variance quantization
- Colormap mapping


The quality of the resulting image depends on the approximation method you use, the range of colors in the input image, and whether or not you use dithering. Note that different methods work better for different images. See "Dithering" on page 13-13 for a description of dithering and how to enable or disable it.

Quantization

Reducing the number of colors in an image involves *quantization*. The function rgb2ind uses quantization as part of its color reduction algorithm. rgb2ind supports two quantization methods: *uniform quantization* and *minimum variance quantization*.

An important term in discussions of image quantization is RGB color cube, which is used frequently throughout this section. The RGB color cube is a three-dimensional array of all of the colors that are defined for a particular data type. Since RGB images in MATLAB can be of type uint8, uint16, or double, three possible color cube definitions exist. For example, if an RGB image is of class uint8, 256 values are defined for each color plane (red, blue, and green), and, in total, there will be 2^{24} (or 16,777,216) colors defined by the color cube. This color cube is the same for all uint8 RGB images, regardless of which colors they actually use.

The uint8, uint16, and double color cubes all have the same range of colors. In other words, the brightest red in a uint8 RGB image appears the same as the brightest red in a double RGB image. The difference is that the double RGB color cube has many more shades of red (and many more shades of all colors). The following figure shows an RGB color cube for a uint8 image.



RGB Color Cube for uint8 Images

Quantization involves dividing the RGB color cube into a number of smaller boxes, and then mapping all colors that fall within each box to the color value at the *center* of that box.

Uniform quantization and minimum variance quantization differ in the approach used to divide up the RGB color cube. With uniform quantization, the color cube is cut up into equal-sized boxes (smaller cubes). With minimum variance quantization, the color cube is cut up into boxes (not necessarily cubes) of different sizes; the sizes of the boxes depend on how the colors are distributed in the image.


Uniform Quantization. To perform uniform quantization, call rgb2ind and specify a tolerance. The tolerance determines the size of the cube-shaped boxes into which the RGB color cube is divided. The allowable range for a tolerance setting is [0,1]. For example, if you specify a tolerance of 0.1, the edges of the boxes are one-tenth the length of the RGB color cube and the maximum total number of boxes is

$$n = (floor(1/tol)+1)^3$$

The commands below perform uniform quantization with a tolerance of 0.1.

```
RGB = imread('peppers.png');
[x,map] = rgb2ind(RGB, 0.1);
```

The following figure illustrates uniform quantization of a uint8 image. For clarity, the figure shows a two-dimensional slice (or color plane) from the color cube where red=0 and green and blue range from 0 to 255. The actual pixel values are denoted by the centers of the x's.



Uniform Quantization on a Slice of the RGB Color Cube

After the color cube has been divided, all empty boxes are thrown out. Therefore, only one of the boxes is used to produce a color for the colormap. As shown earlier, the maximum length of a colormap created by uniform quantization can be predicted, but the colormap can be smaller than the prediction because rgb2ind removes any colors that do not appear in the input image.

Minimum Variance Quantization. To perform minimum variance quantization, call rgb2ind and specify the maximum number of colors in the output image's colormap. The number you specify determines the number of boxes into which

the RGB color cube is divided. These commands use minimum variance quantization to create an indexed image with 185 colors.

```
RGB = imread('peppers.png');
[X,map] = rgb2ind(RGB,185);
```


Minimum variance quantization works by associating pixels into groups based on the variance between their pixel values. For example, a set of blue pixels might be grouped together because they have a small variance from the center pixel of the group.

In minimum variance quantization, the boxes that divide the color cube vary in size, and do not necessarily fill the color cube. If some areas of the color cube do not have pixels, there are no boxes in these areas.

While you set the number of boxes, n, to be used by rgb2ind, the placement is determined by the algorithm as it analyzes the color data in your image. Once the image is divided into n optimally located boxes, the pixels within each box are mapped to the pixel value at the center of the box, as in uniform quantization.

The resulting colormap usually has the number of entries you specify. This is because the color cube is divided so that each region contains at least one color that appears in the input image. If the input image uses fewer colors than the number you specify, the output colormap will have fewer than n colors, and the output image will contain all of the colors of the input image.

The following figure shows the same two-dimensional slice of the color cube as shown in the preceding figure (demonstrating uniform quantization). Eleven boxes have been created using minimum variance quantization.



Minimum Variance Quantization on a Slice of the RGB Color Cube

For a given number of colors, minimum variance quantization produces better results than uniform quantization, because it takes into account the actual data. Minimum variance quantization allocates more of the colormap entries to colors that appear frequently in the input image. It allocates fewer entries to colors that appear infrequently. As a result, the accuracy of the colors is higher than with uniform quantization. For example, if the input image has many shades of green and few shades of red, there will be more greens than reds in the output colormap. Note that the computation for minimum variance quantization takes longer than that for uniform quantization.

Colormap Mapping

If you specify an actual colormap to use, rgb2ind uses colormap mapping (instead of quantization) to find the colors in the specified colormap that best match the colors in the RGB image. This method is useful if you need to create images that use a fixed colormap. For example, if you want to display multiple indexed images on an 8-bit display, you can avoid color problems by mapping them all to the same colormap. Colormap mapping produces a good approximation if the specified colormap has similar colors to those in the RGB image. If the colormap does not have similar colors to those in the RGB image, this method produces poor results.

This example illustrates mapping two images to the same colormap. The colormap used for the two images is created on the fly using the MATLAB function colorcube, which creates an RGB colormap containing the number of colors that you specify. (colorcube always creates the same colormap for a given number of colors.) Because the colormap includes colors all throughout the RGB color cube, the output images can reasonably approximate the input images.

```
RGB1 = imread('autumn.tif');
RGB2 = imread('peppers.png');
X1 = rgb2ind(RGB1,colorcube(128));
X2 = rgb2ind(RGB2,colorcube(128));
```

Note The function subimage is also helpful for displaying multiple indexed images. For more information, see "Displaying Multiple Images in the Same Figure" on page 3-42 or the reference page for subimage.

Reducing Colors in an Indexed Image

Use imapprox when you need to reduce the number of colors in an indexed image. imapprox is based on rgb2ind and uses the same approximation methods. Essentially, imapprox first calls ind2rgb to convert the image to RGB format, and then calls rgb2ind to return a new indexed image with fewer colors.

For example, these commands create a version of the trees image with 64 colors, rather than the original 128.

```
load trees
[Y, newmap] = imapprox(X, map, 64);
imshow(Y, newmap);
```

The quality of the resulting image depends on the approximation method you use, the range of colors in the input image, and whether or not you use dithering. Note that different methods work better for different images. See "Dithering" on page 13-13 for a description of dithering and how to enable or disable it.

Dithering

When you use rgb2ind or imapprox to reduce the number of colors in an image, the resulting image might look inferior to the original, because some of the colors are lost. rgb2ind and imapprox both perform *dithering* to increase the apparent number of colors in the output image. Dithering changes the colors of pixels in a neighborhood so that the average color in each neighborhood approximates the original RGB color.

For an example of how dithering works, consider an image that contains a number of dark orange pixels for which there is no exact match in the colormap. To create the appearance of this shade of orange, the Image Processing Toolbox selects a combination of colors from the colormap, that, taken together as a six-pixel group, approximate the desired shade of pink. From a distance, the pixels appear to be the correct shade, but if you look up close at the image, you can see a blend of other shades. This example loads a 24-bit image, and then use rgb2ind to create two indexed images with just eight colors each:

1 Read image and display it.

```
rgb=imread('onion.png');
imshow(rgb);
```



2 Create an indexed image with eight colors and without dithering.

```
[X_no_dither,map]=rgb2ind(rgb,8,'nodither');
figure, imshow(X no dither,map);
```



3 Create an indexed image using eight colors with dithering.

```
[X_dither,map]=rgb2ind(rgb,8,'dither');
figure, imshow(X_dither,map);
```



Notice that the dithered image has a larger number of apparent colors but is somewhat fuzzy-looking. The image produced without dithering has fewer apparent colors, but an improved spatial resolution when compared to the dithered image. One risk in doing color reduction without dithering is that the new image can contain false contours.

Converting Color Data Between Color Spaces

The Image Processing Toolbox represents colors as RGB values, either directly (in an RGB image) or indirectly (in an indexed image, where the colormap is stored in RGB format). However, there are other models besides RGB for representing colors numerically. The various models are referred to as *color spaces* because most of them can be mapped into a 2-D, 3-D, or 4-D coordinate system; thus, a color specification is made up of coordinates in a 2-D, 3-D, or 4-D space.

The various color spaces exist because they present color information in ways that make certain calculations more convenient or because they provide a way to identify colors that is more intuitive. For example, the RGB color space defines a color as the percentages of red, green, and blue hues mixed together. Other color models describe colors by their hue (green), saturation (dark green), and luminance, or intensity.

The toolbox supports these color spaces by providing a means for converting color data from one color space to another through a mathematical transformation.

This section

- Describes how to convert color data between these color spaces
- Describes how to perform color space conversions using ICC profiles
- Describes some toolbox functions for converting between the RGB color space and three commonly used color spaces: YIQ, HSV, and YCbCr

Converting Between Device-Independent Color Spaces

The standard terms used to describe colors, such as hue, brightness, and intensity, are subjective and make comparisons difficult.

In 1931, the International Commission on Illumination, known by the acronym CIE, for *Commission Internationale de l'Éclairage*, studied human color perception and developed a standard, called the CIE *XYZ*. This standard defined a three-dimensional space where three values, called tristimulus values, define a color. This standard is still widely used today.

In the decades since that initial specification, the CIE has developed several additional color space specifications that attempt to provide alternative color

representations that are better suited to some purposes than XYZ. For example, in 1976, in an effort to get a perceptually uniform color space that could be correlated with the visual appearance of colors, the CIE created the $L^*a^*b^*$ color space.

The toolbox supports conversions between members of the CIE family of device-independent color spaces. In addition, the toolbox also supports conversions between these CIE color spaces and the sRGB color space. This color space was defined by an industry group to describe the characteristics of a typical PC monitor.

This section

- Lists the supported device-independent color spaces
- Provides an example of how to perform a conversion
- Provides guidelines about data type support of the various conversions

Supported Conversions

This table lists all the device-independent color spaces that the toolbox supports.

Color Space	Description	Supported Conversions	
XYZ	The original, 1931 CIE color space specification.	xyY , uvl , $u'v'L$, and $L^*a^*b^*$	
xyY	CIE specification that provides normalized chromaticity values. The capital Y value represents luminance and is the same as in XYZ.	XYZ	
uvL	CIE specification that attempts to make the chromaticity plane more visually uniform. l is luminance and is the same as Y in XYZ.	ty plane more s luminance and is	
u'v'L	CIE specification in which u and v are rescaled to improve uniformity.	XYZ	

Color Space	Description	Supported Conversions
$L^*a^*b^*$	CIE specification that attempts to make the luminance scale more perceptually uniform. L^* is a nonlinear scaling of L , normalized to a reference white point.	XYZ
L*ch	CIE specification where c is chroma and h is hue. These values are a polar coordinate conversion of a^* and b^* in $L^*a^*b^*$.	L*a*b*
sRGB	Standard adopted by major manufacturers that characterizes the average PC monitor.	XYZ and $L^*a^*b^*$

Example: Performing a Color Space Conversion

To illustrate a conversion between two device-independent color spaces, this example reads an RGB color image into the MATLAB workspace and converts the color data to the XYZ color space:

1 Import color space data. This example reads an RGB color image into the MATLAB workspace.

```
I rgb = imread('peppers.png');
```

2 Create a color transformation structure. A color transformation structure defines the conversion between two color spaces. You use the makecform function to create the structure, specifying a transformation type string as an argument.

This example creates a color transformation structure that defines a conversion from RGB color data to *XYZ* color data.

```
C = makecform('srgb2xyz');
```

3 Perform the conversion. You use the applycform function to perform the conversion, specifying as arguments the color data you want to convert and

the color transformation structure that defines the conversion. The applycform function returns the converted data.

$I_xyz = apple$	olyctorm(l_rgb,C);		
whos Name	Size	Bytes	Class
С	1x1	7744	struct array
I_xyz	384x512x3	1179648	uint16 array
I rgb	384x512x3	589824	uint8 array

Color Space Data Encodings

When you convert between two device-independent color spaces, the data type used to encode the color data can sometimes change, depending on what encodings the color spaces support. In the preceding example, the original image is uint8 data. The XYZ conversion is uint16 data. The XYZ color space does not define a uint8 encoding. The following table lists the data types that can be used to represent values in all the device-independent color spaces.

Color Space	Encodings
XYZ	uint16 or double
xyY	double
uvL	double
u'v'L	double
L*a*b*	uint8, uint16, or double
L*ch	double
sRGB	double

As the table indicates, certain color spaces have data type limitations. For example, the XYZ color space does not define a uint8 encoding. If you convert 8-bit CIE LAB data into the XYZ color space, the data is returned in uint16 format. If you want the returned XYZ data to be in the same format as the input LAB data, you can use one of the following toolbox color space format conversion functions.

- lab2double
- lab2uint8
- lab2uint16
- xyz2double
- xyz2uint16

Performing Profile-Based Conversions

The Image Processing Toolbox can perform color space conversions based on device profiles. This section includes the following topics:

- "Understanding Device Profiles" on page 13-19
- "Reading ICC Profiles" on page 13-20
- "Writing Profile Information to a File" on page 13-20
- "Example: Performing a Profile-Based Conversion" on page 13-21
- "Specifying the Rendering Intent" on page 13-22

Understanding Device Profiles

If two colors have the same CIE colorimetry, they will match *if viewed under the same conditions*. However, because color images are typically produced for a wide variety of viewing environments, it is necessary to go beyond simple application of the CIE system.

For this reason, the International Color Consortium (ICC) has defined a Color Management System (CMS) that provides a means for communicating color information among input, output, and display devices. The CMS uses device *profiles* that contain color information specific to a particular device. Vendors that support CMS provide profiles that characterize the color reproduction of their devices, and methods, called Color Management Modules (CMM), that interpret the contents of each profile and perform the necessary image processing.

Device profiles contain the information that color management systems need to translate color data between devices. Any conversion between color spaces is a mathematical transformation from some domain space to a range space. With profile-based conversions, the domain space is often called the *source space* and the range space is called the *destination space*. In the ICC color management model, profiles are used to represent the source and destination spaces.

For more information about color management systems, go to the International Color Consortium Web site, www.color.org.

Reading ICC Profiles

To read an ICC profile into the MATLAB workspace, use the iccread function. In this example, the function reads in the profile for the color space that describes color monitors.

```
P = iccread('sRGB.icm');
```

iccread returns the contents of the profile in the structure P. All profiles contain a header, a tag table, and a series of tagged elements. The header contains general information about the profile, such as the device class, the device color space, and the file size. The tagged elements, or tags, are the data constructs that contain the information used by the CMM. For more information about the contents of a profile, see the iccread function reference page.

Using iccread, you can read both Version 2 (ICC.1:2001-04) or Version 4 (ICC.1:2001-12) ICC profile formats. For detailed information about these specifications and their differences, visit the ICC web site, www.color.org.

Writing Profile Information to a File

To export ICC profile information from the MATLAB workspace to a file, use the iccwrite function. This example reads a profile into the MATLAB workspace and then writes the profile information out to a new file.

```
P = iccread('sRGB.icm');
P new = iccwrite(P,'my profile.icm');
```

iccwrite returns the profile it writes to the file in P new because it can be different than the input profile P. For example, iccwrite updates the Filename field in P to match the name of the file specified as the second argument.

iccwrite checks the validity of the input profile structure. If any required fields are missing, iccwrite errors. To determine if a structure is a valid ICC profile, use the isicc function.

Using iccwrite, you can export profile information in both Version 2 (ICC.1:2001-04) or Version 4 (ICC.1:2001-12) ICC profile formats. The value of the Version field in the file profile header determines the format version. For

detailed information about these specifications and their differences, visit the ICC web site, www.color.org.

Example: Performing a Profile-Based Conversion

To illustrate a profile-based color space conversion, this section presents an example that converts color data from the RGB space of a monitor to the CMYK space of a printer. This conversion requires two profiles: a monitor profile and a printer profile. The source color space in this example is monitor RGB and the destination color space is printer CMYK:

1 Import RGB color space data. This example imports an RGB color image into the MATLAB workspace.

```
I_rgb = imread('peppers.png');
```

2 Read ICC profiles. Read the source and destination profiles into the MATLAB workspace. This example uses the sRGB profile as the source profile. The sRGB profile is an industry-standard color space that describes a color monitor.

```
inprof = iccread('sRGB.icm');
```

For the destination profile, the example uses a profile that describes a particular color printer. The printer vendor supplies this profile. (The following profile and several other useful profiles can be obtained as downloads from www.adobe.com.)

```
outprof = iccread('USSheetfedCoated.icc');
```

3 Create a color transformation structure. You must create a color transformation structure to define the conversion between the color spaces in the profiles. You use the makecform function to create the structure, specifying a transformation type string as an argument.

Note The color space conversion might involve an intermediate conversion into a device-independent color space, called the Profile Connection Space (PCS), but this is transparent to the user.

This example creates a color transformation structure that defines a conversion from RGB color data to CMYK color data.

```
C = makecform('icc',inprof,outprof);
```

4 Perform the conversion. You use the applycform function to perform the conversion, specifying as arguments the color data you want to convert and the color transformation structure that defines the conversion. The function returns the converted data.

```
I cmyk = applycform(I rgb,C);
```

5 Write the converted data to a file. To export the CMYK data, use the imwrite function, specifying the format as TIFF. If the format is TIFF and the data is an m-by-n-by-4 array, imwrite writes CMYK data to the file.

```
imwrite(I cmyk, 'pep cmyk.tif', 'tif')
```

To verify that the CMYK data was written to the file, use imfinfo to get information about the file and look at the Photometric Interpretation field

```
info = imfinfo('pep cmyk.tif');
info.PhotometricInterpretation
ans =
   'CMYK'
```

Specifying the Rendering Intent

For most devices, the range of reproducible colors is much smaller than the range of colors represented by the PCS. It is for this reason that four rendering intents (or gamut mapping techniques) are defined in the profile format. Each one has distinct aesthetic and color-accuracy tradeoffs.

When you create a profile-based color transformation structure, you can specify the rendering intent for the source as well as the destination profiles. For more information, see the makecform reference information.

Converting Between Device-Dependent Color Spaces

The toolbox includes functions that you can use to convert RGB data to several common device-dependent color spaces, and vice versa:

- YIQ
- YCbCr
- Hue, saturation, value (HSV)

YIQ Color Space

The National Television Systems Committee (NTSC) defines a color space known as YIQ. This color space is used in televisions in the United States. One of the main advantages of this format is that grayscale information is separated from color data, so the same signal can be used for both color and black and white sets.

In the NTSC color space, image data consists of three components: luminance (Y), hue (I), and saturation (Q). The first component, luminance, represents grayscale information, while the last two components make up chrominance (color information).

The function rgb2ntsc converts colormaps or RGB images to the NTSC color space. ntsc2rgb performs the reverse operation.

For example, these commands convert an RGB image to NTSC format.

```
RGB = imread('peppers.png');
YIQ = rgb2ntsc(RGB);
```

Because luminance is one of the components of the NTSC format, the RGB to NTSC conversion is also useful for isolating the gray level information in an image. In fact, the toolbox functions rgb2gray and ind2gray use the rgb2ntsc function to extract the grayscale information from a color image.

For example, these commands are equivalent to calling rgb2gray.

```
YIQ = rgb2ntsc(RGB);
```

```
I = YIQ(:,:,1);
```

Note In the YIQ color space, I is one of the two color components, not the grayscale component.

YCbCr Color Space

The YCbCr color space is widely used for digital video. In this format, luminance information is stored as a single component (Y), and chrominance information is stored as two color-difference components (Cb and Cr). Cb represents the difference between the blue component and a reference value. Cr represents the difference between the red component and a reference value.

YCbCr data can be double precision, but the color space is particularly well suited to uint8 data. For uint8 images, the data range for Y is [16, 235], and the range for Cb and Cr is [16, 240]. YCbCr leaves room at the top and bottom of the full uint8 range so that additional (nonimage) information can be included in a video stream.

The function rgb2ycbcr converts colormaps or RGB images to the YCbCr color space. ycbcr2rgb performs the reverse operation.


For example, these commands convert an RGB image to YCbCr format.

```
RGB = imread('peppers.png');
YCBCR = rgb2vcbcr(RGB);
```

HSV Color Space

The HSV color space (hue, saturation, value) is often used by people who are selecting colors (e.g., of paints or inks) from a color wheel or palette, because it corresponds better to how people experience color than the RGB color space does. The functions rgb2hsv and hsv2rgb convert images between the RGB and HSV color spaces.

As hue varies from 0 to 1.0, the corresponding colors vary from red through yellow, green, cyan, blue, magenta, and back to red, so that there are actually red values both at 0 and 1.0. As saturation varies from 0 to 1.0, the corresponding colors (hues) vary from unsaturated (shades of gray) to fully saturated (no white component). As value, or brightness, varies from 0 to 1.0, the corresponding colors become increasingly brighter.



The following figure illustrates the HSV color space.

Illustration of the HSV Color Space


The rgb2hsv function converts colormaps or RGB images to the HSV color space. hsv2rgb performs the reverse operation. These commands convert an RGB image to the HSV color space.

```
RGB = imread('peppers.png');
HSV = rgb2hsv(RGB);
```

For closer inspection of the HSV color space, the next block of code displays the separate color planes (hue, saturation, and value) of an HSV image.

```
RGB=reshape(ones(64,1)*reshape(jet(64),1,192),[64,64,3]);
HSV=rgb2hsv(RGB);
H=HSV(:,:,1);
S=HSV(:,:,2);
V=HSV(:,:,3);
imshow(H)
figure, imshow(S);
```

```
figure, imshow(V);
figure, imshow(RGB);
```



The Separated Color Planes of an HSV Image

As the hue plane image in the preceding figure illustrates, hue values make a linear transition from high to low. If you compare the hue plane image against the original image, you can see that shades of deep blue have the highest values, and shades of deep red have the lowest values. (As stated previously, there are values of red on both ends of the hue scale. To avoid confusion, the sample image uses only the red values from the beginning of the hue range.)

Saturation can be thought of as the purity of a color. As the saturation plane image shows, the colors with the highest saturation have the highest values and are represented as white. In the center of the saturation image, notice the various shades of gray. These correspond to a mixture of colors; the cyans, greens, and yellow shades are mixtures of true colors. Value is roughly

equivalent to brightness, and you will notice that the brightest areas of the value plane correspond to the brightest colors in the original image.

Neighborhood and Block Operations

This chapter discusses these generic block processing functions. Topics covered include

Terminology (p. 14-2) Provides definitions of image processing terms used in

this section

Block Processing Operations (p. 14-3) Provides an overview of the types of block processing

operations supported by the toolbox

Sliding Neighborhood Operations Defines sliding neighborhood operations and describes

how you can use them to implement many types of

filtering operations

Distinct Block Operations (p. 14-8) Describes block operations

(p. 14-4)

Column Processing (p. 14-11) Describes how to process sliding neighborhoods or

distinct blocks as columns

Terminology

An understanding of the following terms will help you to use this section.

Term	Definition
block operation	Operation in which an image is processed in blocks rather than all at once. The blocks have the same size across the image. Some operation is applied to one block at a time. The blocks are reassembled to form an output image.
border padding	Additional rows and columns temporarily added to the border(s) of an image when some of the blocks extend outside the image. The additional rows and columns normally contain zeros.
center pixel	Pixel at the center of a neighborhood.
column processing	Operation in which neighborhoods are reshaped into columns before processing in order to speed up computation time.
distinct block operation	Block operation in which the blocks do not overlap.
neighborhood operation	Operation in which each output pixel is computed from a set of neighboring input pixels. Convolution, dilation, and median filtering are examples of neighborhood operations. A neighborhood operation can also be called a sliding neighborhood operation.
overlap	Extra rows and columns of pixels outside a block whose values are taken into account when processing the block. These extra pixels cause distinct blocks to overlap one another. The blkproc function enables you to specify an overlap.

Block Processing Operations

Certain image processing operations involve processing an image in sections called *blocks*, rather than processing the entire image at once. The Image Processing Toolbox provides several functions for specific operations that work with blocks, for example, the imdilate function for image dilation. In addition, the toolbox provides more generic functions for processing an image in blocks. This section discusses these generic block processing functions.

To use one of the functions, you supply information about the size of the blocks, and specify a separate function to use to process the blocks. The block processing function does the work of breaking the input image into blocks, calling the specified function for each block, and reassembling the results into an output image.

Types of Block Processing Operations

Using these functions, you can perform various block processing operations, including *sliding neighborhood operations* and *distinct block operations*:

- In a sliding neighborhood operation, the input image is processed in a pixelwise fashion. That is, for each pixel in the input image, some operation is performed to determine the value of the corresponding pixel in the output image. The operation is based on the values of a block of neighboring pixels.
- In a distinct block operation, the input image is processed a block at a time. That is, the image is divided into rectangular blocks, and some operation is performed on each block individually to determine the values of the pixels in the corresponding block of the output image.


In addition, the toolbox provides functions for *column processing operations*. These operations are not actually distinct from block operations; instead, they are a way of speeding up block operations by rearranging blocks into matrix columns.

Note that even if you do not use these block processing functions, the information here might be useful to you, as it includes concepts fundamental to many areas of image processing. In particular, the discussion of sliding neighborhood operations is applicable to linear filtering and morphological operations. See Chapter 7, "Linear Filtering and Filter Design," and Chapter 9, "Morphological Operations," for information about these applications.

Sliding Neighborhood Operations

A sliding neighborhood operation is an operation that is performed a pixel at a time, with the value of any given pixel in the output image being determined by the application of an algorithm to the values of the corresponding input pixel's neighborhood. A pixel's neighborhood is some set of pixels, defined by their locations relative to that pixel, which is called the *center pixel*. The neighborhood is a rectangular block, and as you move from one element to the next in an image matrix, the neighborhood block slides in the same direction.

The following figure shows the neighborhood blocks for some of the elements in a 6-by-5 matrix with 2-by-3 sliding blocks. The center pixel for each neighborhood is marked with a dot.



Neighborhood Blocks in a 6-by-5 Matrix

The center pixel is the actual pixel in the input image being processed by the operation. If the neighborhood has an odd number of rows and columns, the center pixel is actually in the center of the neighborhood. If one of the dimensions has even length, the center pixel is just to the left of center or just above center. For example, in a 2-by-2 neighborhood, the center pixel is the upper left one.

For any m-by-n neighborhood, the center pixel is

$$floor(([m n]+1)/2)$$

In the 2-by-3 block shown in Figure, the center pixel is (1,2), or the pixel in the second column of the top row of the neighborhood.

To perform a sliding neighborhood operation,

- 1 Select a single pixel.
- **2** Determine the pixel's neighborhood.
- **3** Apply a function to the values of the pixels in the neighborhood. This function must return a scalar.
- **4** Find the pixel in the output image whose position corresponds to that of the center pixel in the input image. Set this output pixel to the value returned by the function.
- **5** Repeat steps 1 through 4 for each pixel in the input image.

For example, the function might be an averaging operation that sums the values of the neighborhood pixels and then divides the result by the number of pixels in the neighborhood. The result of this calculation is the value of the output pixel.

Padding Borders

As the neighborhood block slides over the image, some of the pixels in a neighborhood might be missing, especially if the center pixel is on the border of the image. For example, if the center pixel is the pixel in the upper left corner of the image, the neighborhoods include pixels that are not part of the image.

To process these neighborhoods, sliding neighborhood operations *pad* the borders of the image, usually with 0's. In other words, these functions process the border pixels by assuming that the image is surrounded by additional rows and columns of 0's. These rows and columns do not become part of the output image and are used only as parts of the neighborhoods of the actual pixels in the image.

Linear and Nonlinear Filtering

You can use sliding neighborhood operations to implement many kinds of filtering operations. One example of a sliding neighbor operation is convolution, which is used to implement linear filtering. MATLAB provides the conv and filter2 functions for performing convolution, and the toolbox

provides the imfilter function. See Chapter 7, "Linear Filtering and Filter Design," for more information about these functions.

In addition to convolution, there are many other filtering operations you can implement through sliding neighborhoods. Many of these operations are nonlinear in nature. For example, you can implement a sliding neighborhood operation where the value of an output pixel is equal to the standard deviation of the values of the pixels in the input pixel's neighborhood.

You can use the nlfilter function to implement a variety of sliding neighborhood operations. nlfilter takes as input arguments an image, a neighborhood size, and a function that returns a scalar, and returns an image of the same size as the input image. The value of each pixel in the output image is computed by passing the corresponding input pixel's neighborhood to the function. For example, this call computes each output pixel by taking the standard deviation of the values of the input pixel's 3-by-3 neighborhood (that is, the pixel itself and its eight contiguous neighbors).

```
I2 = nlfilter(I,[3 3], 'std2');
```

You can write an M-file to implement a specific function, and then use this function with nlfilter. For example, this command processes the matrix I in 2-by-3 neighborhoods with a function called myfun.m.

```
nlfilter(I,[2 3],@myfun);
```

@myfun is an example of a function handle. You can also use an inline function. For example:

```
f = inline('sqrt(min(x(:)))');
I2 = nlfilter(I,[2 2],f);
```

The example below uses nlfilter to set each pixel to the maximum value in its 3-by-3 neighborhood.

```
I = imread('tire.tif');
f = inline('max(x(:))');
I2 = nlfilter(I,[3 3],f);
imshow(I);
figure, imshow(I2);
```





Each Output Pixel Set to Maximum Input Neighborhood Value

Many operations that nlfilter can implement run much faster if the computations are performed on matrix columns rather than rectangular neighborhoods. For information about this approach, see the reference page for colfilt.

Note nlfilter is an example of a "function function." For more information on how to use this kind of function, see "Function Functions" in the MATLAB documentation. For more information on inline functions, see inline in the MATLAB Function Reference documentation. For more information on function handles, see function_handle in the MATLAB Function Reference documentation.

Distinct Block Operations

Distinct blocks are rectangular partitions that divide a matrix into m-by-n sections. Distinct blocks overlay the image matrix starting in the upper left corner, with no overlap. If the blocks don't fit exactly over the image, the toolbox adds zero padding so that they do. The following figure shows a 15-by-30 matrix divided into 4-by-8 blocks.




Image Divided into Distinct Blocks

The zero padding process adds 0's to the bottom and right of the image matrix, as needed. After zero padding, the matrix is size 16-by-32.

The function blkproc performs distinct block operations. blkproc extracts each distinct block from an image and passes it to a function you specify. blkproc assembles the returned blocks to create an output image.

For example, the command below processes the matrix I in 4-by-6 blocks with the function myfun.

```
I2 = blkproc(I, [4 6], @myfun);
```

You can specify the function as an inline function. For example:

```
f = inline('mean2(x)*ones(size(x))');
I2 = blkproc(I, [4 6], f);
```

The example below uses blkproc to set every pixel in each 8-by-8 block of an image matrix to the average of the elements in that block.

```
I = imread('tire.tif');
f = inline('uint8(round(mean2(x)*ones(size(x))))');
I2 = blkproc(I,[8 8],f);
imshow(I)
figure, imshow(I2);
```





Notice that inline computes the mean of the block and then multiplies the result by a matrix of ones, so that the output block is the same size as the input block. As a result, the output image is the same size as the input image. blkproc does not require that the images be the same size; however, if this is the result you want, you must make sure that the function you specify returns blocks of the appropriate size.

Note blkproc is an example of a "function function." For more information on how to use this kind of function, see the "Function Functions" section in the MATLAB documentation.

Overlap

When you call blkproc to define distinct blocks, you can specify that the blocks overlap each other, that is, you can specify extra rows and columns of pixels outside the block whose values are taken into account when processing the block. When there is an overlap, blkproc passes the expanded block (including the overlap) to the specified function.

The following figure shows the overlap areas for some of the blocks in a 15-by-30 matrix with 1-by-2 overlaps. Each 4-by-8 block has a one-row overlap above and below, and a two-column overlap on each side. In the figure, shading indicates the overlap. The 4-by-8 blocks overlay the image matrix starting in the upper left corner.




Image Divided into Distinct Blocks with Specified Overlaps

To specify the overlap, you provide an additional input argument to blkproc. To process the blocks in the figure above with the function myfun, the call is

$$B = blkproc(A, [4 8], [1 2], @myfun)$$

Overlap often increases the amount of zero padding needed. For example, in the figure, the original 15-by-30 matrix became a 16-by-32 matrix with zero padding. When the 15-by-30 matrix includes a 1-by-2 overlap, the padded matrix becomes an 18-by-36 matrix. The outermost rectangle in the figure delineates the new boundaries of the image after padding has been added to accommodate the overlap plus block processing. Notice that in the preceding figure, padding has been added to the left and top of the original image, not just to the right and bottom.

Column Processing

The toolbox provides functions that you can use to process sliding neighborhoods or distinct blocks as columns. This approach is useful for operations that MATLAB performs columnwise; in many cases, column processing can reduce the execution time required to process an image.

For example, suppose the operation you are performing involves computing the mean of each block. This computation is much faster if you first rearrange the blocks into columns, because you can compute the mean of every column with a single call to the mean function, rather than calling mean for each block individually.


You can use the colfilt function to implement column processing. This function

- 1 Reshapes each sliding or distinct block of an image matrix into a column in a temporary matrix
- **2** Passes the temporary matrix to a function you specify
- **3** Rearranges the resulting matrix back into the original shape

Sliding Neighborhoods

For a sliding neighborhood operation, colfilt creates a temporary matrix that has a separate column for each pixel in the original image. The column corresponding to a given pixel contains the values of that pixel's neighborhood from the original image.

The following figure illustrates this process. In this figure, a 6-by-5 image matrix is processed in 2-by-3 neighborhoods. colfilt creates one column for each pixel in the image, so there are a total of 30 columns in the temporary matrix. Each pixel's column contains the value of the pixels in its neighborhood, so there are six rows. colfilt zero-pads the input image as necessary. For example, the neighborhood of the upper left pixel in the figure has two zero-valued neighbors, due to zero padding.



colfilt Creates a Temporary Matrix for Sliding Neighborhood

The temporary matrix is passed to a function, which must return a single value for each column. (Many MATLAB functions work this way, for example, mean, median, std, sum, etc.) The resulting values are then assigned to the appropriate pixels in the output image.


colfilt can produce the same results as nlfilter with faster execution time; however, it might use more memory. The example below sets each output pixel to the maximum value in the input pixel's neighborhood, producing the same result as the nlfilter example shown in "Linear and Nonlinear Filtering" on page 14-5.

I2 = colfilt(I,[3 3], 'sliding',@max);

Distinct Blocks

For a distinct block operation, colfilt creates a temporary matrix by rearranging each block in the image into a column. colfilt pads the original image with 0's, if necessary, before creating the temporary matrix.

The following figure illustrates this process. A 6-by-16 image matrix is processed in 4-by-6 blocks. colfilt first zero-pads the image to make the size 8-by-18 (six 4-by-6 blocks), and then rearranges the blocks into six columns of 24 elements each.



colfilt Creates a Temporary Matrix for Distinct Block Operation

After rearranging the image into a temporary matrix, colfilt passes this matrix to the function. The function must return a matrix of the same size as the temporary matrix. If the block size is m-by-n, and the image is mm-by-nn, the size of the temporary matrix is (m*n)-by-(ceil(mm/m)*ceil(nn/n)). After the function processes the temporary matrix, the output is rearranged into the shape of the original image matrix.

This example sets all the pixels in each 8-by-8 block of an image to the mean pixel value for the block, producing the same result as the blkproc example in "Distinct Block Operations" on page 14-8.

```
I = im2double(imread('tire.tif'));
f = inline('ones(64,1)*mean(x)');
I2 = colfilt(I,[8 8],'distinct',f);
```

Notice that the inline function computes the mean of the block and then multiplies the result by a vector of ones, so that the output block is the same size as the input block. As a result, the output image is the same size as the input image.

Restrictions

You can use colfilt to implement many of the same distinct block operations that blkproc performs. However, colfilt has certain restrictions that blkproc does not:

- The output image must be the same size as the input image.
- The blocks cannot overlap.

For situations that do not satisfy these constraints, use blkproc.

Function Reference

This section describes the Image Processing Toolbox functions.

Functions – Categorical List (p. 15-2) Contains a group of tables that organize the toolbox functions into category groups

Functions – Alphabetical List (p. 15-20) Contains separate reference pages for each toolbox function

Functions - Categorical List

This section provides brief descriptions of all the functions in the Image Processing Toolbox. The functions are listed in tables in the following broad categories.

If you know the name of a function, use "Functions — Alphabetical List" to find the reference page.

Image Input, Output, and Display (p. 15-3)	Functions for importing, exporting, and displaying images and converting between image formats
Modular Interactive Tools (p. 15-5)	Functions for creating the modular interactive tools, with associated utility functions.
Spatial Transformation and Registration (p. 15-7)	Functions for performing spatial transformations and image registration
Image Analysis and Statistics (p. 15-8)	Functions for performing image analysis and getting pixel values and statistics
Image Arithmetic (p. 15-9)	Functions for performing arithmetic operations on images, such as adding, subtracting, multiplying, and dividing.
Image Enhancement and Restoration (p. 15-10)	Functions for image enhancement and restoration, such as deblurring
Linear Filtering and Transforms (p. 15-11)	Functions for creating and using linear filters and transforms
Morphological Operations (p. 15-13)	Functions for performing morphological image processing
Region-Based, Neighborhood, and Block Processing (p. 15-15)	Functions to define regions of interest and operate on these regions

Colormap and Color Space

Functions (p. 15-16)

Functions for working with image color

Miscellaneous Functions

(p. 15-18)

Functions that perform array operations, and set and get Image Processing Toolbox

preferences

Image Input, Output, and Display

• Image Display (p. 15-3)

• Image File I/O (p. 15-3)

• Image Types and Type Conversions (p. 15-4)

Image Display

colorbar Display color bar (MATLAB function)

image Create and display image object (MATLAB function)

imagesc Scale data and display as image (MATLAB function)

immovie Make movie from multiframe indexed image imshow Display image in a MATLAB figure window

imtool Display image in the Image Viewer

montage Display multiple image frames as rectangular montage

subimage Display multiple images in single figure
warp Display image as texture-mapped surface

Image File I/O

dicomanon Anonymize a DICOM file

dicomdict Specify which DICOM data dictionary to use

dicominfo Read metadata from a DICOM message

dicomread Read a DICOM image

dicomuid Generate DICOM unique identifier

dicomwrite Write a DICOM image

dicom-dict.txt Text file containing DICOM data dictionary

imfinfo Return information about image file (MATLAB function)

imread Read image file (MATLAB function) imwrite Write image file (MATLAB function)

Image Types and Type Conversions

dither Convert image using dithering

double Convert data to double precision (MATLAB function)

gray2ind Convert intensity image to indexed image

gravslice Create indexed image from intensity image by

thresholding

Compute global image threshold using Otsu's method graythresh

im2bw Convert image to binary image by thresholding

im2double Convert image array to double precision

im2int16 Convert image array to 16-bit signed integer

im2java Convert image to instance of Java image object

(MATLAB function)

im2java2d Convert image to instance of Java buffered image object

Convert indexed image to intensity image

im2single Convert image array to single precision

im2uint16 Convert image array to 16-bit unsigned integers im2uint8

Convert image array to 8-bit unsigned integers ind2grav

ind2rgb Convert indexed image to RGB image

int16 Convert data to signed 16-bit integers (MATLAB

function)

label2rgb Convert a label matrix to an RGB image

mat2gray Convert matrix to intensity image rgb2gray Convert RGB image or colormap to grayscale

rgb2ind Convert RGB image to indexed image

uint16 Convert data to unsigned 16-bit integers (MATLAB

function)

uint8 Convert data to unsigned 8-bit integers (MATLAB

function)

Modular Interactive Tools

• Modular Tool Creation Functions (p. 15-5)

• Navigational tools (p. 15-6)

• Utility Functions (p. 15-6)

Modular Tool Creation Functions

imageinfo Image Information tool

impixelinfo Pixel Information tool

impixelinfoval Pixel Information tool, without text label

impixelregion Pixel Region tool

impixelregionpanel Pixel Region scroll panel

Navigational tools

immagbox Image Information tool imoverview Adjust Contrast tool imoverviewpanel Display range tool imscrollpanel Pixel Information tool

Utility Functions

axes2pix Convert axes coordinate to pixel coordinate

getimage Get image data from axes

getimagemodel Retrieve imagemodel objects from image handles

imattributes Return information about image attributes

imgca Get handle to current image axes imgcf Get handle to current image figure

imgetfile Image Open File dialog box

imhandles Get all image handles

impositionrect Create position rectangle

iptaddcallback Add function handle to callback list

iptcheckhandle Check validity of handle

iptgetapi Get Application Programmer Interface from a handle

ipticondir Directories containing IPT and MATLAB icons

iptremovecallback Delete function handle from callback list

iptwindowalign Align figure windows

truesize Adjust display size of image

Spatial Transformation and Registration

- Spatial Transformations (p. 15-7)
- Image Registration (p. 15-7)

Spatial Transformations

checkerboard Create checkerboard image

findbounds Find output bounds for spatial transformation

fliptform Flip the input and output roles of a TFORM structure

imcrop Crop imageimresize Resize imageimrotate Rotate image

imtransform Apply 2-D spatial transformation to image

makeresampler Create resampling structure

maketform Create geometric transformation structure

tformarray Geometric transformation of a multidimensional array

tformfwd Apply forward geometric transformation
tforminv Apply inverse geometric transformation

Image Registration

cp2tform Infer geometric transformation from control point pairs

cpcorr Tune control point locations using cross-correlation

cpselect Control point selection tool

 ${\tt cpstruct2pairs} \quad Convert \; {\tt CPSTRUCT} \; to \; valid \; pairs \; of \; control \; points \\$

normxcorr2 Normalized two-dimensional cross-correlation

Image Analysis and Statistics

• Image Analysis (p. 15-8)

• Pixel Values and Statistics (p. 15-8)

Image Analysis

bwboundaries Trace region boundaries in binary image

bwtraceboundary Trace object in binary image edge Find edges in intensity image

hough Hough transform

houghlines Extract line segments based on the Hough transform

houghpeaks Identify peaks in the Hough transform

qtdecomp Perform quadtree decomposition

qtgetblk Get block values in quadtree decomposition qtsetblk Set block values in quadtree decomposition

Texture Analysis

entropy Entropy of an intensity image

entropyfilt Local entropy of an intensity image graycomatrix Gray-level co-occurrence matrix

graycoprops Properties of a gray-level co-occurrence matrix

rangefilt Local range of an image

stdfilt Local standard deviation of an image

Pixel Values and Statistics

corr2 Compute 2-D correlation coefficient imcontour Create contour plot of image data imhist Display histogram of image data impixel Determine pixel color values

improfile Compute pixel-value cross-sections along line segments

mean2 Compute mean of matrix elements

pixval Display information about image pixels

regionprops Measure properties of image regions

std2 Compute standard deviation of matrix elements

Image Arithmetic

imabsdiff Compute absolute difference of two images imadd Add two images, or add constant to image

imcomplement Complement image

imdivide Divide two images, or divide image by constant

imlincomb Compute linear combination of images

immultiply Multiply two images, or multiply image by constant
imsubtract Subtract two images, or subtract constant from image

Image Enhancement and Restoration

- Image Enhancement (p. 15-10)
- Image Restoration (Deblurring) (p. 15-10)

Image Enhancement

_	
adapthisteq	Perform adaptive histogram equalization using CLAHE
decorrstretch	Apply a decorrelation stretch to a multichannel image
histeq	Enhance contrast using histogram equalization
imadjust	Adjust image intensity values or colormap
imnoise	Add noise to an image
intlut	Compute new array values based on lookup table (LUT)
medfilt2	Perform 2-D median filtering
ordfilt2	Perform 2-D order-statistic filtering
stretchlim	Return a pair of intensities that can be used to increase the contrast of an image
wiener2	Perform 2-D adaptive noise-removal filtering

Image Restoration (Deblurring)

deconvblind	Restore image using blind deconvolution
deconvlucy	Restore image using accelerated Richardson-Lucy algorithm
deconvreg	Restore image using regularized filter
deconvwnr	Restore image using Wiener filter
edgetaper	Taper the discontinuities along the image edges
otf2psf	Convert optical transfer function to point spread function
psf2otf	Convert point spread function to optical transfer function

Linear Filtering and Transforms

- Linear Filtering (p. 15-11)
- Linear 2-D Filter Design (p. 15-11)
- Image Transforms (p. 15-11)

Linear Filtering

conv2 Perform 2-D convolution (MATLAB function)

convmtx2 Compute 2-D convolution matrix

convn Perform N-D convolution (MATLAB function)

filter2 Perform 2-D filtering (MATLAB function)

fspecial Create predefined filters

imfilter Multidimensional image filtering

Linear 2-D Filter Design

freqspace Determine 2-D frequency response spacing (MATLAB

function.)

freqz2 Compute 2-D frequency response

fsamp2 Design 2-D FIR filter using frequency sampling

ftrans2 Design 2-D FIR filter using frequency transformation

fwind1 Design 2-D FIR filter using 1-D window method

fwind2 Design 2-D FIR filter using 2-D window method

Image Transforms

dct2 Compute 2-D discrete cosine transform

dctmtx Compute discrete cosine transform matrix

fan2para Convert fan-beam projection data to parallel-beam

fanbeam Compute fan-beam transform

fft2 Compute 2-D fast Fourier transform (MATLAB function)

fftn	$Compute\ N-D\ fast\ Fourier\ transform\ (MATLAB\ function)$
fftshift	Reverse quadrants of output of FFT (MATLAB function)
idct2	Compute 2-D inverse discrete cosine transform
ifft2	Compute 2-D inverse fast Fourier transform (MATLAB function)
ifftn	Compute N-D inverse fast Fourier transform (MATLAB function)
ifanbeam	Compute inverse fan-beam transform
iradon	Compute inverse Radon transform
para2fan	Convert parallel-beam projections to fan-beam
phantom	Generate a head phantom image
radon	Compute Radon transform

Morphological Operations

- Intensity and Binary Images (p. 15-13)
- Binary Images (p. 15-14)
- Structuring Element (STREL) Creation and Manipulation (p. 15-15)

Intensity and Binary Images

conndef Default connectivity array
imbothat Perform bottom-hat filtering

imclearborder Suppress light structures connected to image border

imcloseClose imageimdilateDilate imageimerodeErode image

imextendedmax Find extended-maxima transform
imextendedmin Find extended-minima transform

imfill Fill image regions

imhmax Calculate H-maxima transform
Calculate H-minima transform

imimposemin Impose minima imopen Open image

imreconstruct Perform morphological reconstruction

imregionalmax Find regional maxima of image imregionalmin Find regional minima of image

imtophat Perform tophat filtering

watershed Find image watershed regions

Binary Images

applylut Perform neighborhood operations using lookup tables

bwarea Area of objects in binary image

bwareaopen Binary area open; remove small objects

bwdist Distance transform

bweuler Euler number of binary image **bwhitmiss** Binary hit-and-miss operation

bwlabel Label connected components in 2-D binary image bwlabeln Label connected components in N-D binary image bwmorph Perform morphological operations on binary image

bwpack Pack binary image

Find perimeter of objects in binary image bwperim

bwselect Select objects in binary image

bwulterode Ultimate erosion

Unpack a packed binary image bwunpack

imregionalmin Regional minima of image imtophat Perform tophat filtering

makelut Construct lookup table for use with applylut

Structuring Element (STREL) Creation and Manipulation

getheight Get the height of a structuring element

getneighbors Get structuring element neighbor locations and heights

getnhood Get structuring element neighborhood

getsequence Extract sequence of decomposed structuring elements

isflat Return true for flat structuring element

reflect Reflect structuring element

strel Create morphological structuring element

translate Translate structuring element

Region-Based, Neighborhood, and Block Processing

• Region-Based Processing (p. 15-15)

• Neighborhood and Block Processing (p. 15-16)

Region-Based Processing

poly2mask Convert region-of-interest polygon to mask

roicolor Select region of interest, based on color

roifill Smoothly interpolate within arbitrary region

roifilt2 Filter a region of interest

roipoly Select polygonal region of interest

Neighborhood and Block Processing

bestblk	Choose block size for block processing
blkproc	Implement distinct block processing for image
col2im	Rearrange matrix columns into blocks
colfilt	Perform neighborhood operations using columnwise functions
im2col	Rearrange image blocks into columns
nlfilter	Perform general sliding-neighborhood operations

Colormap and Color Space Functions

- Colormap Manipulation (p. 15-16)
- Color Space Conversions (p. 15-16)

Colormap Manipulation

brighten	Brighten or darken colormap (MATLAB function)
cmpermute	Rearrange colors in colormap
cmunique	Find unique colormap colors and corresponding image
colormap	Set or get color lookup table (MATLAB function)
imapprox	Approximate indexed image by one with fewer colors
rgbplot	Plot RGB colormap components (MATLAB function)

Color Space Conversions

applycform	Apply device-independent color space transformation
hsv2rgb	$Convert\ HSV\ values\ to\ RGB\ color\ space\ (MATLAB\ function)$
iccread	Read ICC color profile
iccwrite	Write ICC color profile
isicc	Determine if ICC color profile is valid
lab2double	Convert $L^*a^*b^*$ color values to double

lab2uint16 Convert L*a*b* color values to uint16 lab2uint8 Convert L*a*b* color values to uint8 makecform Create device-independent color space transform structure

ntsc2rgb Convert NTSC values to RGB color space

rgb2hsv Convert RGB values to HSV color space (MATLAB function)

rgb2ntsc Convert RGB values to NTSC color space
rgb2ycbcr Convert RGB values to YCbCr color space
whitepoint Returns XYZ values of standard illuminants

xyz2double Convert XYZ color values to double xyz2uint16 Convert XYZ color values to uint16

ycbcr2rgb Convert YCbCr values to RGB color space

Miscellaneous Functions

- Toolbox Preferences (p. 15-18)
- Interactive Mouse Utility Functions (p. 15-18)
- Array Operations (p. 15-19)
- Demos (p. 15-19)
- Performance (p. 15-19)

Toolbox Preferences

iptgetpref Get value of Image Processing Toolbox preference iptsetpref Set value of Image Processing Toolbox preference

Toolbox Utility Functions

getrangefromclass Get dynamic range of image based on its class

iptcheckconn Check validity of connectivity argument

iptcheckinput Check validity of array

iptcheckmap Check validity of colormap

iptchecknargin Check number of input arguments

iptcheckstrs Check validity of strings

iptnum2ordinal Convert positive integer to ordinal string

Interactive Mouse Utility Functions

getline Select polyline with mouse getpts Select points with mouse getrect Select rectangle with mouse

Array Operations

circshift Shift array circularly (MATLAB function)

padarray Pad an array

Demos

iptdemos Display index of Image Processing Toolbox demos

Performance

ippl Check for presence of Intel Performance Primitives

Library (IPPL)

Functions - Alphabetical List

This section contains detailed descriptions of all toolbox functions. Each function reference page contains some or all of this information:

- The function name
- The purpose of the function
- The function syntax

All valid input argument and output argument combinations are shown. In some cases, an ellipsis (...) is used for the input arguments. This means that all preceding input argument combinations are valid for the specified output argument(s).

- A description of each argument
- A description of the function
- Additional remarks about usage
- An example of usage
- Related functions

Perform contrast-limited adaptive histogram equalization (CLAHE)

Syntax

J = adapthisteq(I)

J = adapthisteq(I,param1,val1,param2,val2...)

Description

J = adapthisteq(I) enhances the contrast of the intensity image I by transforming the values using contrast-limited adaptive histogram equalization (CLAHE).

CLAHE operates on small regions in the image, called *tiles*, rather than the entire image. Each tile's contrast is enhanced, so that the histogram of the output region approximately matches the histogram specified by the 'Distribution' parameter. The neighboring tiles are then combined using bilinear interpolation to eliminate artificially induced boundaries. The contrast, especially in homogeneous areas, can be limited to avoid amplifying any noise that might be present in the image.

J = adapthisteq(I,param1,val1,param2,val2...) specifies any of the additional parameter/value pairs listed in the following table. Parameter names can be abbreviated, and case does not matter.

Parameter	Value
'NumTiles'	Two-element vector of positive integers specifying the number of tiles by row and column, [M N]. Both M and N must be at least 2. The total number of tiles is equal to M*N. Default: [8 8]
'ClipLimit'	Real scalar in the range [0 1] that specifies a contrast enhancement limit. Higher numbers result in more contrast. Default: 0.01

adapthisteq

Parameter	Value
'NBins'	Positive integer scalar specifying the number of bins for the histogram used in building a contrast enhancing transformation. Higher values result in greater dynamic range at the cost of slower processing speed.
I Dan and I	Default: 256
'Range'	String specifying the range of the output image data
	'original' — Range is limited to the range of the original image, [min(I(:)) max(I(:))].
	'full' — Full range of the output image class is used. For example, for uint8 data, range is [0 255]
	Default: 'full'
'Distribution'	String specifying the desired histogram shape for the image tiles.
	'uniform' — Flat histogram
	'rayleigh' — Bell-shaped histogram
	'exponential' — Curved histogram
	Default: 'uniform'
'Alpha'	Nonnegative real scalar specifying a distribution parameter.
	Default: 0.4
	Note : Only used when 'Distribution' is set to either 'rayleigh' or 'exponential'.

Class Support

Intensity image I can be of class uint8, uint16, int16, single, or double. The output image J has the same class as I.

Example

This example applies Contrast-Limited Adaptive Histogram Equalization (CLAHE) to an image and display the results.

```
I = imread('tire.tif');
  A = adapthisteq(I, 'clipLimit', 0.02, 'Distribution', 'rayleigh');
  figure, imshow(I);
  figure, imshow(A);
This example applies CLAHE to a color photograph.
  [X MAP] = imread('shadow.tif');
  % Convert indexed image to true-color (RGB) format
  RGB = ind2rgb(X,MAP);
  % Convert image to L*a*b* color space
  cform2lab = makecform('srgb2lab');
  LAB = applycform(RGB, cform2lab);
  % Scale values to range from 0 to 1
  L = LAB(:,:,1)/100;
  % Perform CLAHE
  LAB(:,:,1) = adapthisteq(L,'NumTiles',...
                            [8 8], 'ClipLimit', 0.005) *100;
  % Convert back to RGB color space
  cform2srgb = makecform('lab2srgb');
  J = applycform(LAB, cform2srgb);
  % Display the results
  figure, imshow(RGB);
  figure, imshow(J);
```

See Also histeq

applycform

Purpose

Apply color space transformation

Syntax

out = applycform(I,C)

Description

out = applycform(I,C) converts the color values in I to the color space specified in the color transformation structure C. The color transformation structure specifies various parameters of the transformation. See makecform for details.

If I is two-dimensional, each row is interpreted as a color. I typically has either three or four columns, depending on the input color space. out has the same number of rows and either three or four columns, depending on the output color space.

If I is three-dimensional, each row-column location is interpreted as a color, and size(I,3) is typically either three or four, depending on the input color space. out has the same number of rows and columns as I, and size(out,3) is either three or four, depending on the output color space.

Class Support

I must be a real, nonsparse, finite array of class uint8, uint16, or double. The output array out has the same class and size as the input array, unless the output color space is *XYZ*. If the input is *XYZ* data of class uint8, the output is of class uint16, because there is no standard 8-bit encoding defined for *XYZ* color values.

Example

Read in a color image that uses the RGB color space.

```
I = imread('peppers.png');
```

Create a color transformation structure that defines an RGB to XYZ conversion.

```
C = makecform('srgb2xyz');
```

Perform the transformation with applycform.

```
I_xyz = applycform(I,C);
```

See Also

 $lab2 double, \, lab2 uint 16, \, makec form, \, whitepoint, \, xyz2 double, \, xyz2 uint 16$

Perform neighborhood operations on binary images using lookup tables

Syntax

A = applylut(BW, LUT)

Description

A = applylut(BW,LUT) performs a 2-by-2 or 3-by-3 neighborhood operation on binary image BW by using a lookup table (LUT). LUT is either a 16-element or 512-element vector returned by makelut. The vector consists of the output values for all possible 2-by-2 or 3-by-3 neighborhoods.

Class Support

BW can be numeric or logical, and it must be real, two-dimensional, and nonsparse. LUT can be numeric or logical, and it must be a real vector with 16 or 512 elements. If all the elements of LUT are 0 or 1, then A is logical. If all the elements of LUT are integers between 0 and 255, then A is uint8. For all other cases, A is double.

Algorithm

applylut performs a neighborhood operation on a binary image by producing a matrix of indices into lut, and then replacing the indices with the actual values in lut. The specific algorithm used depends on whether you use 2-by-2 or 3-by-3 neighborhoods.

2-by-2 Neighborhoods

For 2-by-2 neighborhoods, length(lut) is 16. There are four pixels in each neighborhood, and two possible states for each pixel, so the total number of permutations is $2^4 = 16$.

To produce the matrix of indices, applylut convolves the binary image BW with this matrix.

841

The resulting convolution contains integer values in the range [0,15]. applylut uses the central part of the convolution, of the same size as BW, and adds 1 to each value to shift the range to [1,16]. It then constructs A by replacing the values in the cells of the index matrix with the values in lut that the indices point to.

3-by-3 Neighborhoods

For 3-by-3 neighborhoods, length(lut) is 512. There are nine pixels in each neighborhood, and two possible states for each pixel, so the total number of permutations is $2^9 = 512$.

To produce the matrix of indices, applylut convolves the binary image BW with this matrix.

```
256 32 4
128 16 2
64 8 1
```


The resulting convolution contains integer values in the range [0,511]. applylut uses the central part of the convolution, of the same size as BW, and adds 1 to each value to shift the range to [1,512]. It then constructs A by replacing the values in the cells of the index matrix with the values in 1ut that the indices point to.

Example

In this example, you perform erosion using a 2-by-2 neighborhood. An output pixel is on only if all four of the input pixel's neighborhood pixels are on.

```
lut = makelut('sum(x(:)) == 4',2);
BW = imread('text.png');
BW2 = applylut(BW,lut);
imshow(BW), figure, imshow(BW2)
```

```
the term watershed refers to a ridge areas drained by different river systems.
```



See Also

makelut

Interactive image contrast and brightness adjustment tool

Syntax

pixelx = axes2pix(DIM, XDATA, AXESX)

Description

pixelx = axes2pix(DIM, XDATA, AXESX) converts an axes coordinate into a pixel coordinate. For example if pt = get(gca, 'CurrentPoint') then AXESX could be pt(1,1) or pt(1,2). AXESX must be in pixel coordinates. XDATA is a two-element vector returned by get(image_handle, 'XData') or get(image_handle, 'YData'). DIM is the number of image columns for the x coordinate, or the number of image rows for the y coordinate.

Class Support

DIM, XDATA, and AXESX can be double. The output is double.

Note

axes2pix performs minimal checking on the validity of AXESX, DIM, or XDATA. For example, axes2pix returns a negative coordinate if AXESX is less than XDATA(1). The function calling axes2pix bears responsibility for error checking.

Examples

Example with default XData and YData.

```
h = imshow('pout.tif');
[nrows,ncols] = size(get(h,'CData'));
xdata = get(h,'XData')
ydata = get(h,'YData')
px = axes2pix(ncols,xdata,30)
py = axes2pix(nrows,ydata,30)
```

Example with non-default XData and YData.

```
xdata = [10 100]
ydata = [20 90]
px = axes2pix(ncols,xdata,30)
py = axes2pix(nrows,ydata,30)
```

See Also

impixelinfo, bwselect, imfill, impixel, improfile, pixval, roipoly

bestblk

Purpose

Determine block size for block processing

Syntax

```
siz = bestblk([m n],k)
[mb,nb] = bestblk([m n],k)
```

Description

siz = bestblk([m n],k) returns, for an m-by-n image, the optimal block size for block processing. k is a scalar specifying the maximum row and column dimensions for the block; if the argument is omitted, it defaults to 100. The return value siz is a 1-by-2 vector containing the row and column dimensions for the block.

[mb,nb] = bestblk([m n],k) returns the row and column dimensions for the block in mb and nb, respectively.

Algorithm

bestblk returns the optimal block size given m, n, and k. The algorithm for determining $\sin z$ is

- If m is less than or equal to k, return m.
- If m is greater than k, consider all values between min(m/10,k/2) and k. Return the value that minimizes the padding required.

The same algorithm is then repeated for n.

Example

```
siz = bestblk([640 800],72)
siz =
64 50
```

See Also

blkproc

Implement distinct block processing for an image

Syntax

```
B = blkproc(A,[m n],fun)
B = blkproc(A,[m n],[mborder nborder],fun,...)
B = blkproc(A,'indexed',...)
```

Description

B = blkproc(A, [m n], fun) processes the image A by applying the function fun to each distinct m-by-n block of A, padding A with 0's if necessary. fun is a function handle that accepts an m-by-n matrix, x, and returns a matrix, vector, or scalar y.

```
y = fun(x)
```

blkproc does not require that y be the same size as x. However, B is the same size as A only if y is the same size as x.

 $B = blkproc(A, [m n], [mborder nborder], fun) \ defines \ an overlapping \ border \ around the blocks. \ blkproc extends the original m-by-n blocks by mborder on the top and bottom, and nborder on the left and right, resulting in blocks of size (m+2*mborder)-by-(n+2*nborder). The blkproc function pads the border with 0's, if necessary, on the edges of A. The function fun should operate on the extended block.$

The line below processes an image matrix as 4-by-6 blocks, each having a row border of 2 and a column border of 3. Because each 4-by-6 block has this 2-by-3 border, fun actually operates on blocks of size 8-by-12.

```
B = blkproc(A, [4 6], [2 3], fun)
```

B = blkproc(A, 'indexed',...) processes A as an indexed image, padding with 0's if the class of A is uint8 or uint16, or 1's if the class of A is double.


Class Support

The input image A can be of any class supported by fun. The class of B depends on the class of the output from fun.

Example

This example uses blkproc to compute the 2-D DCT of each 8-by-8 block to the standard deviation of the elements in that block. In this example, fun is specified as a function handle created using @.

```
I = imread('cameraman.tif');
fun = @dct2;
J = blkproc(I,[8 8],fun);
imagesc(J), colormap(hot)
```



This example uses blkproc to set the pixels in each 16-by-16 block to the standard deviation of the elements in that block. In this example, fun is specified as an anonymous function.

```
I = imread('liftingbody.png');
fun = @(x) std2(x)*ones(size(x));
I2 = blkproc(I,[32 32],fun);
imshow(I), figure, imshow(I2,'DisplayRange',[])
```




Image Courtesy of NASA

See Also bestblk, colfilt, nlfilter, function_handle

brighten

Purpose

Brighten or darken a colormap

brighten is a MATLAB function. To get help for this function, select **MATLAB Help** from the Help menu and view the online function reference page.

Compute the area of the objects in a binary image

Syntax

total = bwarea(BW)

Description

total = bwarea(BW) estimates the area of the objects in binary image BW. total is a scalar whose value corresponds roughly to the total number of on pixels in the image, but might not be exactly the same because different patterns of pixels are weighted differently.

Class Support

BW can be numeric or logical. For numeric input, any nonzero pixels are considered to be on. The return value total is of class double.

Algorithm

bwarea estimates the area of all of the on pixels in an image by summing the areas of each pixel in the image. The area of an individual pixel is determined by looking at its 2-by-2 neighborhood. There are six different patterns, each representing a different area:

- Patterns with zero on pixels (area = 0)
- Patterns with one on pixel (area = 1/4)
- Patterns with two adjacent on pixels (area = 1/2)
- Patterns with two diagonal on pixels (area = 3/4)
- Patterns with three on pixels (area = 7/8)
- Patterns with all four on pixels (area = 1)


Keep in mind that each pixel is part of four different 2-by-2 neighborhoods. This means, for example, that a single on pixel surrounded by off pixels has a total area of 1.

Example

This example computes the area in the objects of a 256-by-256 binary image.

```
BW = imread('circles.png');
imshow(BW);
```

bwarea



bwarea(BW)

ans =

1.4187e+004

See Also

bweuler, bwperim

References

Pratt, William K., *Digital Image Processing*, New York, John Wiley & Sons, Inc., 1991, p. 634.

Binary area open; remove small objects

Syntax

BW2 = bwareaopen(BW,P)

BW2 = bwareaopen(BW,P,CONN)

Description

BW2 = bwareaopen(BW,P) removes from a binary image all connected components (objects) that have fewer than P pixels, producing another binary image, BW2. The default connectivity is 8 for two dimensions, 26 for three dimensions, and conndef(ndims(BW), 'maximal') for higher dimensions.

BW2 = bwareaopen(BW,P,CONN) specifies the desired connectivity. CONN can have any of the following scalar values.

Value	Meaning
Two-dimensional connectivities	
4	4-connected neighborhood
8	8-connected neighborhood
Three-dimensional connectivities	
6	6-connected neighborhood
18	18-connected neighborhood
26	26-connected neighborhood

Connectivity can be defined in a more general way for any dimension by using for CONN a 3-by-3-by-...-by-3 matrix of 0's and 1's. The 1-valued elements define neighborhood locations relative to the center element of CONN. Note that CONN must be symmetric about its center element.

Class Support

BW can be a logical or numeric array of any dimension, and it must be nonsparse. The return value BW2 is of class logical.

Algorithm

The basic steps are

1 Determine the connected components.

L = bwlabeln(BW, CONN);

bwareaopen

2 Compute the area of each component.

```
S = regionprops(L, 'Area');
```

3 Remove small objects.

```
bw2 = ismember(L, find([S.Area] >= P));
```

Example

Read in the image and display it.

```
originalBW = imread('text.png');
imshow(originalBW)
```

```
... divides areas drained by different river systems. ...
```

Remove all objects smaller than 50 pixels. Note the missing letters.

```
bwAreaOpenBW = bwareaopen(originalBW,50);
figure, imshow(bwAreaOpenBW)
```



See Also

bwlabel, bwlabeln, conndef, regionprops

Trace region boundaries in a binary image

Syntax

B = bwboundaries(BW)


B = bwboundaries(BW,CONN)

B = bwboundaries(BW,CONN,options)

[B L] = bwboundaries(...)
[B L N A] = bwboundaries()

Description

B = bwboundaries (BW) traces the exterior boundaries of objects, as well as boundaries of holes inside these objects, in the binary image BW. bwboundaries also descends into the outermost objects (parents) and traces their children (objects completely enclosed by the parents). BW must be a binary image where nonzero pixels belong to an object and 0 pixels constitute the background. The following figure illustrates these components.



bwboundaries returns B, a P-by-1 cell array, where P is the number of objects and holes. Each cell in the cell array contains a Q-by-2 matrix. Each row in the matrix contains the row and column coordinates of a boundary pixel. Q is the number of boundary pixels for the corresponding region.

bwboundaries

B = bwboundaries(BW,CONN) specifies the connectivity to use when tracing parent and child boundaries. CONN can have either of the following scalar values.

Value	Meaning
4	4-connected neighborhood
8	8-connected neighborhood. This is the default.

B = bwboundaries(BW,CONN,options) specifies an optional argument, where options can have either of the following values:

Value	Meaning
'holes'	Search for both object and hole boundaries. This is the default.
'noholes'	Search only for object (parent and child) boundaries. This can provide better performance.

[B,L] = bwboundaries(...) returns the label matrix L as the second output argument. Objects and holes are labeled. L is a two-dimensional array of nonnegative integers that represent contiguous regions. The kth region includes all elements in L that have value k. The number of objects and holes represented by L is equal to $\max(L(:))$. The zero-valued elements of L make up the background.

[B,L,N,A] = bwboundaries(...) returns N, the number of objects found, and A, an adjacency matrix. The first N cells in B are object boundaries. A represents the parent-child-hole dependencies. A is a square, sparse, logical matrix with side of length max(L(:)), whose rows and columns correspond to the positions of boundaries stored in B.

The boundaries enclosed by a $B\{m\}$ as well as the boundary enclosing $B\{m\}$ can both be found using A as follows:

```
enclosing_boundary = find(A(m,:));
enclosed_boundaries = find(A(:,m));
```

Class Support

BW can be logical or numeric and it must be real, 2-D, and nonsparse. L and N are double. A is sparse logical.

Example

Example 1

Read in and threshold an intensity image. Display the labeled objects using the jet colormap, on a gray background, with region boundaries outlined in white.

```
I = imread('rice.png');
BW = im2bw(I, graythresh(I));
[B,L] = bwboundaries(BW,'noholes');
imshow(label2rgb(L, @jet, [.5 .5 .5]))
hold on
for k = 1:length(B)
   boundary = B{k};
   plot(boundary(:,2), boundary(:,1), 'w', 'LineWidth', 2)
end
```

Example 2

Read in and display a binary image. Overlay the region boundaries on the image. Display text showing the region number (based on the label matrix) next to every boundary. Additionally, display the adjacency matrix using the MATLAB spy function.

After the image is displayed, use the zoom tool to read individual labels.

```
BW = imread('blobs.png');
[B,L,N,A] = bwboundaries(BW);
imshow(BW); hold on;
colors=['b' 'g' 'r' 'c' 'm' 'y'];
for k=1:length(B),
  boundary = B{k};
  cidx = mod(k,length(colors))+1;
  plot(boundary(:,2), boundary(:,1),
colors(cidx),'LineWidth',2);
  %randomize text position for better visibility
  rndRow = ceil(length(boundary)/(mod(rand*k,7)+1));
  col = boundary(rndRow,2); row = boundary(rndRow,1);
  h = text(col+1, row-1, num2str(L(row,col)));
  set(h,'Color',colors(cidx),'FontSize',14,'FontWeight','bold');
end
```

```
figure; spy(A);
```

Example 3

Display object boundaries in red and hole boundaries in green.

```
BW = imread('blobs.png');
[B,L,N] = bwboundaries(BW);
imshow(BW); hold on;
for k=1:length(B),
   boundary = B{k};
   if(k > N)
      plot(boundary(:,2), boundary(:,1), 'g','LineWidth',2);
   else
      plot(boundary(:,2), boundary(:,1), 'r','LineWidth',2);
   end
end
```

Example 4

Display parent boundaries in red (any empty row of the adjacency matrix belongs to a parent) and their holes in green.

```
BW = imread('blobs.png');
[B,L,N,A] = bwboundaries(BW);
imshow(BW); hold on;
for k=1:length(B),
   if(~sum(A(k,:)))
     boundary = B{k};
   plot(boundary(:,2), boundary(:,1), 'r','LineWidth',2);
   for l=find(A(:,k))'
     boundary = B{l};
     plot(boundary(:,2), boundary(:,1), 'g','LineWidth',2);
   end
  end
end
```

See Also

bwtraceboundary, bwlabel, bwlabeln

Distance transform

Syntax

D = bwdist(BW)

[D,L] = bwdist(BW)

[D,L] = bwdist(BW,METHOD)

Description

D = bwdist(BW) computes the Euclidean distance transform of the binary image BW. For each pixel in BW, the distance transform assigns a number that is the distance between that pixel and the nearest nonzero pixel of BW. bwdist uses the Euclidean distance metric by default. BW can have any dimension. D is the same size as BW.

[D,L] = bwdist(BW) also computes the nearest-neighbor transform and returns it as label matrix L, which has the same size as BW and D. Each element of L contains the linear index of the nearest nonzero pixel of BW.

[D,L] = bwdist(BW,METHOD) computes the distance transform, where METHOD specifies an alternate distance metric. METHOD can take any of these values:

'chessboard'	In 2-D, the chessboard distance between (x_1, y_1) and (x_2, y_2) is $\max(x_1 - x_2 , y_1 - y_2)$
'cityblock'	In 2-D, the cityblock distance between (x_1,y_1) and (x_2,y_2) is $ x_1-x_2 + y_1-y_2 $

'euclidean'	In 2-D, the Euclidean distance between (x_1,y_1) and (x_2,y_2) is $\sqrt{(x_1-x_2)^2+(y_1-y_2)^2}$ This is the default method.
'quasi-euclidean'	In 2-D, the quasi-Euclidean distance between $ (x_1,y_1) \text{ and } (x_2,y_2) \text{ is } \\ x_1-x_2 +(\sqrt{2}-1) y_1-y_2 , x_1-x_2 > y_1-y_2 \\ (\sqrt{2}-1) x_1-x_2 + y_1-y_2 , otherwise $

The METHOD string can be abbreviated.

Note bwdist uses fast algorithms to compute the true Euclidean distance transform, especially in the 2-D case. The other methods are provided primarily for pedagogical reasons. However, the alternative distance transforms are sometimes significantly faster for multidimensional input images, particularly those that have many nonzero elements.

Class Support

BW can be numeric or logical, and it must be nonsparse. D and L are double matrices with the same size as BW.

Example

Here is a simple example of the Euclidean distance transform.


[D,L] = bwdist(bw)

```
D =
    1.4142
               1.0000
                          1.4142
                                     2.2361
                                                 3.1623
    1.0000
                          1.0000
                                      2.0000
                                                 2.2361
    1.4142
               1.0000
                          1.4142
                                      1.0000
                                                 1.4142
    2.2361
               2.0000
                          1.0000
                                                 1.0000
                                           0
    3.1623
               2.2361
                          1.4142
                                      1.0000
                                                 1.4142
L =
     7
            7
                   7
                         7
                                7
     7
            7
                   7
                         7
                               19
     7
            7
                  7
                        19
                               19
     7
            7
                 19
                        19
                               19
     7
           19
                 19
                        19
                               19
```

In the nearest-neighbor matrix L the values 7 and 19 represent the position of the nonzero elements using linear matrix indexing. If a pixel contains a 7, its closest nonzero neighbor is at linear position 7.


This example compares the 2-D distance transforms for each of the supported distance methods. In the figure, note how the quasi-Euclidean distance transform best approximates the circular shape achieved by the Euclidean distance method.

```
bw = zeros(200,200); bw(50,50) = 1; bw(50,150) = 1;
bw(150,100) = 1;
D1 = bwdist(bw,'euclidean');
D2 = bwdist(bw,'cityblock');
D3 = bwdist(bw,'chessboard');
D4 = bwdist(bw,'quasi-euclidean');
figure
subplot(2,2,1), subimage(mat2gray(D1)), title('Euclidean')
hold on, imcontour(D1)
subplot(2,2,2), subimage(mat2gray(D2)), title('City block')
hold on, imcontour(D2)
subplot(2,2,3), subimage(mat2gray(D3)), title('Chessboard')
hold on, imcontour(D3)
subplot(2,2,4), subimage(mat2gray(D4)), title('Quasi-Euclidean')
hold on, imcontour(D4)
```



This example compares isosurface plots for the distance transforms of a 3-D image containing a single nonzero pixel in the center.

```
bw = zeros(50,50,50); bw(25,25,25) = 1;
D1 = bwdist(bw);
D2 = bwdist(bw,'cityblock');
D3 = bwdist(bw,'chessboard');
D4 = bwdist(bw,'quasi-euclidean');
figure
subplot(2,2,1), isosurface(D1,15), axis equal, view(3)
camlight, lighting gouraud, title('Euclidean')
subplot(2,2,2), isosurface(D2,15), axis equal, view(3)
camlight, lighting gouraud, title('City block')
subplot(2,2,3), isosurface(D3,15), axis equal, view(3)
camlight, lighting gouraud, title('Chessboard')
subplot(2,2,4), isosurface(D4,15), axis equal, view(3)
camlight, lighting gouraud, title('Quasi-Euclidean')
```



Algorithm

For two-dimensional Euclidean distance transforms, bwdist uses the second algorithm described in

Breu, Heinz, Joseph Gil, David Kirkpatrick, and Michael Werman, "Linear Time Euclidean Distance Transform Algorithms," *IEEE Transactions on Pattern Analysis and Machine Intelligence*, Vol. 17, No. 5, May 1995, pp. 529-533.

For higher dimensional Euclidean distance transforms, bwdist uses a nearest-neighbor search on an optimized kd-tree, as described in

Friedman, Jerome H., Jon Louis Bentley, and Raphael Ari Finkel, "An Algorithm for Finding Best Matches in Logarithmic Expected Time," *ACM Transactions on Mathematics Software*, Vol. 3, No. 3, September 1997, pp. 209-226.

For cityblock, chessboard, and quasi-Euclidean distance transforms, bwdist uses the two-pass, sequential scanning algorithm described in

Rosenfeld, A. and J. Pfaltz, "Sequential operations in digital picture processing," *Journal of the Association for Computing Machinery*, Vol. 13, No. 4, 1966, pp. 471-494.

bwdist

The different distance measures are achieved by using different sets of weights in the scans, as described in

Paglieroni, David, "Distance Transforms: Properties and Machine Vision Applications," *Computer Vision, Graphics, and Image Processing: Graphical Models and Image Processing*, Vol. 54, No. 1, January 1992, pp. 57-58.

See Also

watershed

Purpose Compute the Euler number of a binary image

Syntax eul = bweuler(BW,n)


Description eul = bweuler(BW,n) returns the Euler number for the binary image BW. The

return value eul is a scalar whose value is the total number of objects in the image minus the total number of holes in those objects. The argument n can have a value of either 4 or 8, where 4 specifies 4-connected objects and 8 specifies 8-connected objects; if the argument is omitted, it defaults to 8.

Class Support BW can be numeric or logical and it must be real, nonsparse, and

two-dimensional. The return value eul is of class double.

Example
BW = imread('circles.png');
imshow(BW);



bweuler(BW)

ans =

-3

Algorithm

bweuler computes the Euler number by considering patterns of convexity and concavity in local 2-by-2 neighborhoods. See [2] for a discussion of the algorithm used.

See Also bwmorph, bwperim

bweuler

References

- [1] Horn, Berthold P. K., $Robot\ Vision,$ New York, McGraw-Hill, 1986, pp. 73-77.
- [2] Pratt, William K., $Digital\ Image\ Processing$, New York, John Wiley & Sons, Inc., 1991, p. 633.

Binary hit-and-miss operation

Syntax

```
BW2 = bwhitmiss(BW1,SE1,SE2)
BW2 = bwhitmiss(BW1,INTERVAL)
```

Description

BW2 = bwhitmiss(BW1,SE1,SE2) performs the hit-and-miss operation defined by the structuring elements SE1 and SE2. The hit-and-miss operation preserves pixels whose neighborhoods match the shape of SE1 and don't match the shape of SE2. SE1 and SE2 can be flat structuring element objects, created by strel, or neighborhood arrays. The neighborhoods of SE1 and SE2 should not have any overlapping elements. The syntax bwhitmiss(BW1,SE1,SE2) is equivalent to imerode(BW1,SE1) & imerode(~BW1,SE2).

BW2 = bwhitmiss(BW1,INTERVAL) performs the hit-and-miss operation defined in terms of a single array, called an *interval*. An interval is an array whose elements can contain 1, 0, or -1. The 1-valued elements make up the domain of SE1, the -1-valued elements make up the domain of SE2, and the 0-valued elements are ignored. The syntax bwhitmiss(INTERVAL) is equivalent to bwhitmiss(BW1,INTERVAL == 1, INTERVAL == -1).

Class Support

BW1 can be a logical or numeric array of any dimension, and it must be nonsparse. BW2 is always a logical array with the same size as BW1. SE1 and SE2 must be flat STREL objects or they must be logical or numeric arrays containing 1's and 0's. INTERVAL must be an array containing 1's, 0's, and -1's.

Example

This example performs the hit-and-miss operation on a binary image using an interval.

bwhitmiss

bw2 = bwhitmiss(bw,interval)

bw2 =

0	0	0	0	0	0
0	0	0	1	0	0
0	0	0	0	1	0
0	0	0	0	0	0
0	0	0	0	0	0
0	0	0	0	0	0

See Also

imdilate, imerode, strel

Label connected components in a binary image

Syntax

L = bwlabel(BW,n)
[L,num] = bwlabel(BW,n)

Description

L = bwlabel(BW,n) returns a matrix L, of the same size as BW, containing labels for the connected objects in BW. n can have a value of either 4 or 8, where 4 specifies 4-connected objects and 8 specifies 8-connected objects; if the argument is omitted, it defaults to 8.

The elements of L are integer values greater than or equal to 0. The pixels labeled 0 are the background. The pixels labeled 1 make up one object, the pixels labeled 2 make up a second object, and so on.

[L,num] = bwlabel(BW,n) returns in num the number of connected objects found in BW.

Remarks

bwlabel supports 2-D inputs only; bwlabeln supports inputs of any dimension. In some cases, you might prefer to use bwlabeln even for 2-D problems because it can be faster. If you have a 2-D input whose objects are relatively thick in the vertical direction, bwlabel is probably faster; otherwise bwlabeln is probably faster.

Class Support

BW can be logical or numeric, and it must be real, 2-D, and nonsparse. L is of class double.

Remarks

You can use the MATLAB find function in conjunction with bwlabel to return vectors of indices for the pixels that make up a specific object. For example, to return the coordinates for the pixels in object 2,

```
[r,c] = find(bwlabel(BW)==2)
```

You can display the output matrix as a pseudocolor indexed image. Each object appears in a different color, so the objects are easier to distinguish than in the original image. See label2rgb for more information.

Example

This example illustrates using 4-connected objects. Notice objects 2 and 3; with 8-connected labeling, bwlabel would consider these a single object rather than two separate objects.

bwlabel

```
0
BW = [1]
                1
                        1
                                0
                                        0
                                                0
                                                        0
        1
                1
                        1
                                0
                                        1
                                                1
                                                         0
                                                                 0
                1
                        1
                                0
                                        1
                                                1
                                                         0
                                                                 0
        1
                1
                        1
                                0
                                                0
                                                         1
                                                                 0
                                        0
        1
                                                         1
                        1
                                0
                                        0
                                                0
                                                                 0
                                0
                                                0
                                                                 0
        1
                1
                        1
                                        0
                                                         1
        1
                1
                        1
                                0
                                        0
                                                1
                                                         1
                                                                 0
        1
                1
                        1
                                0
                                        0
                                                0
                                                        0
                                                                 0];
L = bwlabel(BW, 4)
L =
      1
              1
                       1
                               0
                                       0
                                               0
                                                       0
                                                               0
      1
               1
                                       2
                                               2
                                                               0
                       1
                               0
                                                       0
      1
               1
                       1
                               0
                                       2
                                               2
                                                       0
                                                               0
                                       0
                                               0
      1
               1
                       1
                               0
                                                       3
                                                               0
                                       0
                                               0
                                                       3
                                                               0
      1
               1
                       1
                               0
      1
               1
                       1
                               0
                                       0
                                               0
                                                       3
                                                               0
      1
               1
                       1
                               0
                                       0
                                               3
                                                       3
                                                               0
```

Algorithm

bwlabel uses the general procedure outlined in reference [1], pp. 40-48:

- 1 Run-length encode the input image.
- Scan the runs, assigning preliminary labels and recording label equivalences in a local equivalence table.
- 3 Resolve the equivalence classes.
- 4 Relabel the runs based on the resolved equivalence classes.

bwlabel

See Also bweuler, bwlabeln, bwselect, label2rgb

Reference [1] Haralick, Robert M., and Linda G. Shapiro, Computer and Robot Vision,

Volume I, Addison-Wesley, 1992, pp. 28-48.

bwlabeln

Purpose

Label connected components in N-D binary image

Syntax

L = bwlabeln(BW)

[L,NUM] = bwlabeln(BW)

[L,NUM] = bwlabeln(BW,CONN)

Description

L = bwlabeln(BW) returns a label matrix L containing labels for the connected components in BW. BW can have any dimension; L is the same size as BW. The elements of L are integer values greater than or equal to 0. The pixels labeled 0 are the background. The pixels labeled 1 make up one object, the pixels labeled 2 make up a second object, and so on. The default connectivity is 8 for two dimensions, 26 for three dimensions, and conndef(ndims(BW), 'maximal') for higher dimensions.

[L, NUM] = bwlabeln(BW) returns in NUM the number of connected objects found in BW.

[L,NUM] = bwlabeln(BW,CONN) specifies the desired connectivity. CONN can have any of the following scalar values.

Value	Meaning		
Two-dime	ensional connectivities		
4	4-connected neighborhood		
8	8-connected neighborhood		
Three-din	Three-dimensional connectivities		
6	6-connected neighborhood		
18	18-connected neighborhood		
26	26-connected neighborhood		

Connectivity can also be defined in a more general way for any dimension by using for CONN a 3-by-3-by-...-by-3 matrix of 0's and 1's. The 1-valued elements define neighborhood locations relative to the center element of CONN. Note that CONN must be symmetric about its center element.

Remarks

bwlabel supports 2-D inputs only; bwlabeln supports inputs of any dimension. In some cases, you might prefer to use bwlabeln even for 2-D problems because it can be faster. If you have a 2-D input whose objects are relatively thick in the vertical direction, bwlabel is probably faster; otherwise bwlabeln is probably faster.

Class Support

BW can be numeric or logical, and it must be real and nonsparse. \mbox{L} is of class double.

Example

```
BW = cat(3,[1 1 0; 0 0 0; 1 0 0],...
[0 1 0; 0 0 0; 0 1 0],...
[0 1 1; 0 0 0; 0 0 1])
bwlabeln(BW)
ans(:,:,1) =
     1
           1
                  0
     0
           0
                  0
     2
           0
                  0
ans(:,:,2) =
     0
                  0
           1
     0
           0
                  0
     0
ans(:,:,3) =
```

Algorithm

bwlabeln uses the following general procedure:

1

0

0

0

0

1 Scan all image pixels, assigning preliminary labels to nonzero pixels and recording label equivalences in a union-find table.

bwlabeln

- 2 Resolve the equivalence classes using the union-find algorithm [1].
- **3** Relabel the pixels based on the resolved equivalence classes.

See Also

bwlabel, label2rgb

Reference

[1] Sedgewick, Robert, $Algorithms\ in\ C, 3rd\ Ed.,$ Addison-Wesley, 1998, pp. 11-20.

Perform morphological operations on binary images

Syntax

BW2 = bwmorph(BW,operation)
BW2 = bwmorph(BW,operation,n)

Description

BW2 = bwmorph(BW, operation) applies a specific morphological operation to the binary image BW.

BW2 = bwmorph(BW,operation,n) applies the operation n times. n can be Inf, in which case the operation is repeated until the image no longer changes.

operation is a string that can have one of the values listed below.

Operation	Description
'bothat'	Performs the morphological "bottom hat" operation, which is closing (dilation followed by erosion) and subtracts the original image.
'bridge' Bridges unconnected pixels, that is, sets 0-valued pi to 1 if they have two nonzero neighbors that are not connected. For example:	
	1 0 0 1 1 0
	1 0 1 becomes 1 1 1 0 0 1 0 1 1
'clean'	Removes isolated pixels (individual 1's that are surrounded by 0's), such as the center pixel in this pattern.
	0 0 0 0 0 1 0
	0 0 0
'close'	Performs morphological closing (dilation followed by erosion).

bwmorph

Operation	Description		
'diag'	Uses diagonal fill to eliminate 8-connectivity of the background. For example:		
	0 1 0 0 1 0 1 0 0 becomes 1 1 0 0 0 0 0 0 0		
'dilate'	Performs dilation using the structuring element ones(3).		
'erode'	Performs erosion using the structuring element ones(3)		
'fill'	Fills isolated interior pixels (individual 0's that are surrounded by 1's), such as the center pixel in this pattern. 1		
'hbreak'	Removes H-connected pixels. For example:		
	0 1 0 becomes 0 0 0 1 1 1 1 1 1 1		
'majority'	Sets a pixel to 1 if five or more pixels in its 3-by-3 neighborhood are 1's; otherwise, it sets the pixel to 0.		
'open'	Peforms morphological opening (erosion followed by dilation).		
'remove'	Removes interior pixels. This option sets a pixel to 0 if all its 4-connected neighbors are 1, thus leaving only the boundary pixels on.		

Operation	Description	
'shrink'	With n = Inf, shrinks objects to points. It removes pixels so that objects without holes shrink to a point, and objects with holes shrink to a connected ring halfway between each hole and the outer boundary. This option preserves the Euler number	
'skel'	With n = Inf, removes pixels on the boundaries of objects but does not allow objects to break apart. The pixels remaining make up the image skeleton. This option preserves the Euler number.	
'spur'	Removes spur pixels. For example:	
	0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0	
'thicken'	With n = Inf, thickens objects by adding pixels to the exterior of objects until doing so would result in previously unconnected objects being 8-connected. This option preserves the Euler number.	
'thin'	With n = Inf, thins objects to lines. It removes pixels so that an object without holes shrinks to a minimally connected stroke, and an object with holes shrinks to a connected ring halfway between each hole and the outer boundary. This option preserves the Euler number	
'tophat'	Performs morphological "top hat" operation, returning the image minus the morphological opening of the image.	


Class Support

The input image BW can be numeric or logical. It must be 2-D, real and nonsparse. The output image BW2 is of class logical.


Example

```
BW = imread('circles.png');
imshow(BW);
```


bwmorph



BW2 = bwmorph(BW,'remove');
figure, imshow(BW2)



BW3 = bwmorph(BW,'skel',Inf);
figure, imshow(BW3)



See Also

bweuler, bwperim, imdilate, imerode

References

- [1] Haralick, Robert M., and Linda G. Shapiro, *Computer and Robot Vision, Volume I*, Addison-Wesley, 1992.
- [2] Pratt, William K., Digital Image Processing, John Wiley & Sons, Inc., 1991.
- [3] Lam, L., Seong-Whan Lee, and Ching Y. Suen, "Thinning Methodologies-A Comprehensive Survey," *IEEE Transactions on Pattern Analysis and Machine Intelligence*, Vol 14, No. 9, September 1992, page 879, bottom of first column through top of second column.

bwpack


Purpose Pack binary image

Syntax BWP = bwpack(BW)

Description

BWP = bwpack(BW) packs the uint8 binary image BW into the uint32 array BWP, which is known as a *packed binary image*. Because each 8-bit pixel value in the binary image has only two possible values, 1 and 0, bwpack can map each pixel to a single bit in the packed output image.

bwpack processes the image pixels by column, mapping groups of 32 pixels into the bits of a uint32 value. The first pixel in the first row corresponds to the least significant bit of the first uint32 element of the output array. The first pixel in the 32nd input row corresponds to the most significant bit of this same element. The first pixel of the 33rd row corresponds to the least significant bit of the second output element, and so on. If BW is M-by-N, then BWP is ceil(M/32)-by-N. This figure illustrates how bwpack maps the pixels in a binary image to the bits in a packed binary image.



Binary image packing is used to accelerate some binary morphological operations, such as dilation and erosion. If the input to imdilate or imerode is a packed binary image, the functions use a specialized routine to perform the operation faster.

bwunpack is used to unpack packed binary images.

Class Support

BW can be logical or numeric, and it must be 2-D, real, and nonsparse. BWP is of class uint32.

Example

Pack, dilate, and unpack a binary image:

```
BW = imread('text.png');
BWp = bwpack(BW);
BWp_dilated = imdilate(BWp,ones(3,3),'ispacked');
BW_dilated = bwunpack(BWp_dilated, size(BW,1));
```

See Also

bwunpack, imdilate, imerode

bwperim

Purpose

Find perimeter pixels in binary image

Syntax

```
BW2 = bwperim(BW1)
BW2 = bwperim(BW1,CONN)
```

Description

BW2 = bwperim(BW1) returns a binary image containing only the perimeter pixels of objects in the input image BW1. A pixel is part of the perimeter if it is nonzero and it is connected to at least one zero-valued pixel. The default connectivity is 4 for two dimensions, 6 for three dimensions, and conndef(ndims(BW), 'minimal') for higher dimensions.

BW2 = bwperim(BW1, CONN) specifies the desired connectivity. CONN can have any of the following scalar values.

Value	Meaning		
Two-dime	ensional connectivities		
4	4-connected neighborhood		
8	8-connected neighborhood		
Three-din	Three-dimensional connectivities		
6	6-connected neighborhood		
18	18-connected neighborhood		
26	26-connected neighborhood		

Connectivity can also be defined in a more general way for any dimension by using for CONN a 3-by-3-by-...-by-3 matrix of 0's and 1's. The 1-valued elements define neighborhood locations relative to the center element of CONN. Note that CONN must be symmetric about its center element.


Class Support


BW1 must be logical or numeric, and it must be nonsparse. BW2 is of class logical.

Example

```
BW1 = imread('circbw.tif');
BW2 = bwperim(BW1,8);
imshow(BW1)
```

figure, imshow(BW2)





See Also

bwarea, bweuler, conndef, imfill

bwselect

Purpose

Select objects in a binary image

Syntax

```
BW2 = bwselect(BW,c,r,n)
BW2 = bwselect(BW,n)
[BW2,idx] = bwselect(...)

BW2 = bwselect(x,y,BW,xi,yi,n)
[x,y,BW2,idx,xi,yi] = bwselect(...)
```

Description

BW2 = bwselect (BW, c, r, n) returns a binary image containing the objects that overlap the pixel (r, c). r and c can be scalars or equal-length vectors. If r and c are vectors, BW2 contains the sets of objects overlapping with any of the pixels (r(k), c(k)). n can have a value of either 4 or 8 (the default), where 4 specifies 4-connected objects and 8 specifies 8-connected objects. Objects are connected sets of on pixels (i.e., pixels having a value of 1).

BW2 = bwselect (BW,n) displays the image BW on the screen and lets you select the (r,c) coordinates using the mouse. If you omit BW, bwselect operates on the image in the current axes. Use normal button clicks to add points. Pressing **Backspace** or **Delete** removes the previously selected point. A shift-click, right-click, or double-click selects the final point; pressing **Return** finishes the selection without adding a point.

[BW2,idx] = bwselect(...) returns the linear indices of the pixels belonging to the selected objects.

BW2 = bwselect(x,y,BW,xi,yi,n) uses the vectors x and y to establish a nondefault spatial coordinate system for BW1. xi and yi are scalars or equal-length vectors that specify locations in this coordinate system.

[x,y,BW2,idx,xi,yi] = bwselect(...) returns the XData and YData in x and y, the output image in BW2, linear indices of all the pixels belonging to the selected objects in idx, and the specified spatial coordinates in xi and yi.

If bwselect is called with no output arguments, the resulting image is displayed in a new figure.


Class Support

The input image BW can be logical or numeric and must be 2-D and nonsparse. The output image BW2 is of class logical.

Example

```
BW1 = imread('text.png');
c = [43 185 212];
r = [38 68 181];
BW2 = bwselect(BW1,c,r,4);
imshow(BW1), figure, imshow(BW2)
```





See Also

bwlabel, imfill, impixel, roipoly, roifill

bwtraceboundary

Purpose

Trace object in a binary image

Syntax


B = bwtraceboundary(BW,P,fstep)

B = bwtraceboundary(BW,P,fstep,CONN)

B = bwtraceboundary(...,N,dir)

Description

B = bwtraceboundary(BW,P,fstep) traces the outline of an object in binary image bw. Nonzero pixels belong to an object and 0 pixels constitute the background. P is a two-element vector specifying the row and column coordinates of the point on the object boundary where you want the tracing to begin. fstep is a string specifying the initial search direction for the next object pixel connected to P. You use strings such as 'N' for north, 'NE' for northeast, to specify the direction. The following figure illustrates all the possible values for fstep.



bwtraceboundary returns B, a Q-by-2 matrix, where ${\bf Q}$ is the number of boundary pixels for the region. B holds the row and column coordinates of the boundary pixels.

B = bwtraceboundary(bw,P,fstep,CONN) specifies the connectivity to use when tracing the boundary. CONN can have either of the following scalar values.

Value	Meaning
4	4-connected neighborhood
	Note: With this connectivity, fstep is limited to the following values: 'N', 'E', 'S', and 'W'.
8	8-connected neighborhood. This is the default.

B = bwtraceboundary(...,N,dir) specifies n, the maximum number of boundary pixels to extract, and dir, the direction in which to trace the boundary. When N is set to Inf, the default value, the algorithm identifies all the pixels on the boundary. dir can have either of the following values:

Value	Meaning
'clockwise'	Search in a clockwise direction. This is the default.
'counterclockwise'	Search in counterclockwise direction.

Class Support

BW can be logical or numeric and it must be real, 2-D, and nonsparse. B, P, CONN, and N are of class double. dir and fstep are strings.

Example

Read in and display a binary image. Starting from the top left, project a beam across the image searching for the first nonzero pixel. Use the location of that pixel as the starting point for the boundary tracing. Including the starting point, extract 50 pixels of the boundary and overlay them on the image. Mark the starting points with a green x. Mark beams that missed their targets with a red x.

```
BW = imread('blobs.png');
imshow(BW,[]);
s=size(BW);
for row = 2:55:s(1)
    for col=1:s(2)
```

bwtraceboundary

See Also

bwboundaries

Ultimate erosion

Syntax

BW2 = bwulterode(BW)

BW2 = bwulterode(BW, METHOD, CONN)

Description

BW2 = bwulterode(BW) computes the ultimate erosion of the binary image BW. The ultimate erosion of BW consists of the regional maxima of the Euclidean distance transform of the complement of BW. The default connectivity for computing the regional maxima is 8 for two dimensions, 26 for three dimensions, and conndef(ndims(BW), 'maximal') for higher dimensions.

BW2 = bwulterode(BW, METHOD, CONN) specifies the distance transform method and the regional maxima connectivity. METHOD can be one of the strings 'euclidean', 'cityblock', 'chessboard', and 'quasi-euclidean'.

CONN can have any of the following scalar values.

Value	Meaning		
Two-dime	nsional connectivities		
4	4-connected neighborhood		
8	8-connected neighborhood		
Three-dim	Three-dimensional connectivities		
6	6-connected neighborhood		
18	18-connected neighborhood		
26	26-connected neighborhood		

Connectivity can be defined in a more general way for any dimension by using for CONN a 3-by-3-by... - by-3 matrix of 0's and 1's. The 1-valued elements define neighborhood locations relative to the center element of CONN. Note that CONN must be symmetric about its center element.

Class Support

BW can be numeric or logical and it must be nonsparse. It can have any dimension. The return value BW2 is always a logical array.

bwulterode

```
originalBW = imread('circles.png');
imshow(originalBW)
ultimateErosion = bwulterode(originalBW);
figure, imshow(ultimateErosion)
See Also
bwdist, conndef, imregionalmax
```

Unpack binary image

Syntax

BW = bwunpack(BWP,M)

Description

BW = bwunpack(BWP,M) unpacks the packed binary image BWP. BWP is a uint32 array. When it unpacks BWP, bwunpack maps the least significant bit of the first row of BWP to the first pixel in the first row of BW. The most significant bit of the first element of BWP maps to the first pixel in the 32nd row of BW, and so on. BW is M-by-N, where N is the number of columns of BWP. If M is omitted, its default value is 32*size(BWP,1).

Binary image packing is used to accelerate some binary morphological operations, such as dilation and erosion. If the input to imdilate or imerode is a packed binary image, the functions use a specialized routine to perform the operation faster.

bwpack is used to create packed binary images.

Class Support

BWP is of class uint32 and must be real, 2-D, and nonsparse. The return value BW is of class uint8.

Example

Pack, dilate, and unpack a binary image.

```
bw = imread('text.png');
bwp = bwpack(bw);
bwp_dilated = imdilate(bwp,ones(3,3),'ispacked');
bw dilated = bwunpack(bwp dilated, size(bw,1));
```

See Also

bwpack, imdilate, imerode

checkerboard

Purpose

Create checkerboard image

Syntax

I = checkerboard

I = checkerboard(N)

I = checkerboard(N,P,Q)

Description

I = checkerboard creates an 8-by-8 square checkerboard image that has four identifiable corners. Each square has 10 pixels per side. The light squares on the left half of the checkerboard are white. The light squares on the right half of the checkerboard are gray.

I = checkerboard(N) creates a checkerboard image where each square has N pixels per side.

I = checkerboard (N,P,Q) creates a rectangular checkerboard where P specifies the number of rows and Q specifies the number of columns. If you omit Q, it defaults to P and the checkerboard is square.

Each row and column is made up of tiles. Each tile contains four squares, N pixels per side, defined as

```
TILE = [DARK LIGHT; LIGHT DARK]
```




The light squares on the left half of the checkerboard are white. The light squares on the right half of the checkerboard are gray.

Example

Create a checkerboard where the side of every square is 20 pixels in length.

```
I = checkerboard(20);
imshow(I)
```



Create a rectangular checkerboard that is 2 tiles in height and 3 tiles wide.

```
J = checkerboard(10,2,3);
```

checkerboard

figure, imshow(J)



Create a black and white checkerboard.

K = (checkerboard > 0.5);
figure, imshow(K)



See Also

cp2tform, imtransform, maketform

cmpermute

Purpose

Rearrange the colors in a colormap

Syntax

```
[Y,newmap] = cmpermute(X,map)
[Y,newmap] = cmpermute(X,map,index)
```

Description

[Y,newmap] = cmpermute(X,map) randomly reorders the colors in map to produce a new colormap newmap. The cmpermute function also modifies the values in X to maintain correspondence between the indices and the colormap, and returns the result in Y. The image Y and associated colormap newmap produce the same image as X and map.

[Y,newmap] = cmpermute(X,map,index) uses an ordering matrix (such as the second output of sort) to define the order of colors in the new colormap.

Class Support

The input image X can be of class uint8 or double. Y is returned as an array of the same class as X.

Example

To arrange a colormap in order by luminance, use

```
ntsc = rgb2ntsc(map);
[dum,index] = sort(ntsc(:,1));
[Y,newmap] = cmpermute(X,map,index);
```

This example orders a colormap by luminance.

```
load trees
ntsc = rgb2ntsc(map);
[dum,index] = sort(ntsc(:,1));
[Y,newmap] = cmpermute(X,map,index);
figure, imshow(X,map)
figure, imshow(Y,newmap)
```

See Also

randperm, sort in the MATLAB Function Reference

Find unique colormap colors and the corresponding image

Syntax

```
[Y,newmap] = cmunique(X,map)
[Y,newmap] = cmunique(RGB)
[Y,newmap] = cmunique(I)
```

Description

[Y,newmap] = cmunique(X,map) returns the indexed image Y and associated colormap newmap that produce the same image as (X,map) but with the smallest possible colormap. The cmunique function removes duplicate rows from the colormap and adjusts the indices in the image matrix accordingly.

[Y,newmap] = cmunique(RGB) converts the true-color image RGB to the indexed image Y and its associated colormap newmap. The return value newmap is the smallest possible colormap for the image, containing one entry for each unique color in RGB. (Note that newmap might be very large, because the number of entries can be as many as the number of pixels in RGB.)

[Y,newmap] = cmunique(I) converts the intensity image I to an indexed image Y and its associated colormap newmap. The return value newmap is the smallest possible colormap for the image, containing one entry for each unique intensity level in I.

Class Support

The input image can be of class uint8, uint16, or double. The class of the output image Y is uint8 if the length of newmap is less than or equal to 256. If the length of newmap is greater than 256, Y is of class double.

Example

Use the magic function to create a sample 4-by-4 image that uses every value in the range between 1 and 16.

```
X = magic(4)
X =
    16
                    3
                          13
     5
           11
                   10
                           8
     9
            7
                    6
                          12
      4
           14
                   15
                           1
```

Concatenate two 8-entry grayscale colormaps created using the gray function. The resultant colormap, map, has 16 entries. Entries 9 through 16 are duplicates of entries 1 through 8.

```
map = [gray(8); gray(8)]
size(map)
ans =
    16    3
```

Use cmunique to eliminate duplicate entries in the colormap.

```
[Y, newmap] = cmunique(X, map);
size(newmap)
ans =
    8    3
```

cmunique adjusts the values in the original image X to index the new colormap.

View both images to verify that their appearance is the same.

```
imshow(X, map, 'InitialMagnification', 'fit')
figure, imshow(Y, newmap, 'InitialMagnification', 'fit')
```

See Also

gray2ind, rgb2ind

Rearrange matrix columns into blocks

Syntax

```
A = col2im(B,[m n],[mm nn], block_type)
A = col2im(B,[m n],[mm nn])
```

Description

col2im rearranges matrix columns into blocks. block_type is a string with one
of these values:

- 'distinct' for m-by-n distinct blocks
- 'sliding' for m-by-n sliding blocks (default)

A = col2im(B,[m n],[mm nn],'distinct') rearranges each column of B into a distinct m-by-n block to create the matrix A of size mm-by-nn. If B = [A11(:) A12(:) A21(:) A22(:)], where each column has length m*n, then A = [A11 A12;A21 A22] where each Aij is m-by-n.

A = col2im(B,[m n],[mm nn],'sliding') rearranges the row vector B into a matrix of size (mm-m+1)-by-(nn-n+1). B must be a vector of size 1-by-(mm-m+1)*(nn-n+1). B is usually the result of processing the output of im2col(...,'sliding') using a column compression function (such as sum).

A = col2im(B,[m n],[mm nn]) uses the default block type of 'sliding'.

Class Support

B can be logical or numeric. The return value A is of the same class as B.

See Also

blkproc, colfilt, im2col, nlfilter

Perform neighborhood operations using columnwise functions

Syntax

B = colfilt(A,[m n],block_type,fun)

B = colfilt(A,[m n],[mblock nblock],block_type,fun)

B = colfilt(A, 'indexed',...)

Description

colfilt processes distinct or sliding blocks as columns. colfilt can perform operations similar to blkproc and nlfilter, but often executes much faster.

B = colfilt(A, [m n], block_type, fun) processes the image A by rearranging each m-by-n block of A into a column of a temporary matrix, and then applying the function fun to this matrix. fun must be a function handle. colfilt zero-pads A, if necessary.

Before calling fun, colfilt calls im2col to create the temporary matrix. After calling fun, colfilt rearranges the columns of the matrix back into m-by-n blocks using col2im.

block type is a string that can have one of the values listed in this table.

Value	Description
'distinct'	Rearranges each m-by-n distinct block of A into a column in a temporary matrix, and then applies the function fun to this matrix. fun must return a matrix the same size as the temporary matrix. colfilt then rearranges the columns of the matrix returned by fun into m-by-n distinct blocks.
'sliding'	Rearranges each m-by-n sliding neighborhood of A into a column in a temporary matrix, and then applies the function fun to this matrix. fun must return a row vector containing a single value for each column in the temporary matrix. (Column compression functions such as sum return the appropriate type of output.) colfilt then rearranges the vector returned by fun into a matrix the same size as A.

B = colfilt(A,[m n],[mblock nblock],block_type,fun) processes the matrix A as above, but in blocks of size mblock-by-nblock to save memory. Note that using the [mblock nblock] argument does not change the result of the operation.

B = colfilt(A, 'indexed',...) processes A as an indexed image, padding with 0's if the class of A is uint8 or uint16, or 1's if the class of A is double or single.

Note To save memory, the colfilt function might divide A into subimages and process one subimage at a time. This implies that fun may be called multiple times, and that the first argument to fun may have a different number of columns each time.

Class Support

The input image A can be of any class supported by fun. The class of B depends on the class of the output from fun.

Example

This example sets each output pixel to the mean value of the input pixel's 5-by-5 neighborhood.

```
I = imread('tire.tif');
imshow(I)
I2 = uint8(colfilt(I,[5 5],'sliding',@mean));
figure, imshow(I2)
```

See Also

blkproc, col2im, function_handle, im2col, nlfilter

colorbar

Purpose

Display a color bar

colorbar is a MATLAB function. To get help for this function, select **MATLAB Help** from the Help menu and view the online function reference page.

Create connectivity array

Syntax

CONN = conndef(NUM DIMS, TYPE)

Description

CONN = conndef(NUM_DIMS, TYPE) returns the connectivity array defined by TYPE for NUM_DIMS dimensions. TYPE can have either of the values listed in this table.

Value	Description
'minimal'	Defines a neighborhood whose neighbors are touching the central element on an (N-1)-dimensional surface, for the N-dimensional case.
'maximal'	Defines a neighborhood including neighbors that touch the central element in any way; it is ones(repmat(3,1,NUM_DIMS)).

Several Image Processing Toolbox functions use conndef to create the default connectivity input argument.

Examples

The minimal connectivity array for two dimensions includes the neighbors touching the central element along a line.

The minimal connectivity array for three dimensions includes all the neighbors touching the central element along a face.

conndef

The maximal connectivity array for two dimensions includes all the neighbors touching the central element in any way.

```
conn2 = conndef(2, 'maximal')
conn2 =
    1     1     1
    1     1     1
    1     1     1
```

Perform two-dimensional convolution

conv2 is a function in MATLAB. To get help for this function, select **MATLAB Help** from the Help menu and view the online function reference page.

convmtx2

Purpose Compute two-dimensional convolution matrix

Syntax T = convmtx2(H,m,n)

T = convmtx2(H,[m n])

Description T = convmtx2(H,m,n) or T = convmtx2(H,[m n]) returns the

convolution matrix T for the matrix H. If X is an m-by-n matrix, then $reshape(T*X(:),size(H)+[m\ n]-1)$ is the same as conv2(X,H).

Class Support The inputs are all of class double. The output matrix T is of class sparse. The

number of nonzero elements in T is no larger than prod(size(H))*m*n.

See Also conv2

convmtx in the Signal Processing Toolbox User's Guide documentation

Purpose Perform N-dimensional convolution

convn is a MATLAB function. To get help for this function, select **MATLAB Help** from the Help menu and view the online function reference page.

corr2

Purpose Compute the two-dimensional correlation coefficient between two matrices

Syntax r = corr2(A,B)

Description r = corr2(A,B) computes the correlation coefficient between A and B, where A

and B are matrices or vectors of the same size.

Class Support A and B can be numeric or logical. The return value r is a scalar double.

Algorithm corr2 computes the correlation coefficient using

$$r = \frac{\displaystyle\sum_{m} \sum_{n} (A_{mn} - \overline{A})(B_{mn} - \overline{B})}{\sqrt{\left(\displaystyle\sum_{m} \sum_{n} (A_{mn} - \overline{A})^{2}\right) \left(\displaystyle\sum_{m} \sum_{n} (B_{mn} - \overline{B})^{2}\right)}}$$

where \overline{A} = mean2(A), and \overline{B} = mean2(B).

See Also std2

corrcoef in the MATLAB Function Reference

Infer geometric transformation from control point pairs

Syntax

Description

TFORM = cp2tform(input_points,base_points,transformtype) takes pairs of control points and uses them to infer a spatial transformation. input_points is an m-by-2 double matrix containing the x- and y-coordinates

of control points is an m-by-2 double matrix containing the x- and y-coordinates of control points in the image you want to transform. base_points is an m-by-2 double matrix containing the x- and y-coordinates of control points specified in the base image. The function returns a TFORM structure containing the spatial transformation.

TFORM = cp2tform(CPSTRUCT, transformtype) takes pairs of control points and uses them to infer a spatial transformation. CPSTRUCT is a structure that contains the control point matrices for the input and base images. You use the Control Point Selection Tool to create the CPSTRUCT.

transformtype specifies the type of spatial transformation to infer. This table lists all the transformation types supported by cp2tform in order of complexity.

cp2tform

The 'lwm' and 'polynomial' transform types can each take an optional, additional parameter. See the syntax descriptions that follow for details.

Transformation Type	Description	Minimum Control Points	Example
'linear conformal'	Use this transformation when shapes in the input image are unchanged, but the image is distorted by some combination of translation, rotation, and scaling. Straight lines remain straight, and parallel lines are still parallel.	2 pairs	₩ •₩•
'affine'	Use this transformation when shapes in the input image exhibit shearing. Straight lines remain straight, and parallel lines remain parallel, but rectangles become parallelograms.	3 pairs	**************************************
'projective'	Use this transformation when the scene appears tilted. Straight lines remain straight, but parallel lines converge toward vanishing points that might or might not fall within the image.	4 pairs	
'polynomial'	Use this transformation when objects in the image are curved. The higher the order of the polynomial, the better the fit, but the result can contain more curves than the base image.	6 pairs (order 2) 10 pairs (order 3) 16 pairs (order 4)	38 3 2

Transformation Type	Description	Minimum Control Points	Example
'piecewise linear'	Use this transformation when parts of the image appear distorted differently.	4 pairs	8.88
'lwm'	Use this transformation (local weighted mean), when the distortion varies locally and piecewise linear is not sufficient.	6 pairs (12 pairs recommended)	88

Note When transformtype is 'linear conformal', 'affine', 'projective', or 'polynomial', and input_points and base_points (or CPSTRUCT) have the minimum number of control points needed for a particular transformation, cp2tform finds the coefficients exactly. If input_points and base_points include more than the minimum number of points, cp2tform uses a least squares solution. For more information, see mldivide.

TFORM = cp2tform(input_points,base_points,'polynomial',order) returns a TFORM structure specifying a 'polynomial' transformation, where order specifies the order of the polynomial to use. order can be the scalar value 2, 3, or 4. If you omit order, it defaults to 3.

TFORM = cp2tform(CPSTRUCT, 'polynomial', order) same as the previous syntax except that the control points are specified in a CPSTRUCT.

TFORM = cp2tform(input_points,base_points,'lwm',N) returns a TFORM structure specifying a 'lwm' transformation, where N specifies the number of points used to infer each polynomial. The radius of influence extends out to the furthest control point used to infer that polynomial. The N closest points are used to infer a polynomial of order 2 for each control point pair. If you omit N, it defaults to 12. N can be as small as 6, but making N small risks generating ill-conditioned polynomials.

TFORM = cp2tform(CPSTRUCT, 'lwm', N) same as the previous syntax except that the control points are specified in a CPSTRUCT.

[TFORM,input_points,base_points] = cp2tform(CPSTRUCT,...) returns the control points that were actually used in the return values input_points and base_points. Unmatched and predicted points are not used. For more information, see cpstruct2pairs.

[TFORM,input_points,base_points,input_points_bad,base_points_bad]= cp2tform(input_points,base_points,'piecewise linear') returns a
TFORM structure specifying a 'piecewise linear' transformation. Returns the control points that were actually used in input_points and base_points, and returns the control points that were eliminated because they were middle vertices of degenerate fold-over triangles, in input_points_bad and base points bad.

[TFORM,input_points,base_points,input_points_bad,base_points_bad] = cp2tform(CPSTRUCT,'piecewise linear') same as the previous syntax except that the control points are specified in a CPSTRUCT.

Algorithms

cp2tform uses the following general procedure:

- 1 Use valid pairs of control points to infer a spatial transformation or an inverse mapping from output space (x,y) to input space (u,v) according to transformtype.
- **2** Return TFORM structure containing spatial transformation.

The procedure varies depending on the transformtype.

Linear Conformal

Linear conformal transformations can include a rotation, a scaling, and a translation. Shapes and angles are preserved. Parallel lines remain parallel. Straight lines remain straight.

Let

```
sc = scale*cos(angle)
ss = scale*sin(angle)

[u v] = [x y 1] * [ sc -ss
```

```
ss sc
tx ty]
```

Solve for sc, ss, tx, ty.

```
t lc = cp2tform(input points,base points,'linear conformal');
```

The coefficients of the inverse mapping are stored in t_lc.tdata.Tinv.

Since linear conformal transformations are a subset of affine transformations, t_lc.forward_fcn is @affine_fwd and t_lc.inverse_fcn is @affine_inv.

At least two control-point pairs are needed to solve for the four unknown coefficients.

Affine

In an affine transformation, the x and y dimensions can be scaled or sheared independently and there can be a translation. Parallel lines remain parallel. Straight lines remain straight. Linear conformal transformations are a subset of affine transformations.

For an affine transformation,

```
[u v] = [x y 1] * Tinv
```

Tinv is a 3-by-2 matrix. Solve for the six elements of Tinv.

```
t_affine = cp2tform(input_points,base_points,'affine');
```

The coefficients of the inverse mapping are stored in t affine.tdata.Tinv.

At least three control-point pairs are needed to solve for the six unknown coefficients.

Projective

In a projective transformation, quadrilaterals map to quadrilaterals. Straight lines remain straight. Affine transformations are a subset of projective transformations.

For a projective transformation

```
[up vp wp] = [x y w] * Tinv
```

where

cp2tform

```
u = up/wp
v = vp/wp
```

Tinv is a 3-by-3 matrix.

Assuming

Solve for the nine elements of Tinv.

```
t_proj = cp2tform(input_points,base_points,'projective');
```

The coefficients of the inverse mapping are stored in t_proj.tdata.Tinv.

At least four control-point pairs are needed to solve for the nine unknown coefficients.

Polynomial

In a polynomial transformation, polynomial functions of x and y determine the mapping.

Second-Order Polynomials

For a second-order polynomial transformation,

```
[u \ v] = [1 \ x \ y \ x^y \ x^2 \ y^2] * Tinv
```

Both u and v are second-order polynomials of x and y. Each second-order polynomial has six terms. To specify all coefficients, Tinv has size 6-by-2.

```
t poly ord2 = cp2tform(input points, base points, 'polynomial');
```

The coefficients of the inverse mapping are stored in t poly ord2.tdata.

At least six control-point pairs are needed to solve for the 12 unknown coefficients.

Third-Order Polynomials

For a third-order polynomial transformation:

```
[u \ v] = [1 \ x \ y \ x^y \ x^2 \ y^2 \ y^x^2 \ x^y^2 \ x^3 \ y^3] * Tinv
```

Both u and v are third-order polynomials of x and y. Each third-order polynomial has ten terms. To specify all coefficients, Tinv has size 10-by-2.

```
t poly ord3 = cp2tform(input points, base points, 'polynomial',3);
```

The coefficients of the inverse mapping are stored in t poly ord3.tdata.

At least ten control-point pairs are needed to solve for the 20 unknown coefficients.

Fourth-Order Polynomials

For a fourth-order polynomial transformation:

```
[u v] = [1 x y x*y x^2 y^2 y*x^2 x*y^2 x^3 y^3 x^3*y x^2*y^2 x*y^3 x^4 y^4] * Tinv Both u and v are fourth-order polynomials of x and y. Each fourth-order polynomial has 15 terms. To specify all coefficients, Tinv has size 15-by-2.
```

```
t poly ord4 = cp2tform(input points, base points, 'polynomial',4);
```

The coefficients of the inverse mapping are stored in t poly ord4.tdata.

At least 15 control-point pairs are needed to solve for the 30 unknown coefficients.

Piecewise Linear

In a piecewise linear transformation, linear (affine) transformations are applied separately to each triangular region of the image [1].

- 1 Find a Delaunay triangulation of the base control points.
- **2** Using the three vertices of each triangle, infer an affine mapping from base to input coordinates.

Note At least four control-point pairs are needed. Four pairs result in two triangles with distinct mappings.

Local Weighted Mean

For each control point in base_points:

- 1 Find the N closest control points.
- 2 Use these N points and their corresponding points in input_points to infer a second-order polynomial.
- 3 Calculate the radius of influence of this polynomial as the distance from the center control point to the farthest point used to infer the polynomial (using base points). [2]

Note At least six control-point pairs are needed to solve for the second-order polynomial. Ill-conditioned polynomials might result if too few pairs are used.

Example

```
I = checkerboard;
J = imrotate(I,30);
base_points = [11 11; 41 71];
input_points = [14 44; 70 81];
cpselect(J,I,input_points,base_points);

t = cp2tform(input_points,base_points,'linear conformal');

To recover angle and scale,

ss = t.tdata.Tinv(2,1); % ss = scale * sin(angle)
sc = t.tdata.Tinv(1,1); % sc = scale * cos(angle)
angle = atan2(ss,sc)*180/pi
scale = sqrt(ss*ss + sc*sc)
```

See Also

cpcorr, cpselect, cpstruct2pairs, imtransform

References

- [1] Goshtasby, Ardeshir, "Piecewise linear mapping functions for image registration," *Pattern Recognition*, Vol. 19, 1986, pp. 459-466.
- [2] Goshtasby, Ardeshir, "Image registration by local approximation methods," *Image and Vision Computing*, Vol. 6, 1988, pp. 255-261.

Tune control-point locations using cross correlation

Syntax

input_points = cpcorr(input_points_in,base_points_in,input,base)

Description

input_points = cpcorr(input_points_in,base_points_in,input,base)
uses normalized cross-correlation to adjust each pair of control points specified
in input points in and base points in.

input_points_in must be an M-by-2 double matrix containing the coordinates of control points in the input image. base_points_in is an M-by-2 double matrix containing the coordinates of control points in the base image.

cpcorr returns the adjusted control points in input_points, a double matrix the same size as input_points_in. If cpcorr cannot correlate a pair of control points, input_points contains the same coordinates as input_points_in for that pair.

cpcorr only moves the position of a control point by up to four pixels. Adjusted coordinates are accurate to one-tenth of a pixel. cpcorr is designed to get subpixel accuracy from the image content and coarse control-point selection.

Note input and base images must have the same scale for cpcorr to be effective.

cpcorr cannot adjust a point if any of the following occur:

- Points are too near the edge of either image.
- Regions of images around points contain Inf or NaN.
- Region around a point in input image has zero standard deviation.
- Regions of images around points are poorly correlated.

Class Support

The images input and base can be numeric and must contain finite values. The control-point pairs are of class double.

Algorithm

 ${\tt cpcorr}$ uses the following general procedure.

For each control-point pair,

- 1 Extract an 11-by-11 template around the input control point and a 21-by-21 region around the base control point.
- **2** Calculate the normalized cross-correlation of the template with the region.
- **3** Find the absolute peak of the cross-correlation matrix.
- **4** Use the position of the peak to adjust the coordinates of the input control point.

Example

This example uses cpcorr to fine-tune control points selected in an image. Note the difference in the values of the input_points matrix and the input points adj matrix.

See Also

cp2tform, cpselect, imtransform, normxcorr2

cpselect

Purpose

Control Point Selection Tool

Syntax

```
cpselect(input,base)
```

cpselect(input,base,CPSTRUCT IN)

cpselect(input,base,xyinput_in,xybase_in)

H = cpselect(input,base,...)

Description

cpselect (input, base) starts the Control Point Selection Tool, a graphical user interface that enables you to select control points in two related images. input is the image that needs to be warped to bring it into the coordinate system of the base image. input and base can be either variables that contain images or strings that identify files containing grayscale images. The Control Point Selection Tool returns the control points in a CPSTRUCT structure. (For more information, see "Using the Control Point Selection Tool" in Chapter 6.)

cpselect(input,base,CPSTRUCT_IN) starts cpselect with an initial set of control points that are stored in CPSTRUCT_IN. This syntax allows you to restart cpselect with the state of control points previously saved in CPSTRUCT_IN.

cpselect(input,base,xyinput_in,xybase_in) starts cpselect with a set of initial pairs of control points. xyinput_in and xybase_in are *m*-by-2 matrices that store the input and base coordinates, respectively.

H = cpselect(input,base,...) returns a handle H to the tool. You can use the close(H) or H.close syntax to close the tool from the command line.

Class Support

The input images can be of class uint8, uint16, double, or logical.

Algorithm

cpselect uses the following general procedure for control-point prediction.

- **1** Find all valid pairs of control points.
- **2** Infer a spatial transformation between input and base control points using method that depends on the number of valid pairs, as follows:

2 pairs Linear conformal

3 pairs Affine

4 or more pairs Projective

- **3** Apply spatial transformation to the new point to generate the predicted point.
- **4** Display predicted point.

Notes

Platform Support

cpselect requires Java and is not available on any platform that does not support Java. In addition, cpselect is not available on the Macintosh systems even with Java.

Memory Usage

To increase the amount of memory available to cpselect, you must put a file called 'java.opts' in your start-up directory.

Example

Start tool with saved images.

```
aerial = imread('westconcordaerial.png');
cpselect(aerial(:,:,1),'westconcordorthophoto.png')
```

Start tool with workspace images and points.

```
I = checkerboard;
J = imrotate(I,30);
base_points = [11 11; 41 71];
input_points = [14 44; 70 81];
cpselect(J,I,input_points,base_points);
```

See Also

cpcorr, cp2tform, cpstruct2pairs, imtransform

cpstruct2pairs

Purpose Convert CPSTRUCT to valid pairs of control points

Syntax [input points, base points] = cpstruct2pairs(CPSTRUCT)

Description [input points, base points] = cpstruct2pairs(CPSTRUCT) takes a

CPSTRUCT (produced by cpselect) and returns the arrays of coordinates of valid control point pairs in input points and base points. cpstruct2pairs

eliminates unmatched points and predicted points.

Example Start the Control Point Selection Tool, cpselect, with saved images.

```
aerial = imread('westconcordaerial.png');
cpselect(aerial(:,:,1),'westconcordorthophoto.png')
```

Using cpselect, pick control points in the images. Select **Save to Workspace** from the **File** menu to save the points to the workspace. On the **Save** dialog box, check the **Structure with all points** check box and clear **Input points of valid pairs** and **Base points of valid pairs**. Click **OK**. Use cpstruct2pairs to extract the input and base points from the CPSTRUCT.

```
[input points,base points] = cpstruct2pairs(cpstruct);
```

See Also

cp2tform, cpselect, imtransform

Compute two-dimensional discrete cosine transform

Syntax

B = dct2(A) B = dct2(A,m,n) B = dct2(A,[m n])

Description

B = dct2(A) returns the two-dimensional discrete cosine transform of A. The matrix B is the same size as A and contains the discrete cosine transform coefficients $B(k_1,k_2)$.

B = dct2(A,m,n) or B = dct2(A,[m n]) pads the matrix A with 0's to size m-by-n before transforming. If m or n is smaller than the corresponding dimension of A, dct2 truncates A.

Class Support

A can be numeric or logical. The returned matrix B is of class double.

Algorithm

The discrete cosine transform (DCT) is closely related to the discrete Fourier transform. It is a separable linear transformation; that is, the two-dimensional transform is equivalent to a one-dimensional DCT performed along a single dimension followed by a one-dimensional DCT in the other dimension. The definition of the two-dimensional DCT for an input image A and output image B is

$$B_{pq} = \alpha_p \alpha_q \sum_{m=0}^{M-1} \sum_{n=0}^{N-1} A_{mn} \cos \frac{\pi (2m+1)p}{2M} \cos \frac{\pi (2n+1)q}{2N}, \quad 0 \le p \le M-1$$

$$\alpha_p = \begin{cases} 1/\sqrt{M}, & p=0 \\ \sqrt{2/M}, & 1 \leq p \leq M-1 \end{cases} \qquad \alpha_q = \begin{cases} 1/\sqrt{N}, & q=0 \\ \sqrt{2/N}, & 1 \leq q \leq N-1 \end{cases}$$


where M and N are the row and column size of A, respectively. If you apply the DCT to real data, the result is also real. The DCT tends to concentrate information, making it useful for image compression applications.

This transform can be inverted using idct2.

Example

The commands below compute the discrete cosine transform for the autumn image. Notice that most of the energy is in the upper left corner.

```
RGB = imread('autumn.tif');
I = rgb2gray(RGB);
J = dct2(I);
imshow(log(abs(J)),[]), colormap(jet(64)), colorbar
```



Now set values less than magnitude 10 in the DCT matrix to zero, and then reconstruct the image using the inverse DCT function idct2.

```
J(abs(J) < 10) = 0;
K = idct2(J);
imshow(I)
figure, imshow(K,[0 255])</pre>
```



See Also

fft2, idct2, ifft2

References

[1] Jain, Anil K., Fundamentals of Digital Image Processing, Englewood Cliffs, NJ, Prentice Hall, 1989, pp. 150-153.

[2] Pennebaker, William B., and Joan L. Mitchell, *JPEG: Still Image Data Compression Standard*, Van Nostrand Reinhold, 1993.

dctmtx

Purpose

Compute discrete cosine transform matrix

Syntax

D = dctmtx(n)

Description

D = dctmtx(n) returns the n-by-n DCT (discrete cosine transform) matrix. D*A is the DCT of the columns of A and D'*A is the inverse DCT of the columns of A (when A is n-by-n).

Class Support

n is an integer scalar of class double. D is returned as a matrix of class double.

Remarks

If A is square, the two-dimensional DCT of A can be computed as D*A*D'. This computation is sometimes faster than using dct2, especially if you are computing a large number of small DCTs, because D needs to be determined only once.

For example, in JPEG compression, the DCT of each 8-by-8 block is computed. To perform this computation, use dctmtx to determine D, and then calculate each DCT using D*A*D' (where A is each 8-by-8 block). This is faster than calling dct2 for each individual block.

Example

```
A = im2double(imread('rice.png'));
D = dctmtx(size(A,1));
dct = D*A*D';
figure, imshow(dct)
```

See Also

dct2

Restore image using the blind deconvolution algorithm

Syntax

```
[J,PSF] = deconvblind(I,INITPSF)
```

[J,PSF] = deconvblind(I,INITPSF,NUMIT)

[J,PSF] = deconvblind(I,INITPSF,NUMIT,DAMPAR)

[J,PSF] = deconvblind(I,INITPSF,NUMIT,DAMPAR,WEIGHT)

[J,PSF] = deconvblind(I,INITPSF,NUMIT,DAMPAR,WEIGHT,READOUT)

[J,PSF] = deconvblind(...,FUN)

Description

[J,PSF] = deconvblind(I,INITPSF) deconvolves image I using the maximum likelihood algorithm, returning both the deblurred image J and a restored point-spread function PSF. The input array I and your initial guess at the PSF INITPSF can be numeric arrays or cell arrays. (Use cell arrays when you want to be able to perform additional deconvolutions that start where your initial deconvolution finished. The restored PSF is a positive array that is the same size as INITPSF, normalized so its sum adds up to 1.

Note The PSF restoration is affected strongly by the size of the initial guess INITPSF and less by the values it contains. For this reason, specify an array of 1's as your INITPSF.

To improve the restoration, deconvblind supports several optional parameters, described below. Use [] as a placeholder if you do not specify an intermediate parameter.

[J,PSF] = deconvblind(I,INITPSF,NUMIT) specifies the number of iterations (default is 10).

[J,PSF] = deconvblind(I,INITPSF,NUMIT,DAMPAR) specifies the threshold deviation of the resulting image from the input image I (in terms of the standard deviation of Poisson noise) below which damping occurs. The iterations are suppressed for the pixels that deviate within the DAMPAR value from their original value. This suppresses the noise generation in such pixels, preserving necessary image details elsewhere. The default value is 0 (no damping).

deconvblind

[J,PSF] = deconvblind(I,INITPSF,NUMIT,DAMPAR,WEIGHT) specifies which pixels in the input image I are considered in the restoration. By default, WEIGHT is a unit array, the same size as the input image. You can assign a value between 0.0 and 1.0 to elements in the WEIGHT array. The value of an element in the WEIGHT array determines how much the pixel at the corresponding position in the input image is considered. For example, to exclude a pixel from consideration, assign it a value of 0 in the WEIGHT array. You can adjust the weight value assigned to each pixel according to the amount of flat-field correction.

[J,PSF] = deconvblind(I,INITPSF,NUMIT,DAMPAR,WEIGHT,READOUT), where READOUT is an array (or a value) corresponding to the additive noise (e.g., background, foreground noise) and the variance of the read-out camera noise. READOUT has to be in the units of the image. The default value is 0.

[J,PSF] = deconvblind(...,FUN,P1,P2,...,PN), where FUN is a function describing additional constraints on the PSF. FUN must be a function handle.

FUN is called at the end of each iteration. FUN must accept the PSF as its first argument and can accept additional parameters P1, P2,..., PN. The FUN function should return one argument, PSF, that is the same size as the original PSF and that satisfies the positivity and normalization constraints.

Note The output image J could exhibit ringing introduced by the discrete Fourier transform used in the algorithm. To reduce the ringing, use I = edgetaper(I,PSF) before calling deconvblind.

Resuming Deconvolution

You can use deconvblind to perform a deconvolution that starts where a previous deconvolution stopped. To use this feature, pass the input image I and the initial guess at the PSF, INITPSF, as cell arrays: {I} and {INITPSF}. When you do, the deconvblind function returns the output image J and the restored point-spread function, PSF, as cell arrays, which can then be passed as the

input arrays into the next deconvblind call. The output cell array J contains four elements:

- J{1} contains I, the original image.
- J{2} contains the result of the last iteration.
- J{3} contains the result of the next-to-last iteration.
- J{4} is an array generated by the iterative algorithm.

Class Support

I and INITPSF can be uint8, uint16, int16, double, or single. DAMPAR and READOUT must have the same class as the input image. Other inputs have to be double. The output image J (or the first array of the output cell) has the same class as the input image I. The output PSF is double.

Example

```
I = checkerboard(8);
PSF = fspecial('gaussian',7,10);
V = .0001;
BlurredNoisy = imnoise(imfilter(I,PSF), 'gaussian',0,V);
WT = zeros(size(I));
WT(5:end-4,5:end-4) = 1;
INITPSF = ones(size(PSF));
FUN = @(PSF,P1) PSF + P1;
[J P] = deconvblind(BlurredNoisy, INITPSF, 20, 10*sqrt(V), WT, FUN, 0);
subplot(221);imshow(BlurredNoisy);
title('A = Blurred and Noisy');
subplot(222);imshow(PSF,[]);
title('True PSF');
subplot(223);imshow(J);
title('Deblured Image');
subplot(224);imshow(P,[]);
title('Recovered PSF');
```

See Also

deconvlucy, deconvreg, deconvwnr, edgetaper, function_handle, imnoise, otf2psf, padarray, psf2otf

deconvlucy

Purpose

Restore image using the Lucy-Richardson algorithm

Syntax

- J = deconvlucy(I,PSF)
- J = deconvlucy(I,PSF,NUMIT)
- J = deconvlucy(I,PSF,NUMIT,DAMPAR)
- J = deconvlucy(I,PSF,NUMIT,DAMPAR,WEIGHT)
- J = deconvlucy(I,PSF,NUMIT,DAMPAR,WEIGHT,READOUT)
- J = deconvlucy(I,PSF,NUMIT,DAMPAR,WEIGHT,READOUT,SUBSMPL)

Description

J = deconvlucy(I,PSF) restores image I that was degraded by convolution with a point-spread function PSF and possibly by additive noise. The algorithm is based on maximizing the likelihood of the resulting image J's being an instance of the original image I under Poisson statistics. The input array I can be a numeric array (the blurred image) or a cell array.

If I is a cell array, it can contain a single numerical array (the blurred image) or it can be the output from a previous run of deconvlucy.

When you pass a cell array to deconvlucy as input, it returns a 1-by-4 cell array J, where

- J{1} contains I, the original image.
- J{2} contains the result of the last iteration.
- J{3} contains the result of the next-to-last iteration.
- J{4} is an array generated by the iterative algorithm.

To improve the restoration, deconvlucy supports several optional parameters. Use [] as a placeholder if you do not specify an intermediate parameter.

- J = deconvlucy(I,PSF,NUMIT) specifies the number of iterations the deconvlucy function performs. If this value is not specified, the default is 10.
- J = deconvlucy(I,PSF,NUMIT,DAMPAR) specifies the threshold deviation of the resulting image from the image I (in terms of the standard deviation of Poisson noise) below which damping occurs. Iterations are suppressed for pixels that deviate beyond the DAMPAR value from their original value. This suppresses the noise generation in such pixels, preserving necessary image details elsewhere. The default value is 0 (no damping).

J = deconvlucy(I,PSF,NUMIT,DAMPAR,WEIGHT) specifies the weight to be assigned to each pixel to reflect its recording quality in the camera. A bad pixel is excluded from the solution by assigning it zero weight value. Instead of giving a weight of unity for good pixels, you can adjust their weight according to the amount of flat-field correction. The default is a unit array of the same size as input image I.

J = deconvlucy(I,PSF,NUMIT,DAMPAR,WEIGHT,READOUT) specifies a value corresponding to the additive noise (e.g., background, foreground noise) and the variance of the readout camera noise. READOUT has to be in the units of the image. The default value is 0.

J = deconvlucy(I,PSF,NUMIT,DAMPAR,WEIGHT,READOUT,SUBSMPL), where SUBSMPL denotes subsampling and is used when the PSF is given on a grid that is SUBSMPL times finer than the image. The default value is 1.

Note The output image J could exhibit ringing introduced by the discrete Fourier transform used in the algorithm. To reduce the ringing, use I = edgetaper(I,PSF) before calling deconvlucy.

Class Support

I and PSF can be uint8, uint16, int16, double, or single. DAMPAR and READOUT must have the same class as the input image. Other inputs have to be double. The output image J (or the first array of the output cell) has the same class as the input image I.

Example

```
I = checkerboard(8);
PSF = fspecial('gaussian',7,10);
V = .0001;
BlurredNoisy = imnoise(imfilter(I,PSF),'gaussian',0,V);
WT = zeros(size(I));
WT(5:end-4,5:end-4) = 1;
J1 = deconvlucy(BlurredNoisy,PSF);
J2 = deconvlucy(BlurredNoisy,PSF,20,sqrt(V));
J3 = deconvlucy(BlurredNoisy,PSF,20,sqrt(V),WT);
subplot(221);imshow(BlurredNoisy);
title('A = Blurred and Noisy');
```

deconvlucy

```
subplot(222);imshow(J1);
title('deconvlucy(A,PSF)');
subplot(223);imshow(J2);
title('deconvlucy(A,PSF,NI,DP)');
subplot(224);imshow(J3);
title('deconvlucy(A,PSF,NI,DP,WT)');
```

See Also

deconvblind, deconvreg, deconvwnr, otf2psf, padarray, psf2otf

Restore image using a regularized filter

Syntax

- J = deconvreg(I,PSF)
- J = deconvreg(I,PSF,NOISEPOWER)
- J = deconvreg(I,PSF,NOISEPOWER,LRANGE)
- J = deconvreg(I,PSF,NOISEPOWER,LRANGE,REGOP)
- [J, LAGRA] = deconvreg(I,PSF,...)

Description

- J = deconvreg(I,PSF) restores image I that was degraded by convolution with a point-spread function PSF and possibly by additive noise. The algorithm is a constrained optimum in a sense of least square error between the estimated and the true images under the requirement of preserving image smoothness.
- J = deconvreg(I,PSF,NOISEPOWER), where NOISEPOWER is the additive noise power. The default value is 0.
- J = deconvreg(I,PSF,NOISEPOWER,LRANGE), where LRANGE is a vector specifying range where the search for the optimal solution is performed. The algorithm finds an optimal Lagrange multiplier LAGRA within the LRANGE range. If LRANGE is a scalar, the algorithm assumes that LAGRA is given and equal to LRANGE; the NP value is then ignored. The default range is between [1e-9 and 1e9].
- J = deconvreg(I,PSF,NOISEPOWER,LRANGE,REGOP), where REGOP is the regularization operator to constrain the deconvolution. The default regularization operator is the Laplacian operator, to retain the image smoothness. The REGOP array dimensions must not exceed the image dimensions; any nonsingleton dimensions must correspond to the nonsingleton dimensions of PSF.
- [J, LAGRA] = deconvreg(I,PSF,...) outputs the value of the Lagrange multiplier LAGRA in addition to the restored image J.

Note The output image J could exhibit ringing introduced by the discrete Fourier transform used in the algorithm. To reduce the ringing, process the image with the edgetaper function prior to calling the deconvreg function. For example, I = edgetaper(I,PSF).

deconvreg

Class Support

I can be of class uint8, uint16, int16, double, or single. Other inputs have to be of class double. J has the same class as I.

Example

```
I = checkerboard(8);
PSF = fspecial('gaussian',7,10);
V = .01;
BlurredNoisy = imnoise(imfilter(I,PSF), 'gaussian',0,V);
NOISEPOWER = V*prod(size(I));
[J LAGRA] = deconvreg(BlurredNoisy,PSF,NOISEPOWER);

subplot(221); imshow(BlurredNoisy);
title('A = Blurred and Noisy');
subplot(222); imshow(J);
title('[J LAGRA] = deconvreg(A,PSF,NP)');
subplot(223); imshow(deconvreg(BlurredNoisy,PSF,[],LAGRA/10));
title('deconvreg(A,PSF,[],0.1*LAGRA)');
subplot(224); imshow(deconvreg(BlurredNoisy,PSF,[],LAGRA*10));
title('deconvreg(A,PSF,[],10*LAGRA)');
```

See Also

deconvblind, deconvlucy, deconvwnr, otf2psf, padarray, psf2otf

Restore image using the Wiener filter

Syntax

```
J = deconvwnr(I,PSF)
J = deconvwnr(I,PSF,NSR)
J = deconvwnr(I,PSF,NCORR,ICORR)
```

Description

J = deconvwnr(I,PSF) restores image I that was degraded by convolution with a point-spread function PSF and possibly by additive noise. The algorithm is optimal in a sense of least mean square error between the estimated and the true image, and uses the correlation matrixes of image and noise. In the absence of noise, the Wiener filter reduces to the ideal inverse filter.

J = deconvwnr(I, PSF, NSR), where NSR is the noise-to-signal power ratio. NSR could be a scalar or an array of the same size as I. The default value is 0.

J = deconvwnr(I,PSF,NCORR,ICORR), where NCORR and ICORR are the autocorrelation functions of the noise and the original image, respectively. NCORR and ICORR can be of any size or dimension not exceeding the original image. An N-dimensional NCORR or ICORR array corresponds to the autocorrelation within each dimension. A vector NCORR or ICORR represents an autocorrelation function in the first dimension if PSF is a vector. If PSF is an array, the 1-D autocorrelation function is extrapolated by symmetry to all nonsingleton dimensions of PSF. A scalar NCORR or ICORR represents the power of the noise or the image.

Note The output image J could exhibit ringing introduced by the discrete Fourier transform used in the algorithm. To reduce the ringing, process the image with the edgetaper function prior to calling the deconvwnr function. For example, I = edgetaper(I,PSF)

Class Support

I can be of class uint8, uint16, int16, double, or single. Other inputs have to be of class double. J has the same class as I.

Example

```
I = checkerboard(8);
noise = 0.1*randn(size(I));
PSF = fspecial('motion',21,11);
Blurred = imfilter(I,PSF,'circular');
```

```
BlurredNoisy = im2uint8(Blurred + noise);
NSR = sum(noise(:).^2)/sum(I(:).^2);% noise-to-power ratio
NP = abs(fftn(noise)).^2;% noise power
NPOW = sum(NP(:))/prod(size(noise));
NCORR = fftshift(real(ifftn(NP)));% noise autocorrelation
function, centered
IP = abs(fftn(I)).^2;% original image power
IPOW = sum(IP(:))/prod(size(I));
ICORR = fftshift(real(ifftn(IP)));% image autocorrelation
function, centered
ICORR1 = ICORR(:,ceil(size(I,1)/2));
NSR = NPOW/IPOW;
subplot(221);imshow(BlurredNoisy,[]);
title('A = Blurred and Noisy');
subplot(222);imshow(deconvwnr(BlurredNoisy,PSF,NSR),[]);
title('deconvwnr(A,PSF,NSR)');
subplot(223);imshow(deconvwnr(BlurredNoisy,PSF,NCORR,ICORR),[])
title('deconvwnr(A,PSF,NCORR,ICORR)');
subplot(224);imshow(deconvwnr(BlurredNoisy,PSF,NPOW,ICORR1),[])
title('deconvwnr(A, PSF, NPOW, ICORR 1 D)');
```

See Also

deconvblind, deconvlucy, deconvreg, otf2psf, padarray, psf2otf

Apply a decorrelation stretch to a multichannel image

Syntax

```
S = decorrstretch(I)
S = decorrstretch(I,TOL)
```

Description

S = decorretretch(I) applies a decorrelation stretch to a multichannel image I and returns the result in S. S has the same size and class as I. The mean and variance in each band are the same as in I.

S = decorrstretch(I,TOL) applies a contrast following the decorrelation stretch. The contrast stretch is controlled by TOL:

- TOL = [LOW_FRACT HIGH_FRACT] specifies the fraction of the image to saturate at low and high intensities.
- If TOL is a scalar, LOW_FRACT = TOL, and HIGH_FRACT = 1 TOL, which saturates equal fractions at low and high intensities.

Notes

The decorrelation stretch is normally applied to three band images (ordinary RGB images or RGB multispectral composite images), but decorretch works on an arbitrary number of bands.

The primary purpose of decorrelation stretch is visual enhancement. Small adjustments to TOL can strongly affect the visual appearance of the output.

Class Support

The input image must be of class uint8, uint16, int16, single, or double.

Example

```
[X, map] = imread('forest.tif');
S = decorrstretch(ind2rgb(X, map), 'tol', 0.01);
figure, imshow(X, map)
figure, imshow(S)
```

See Also

imadjust, stretchlim

Anonymize a DICOM file

Syntax

```
dicomanon(file_in, file_out)
dicomanon(...,'keep',FIELDS)
dicomanon(...,'update',ATTRS)
```

Description

dicomanon(file_in,file_out) removes confidential medical information from the DICOM file file_in and creates a new file file_out with the modified values. Image data and other attributes are unmodified.

dicomanon(..., 'keep', FIELDS) modifies all of the confidential data except for those listed in FIELDS, which is a cell array of field names. This syntax is useful for keeping metadata that does not uniquely identify the patient but is useful for diagnostic purposes (e.g., PatientAge, PatientSex, etc.).

Note Keeping certain fields might compromise patient confidentiality.

dicomanon(..., 'update',ATTRS) modifies the confidential data and updates particular confidential data. ATTRS is a structure. The field names of ATTRS are the attributes to preserve, and the structure values are the attribute values. Use this syntax to preserve the Study/Series/Image hierarchy or to replace a specific value with a more generic property (e.g., remove PatientBirthDate but keep a computed PatientAge).

For information about the fields that will be modified or removed, see DICOM Supplement 55 from http://medical.nema.org/.

Examples

Remove all confidential metadata from a file.

```
\verb|dicomanon('patient.dcm', 'anonymized.dcm')| \\
```

Create a training file.

Anonymize a series of images, keeping the hierarchy.

```
values.StudyInstanceUID = dicomuid;
```

dicomanon

dicomdict

Purpose

Get or set the active DICOM data dictionary

Syntax

```
dicomdict('set', dictionary)
dictionary = dicomdict('get')
dictionary = dicomdict('factory')
```

Description

dicomdict('set', dictionary) sets the Digital Imaging and Communications in Medicine (DICOM) data dictionary to the value stored in dictionary, a string containing the filename of the dictionary. DICOM-related functions use this dictionary by default, unless a different dictionary is provided at the command line.

dictionary = dicomdict('get') returns a string containing the filename of the stored DICOM data dictionary.

dictionary = dicomdict('factory') resets the DICOM data dictionary to its default startup value.

Note The default data dictionary is a MAT-file, dicom-dict.mat. The toolbox also includes a text version of this default data dictionary, dicom-dict.txt. If you want to create your own DICOM data dictionary, open the dicom-dict.txt file in a text editor, modify it, and save it under another name.

Example

```
dictionary = dicomdict('get')
dictionary =
dicom-dict.mat
```

See Also

dicominfo, dicomread, dicomwrite

Purpose Read metadata from a DICOM message

Syntax info = dicominfo(filename)

info = dicominfo(filename, 'dictionary', D)

Description

info = dicominfo(filename) reads the metadata from the compliant Digital Imaging and Communications in Medicine (DICOM) file specified in the string filename.

info = dicominfo(filename, 'dictionary', D) uses the data dictionary file given in the string D to read the DICOM message. The file in D must be on the MATLAB search path. The default file is dicom-dict.mat.

Examples

```
info = dicominfo('CT-MONO2-16-ankle.dcm')
```

info =

Filename: [1x68 char]

FileModDate: '18-Dec-2000 12:06:43'

FileSize: 525436 Format: 'DICOM'

FormatVersion: 3

Width: 512 Height: 512

BitDepth: 16

ColorType: 'grayscale'

.

See Also

dicomdict, dicomread, dicomwrite, dicomuid

Read a DICOM image

Syntax

```
X = dicomread(filename)
X = dicomread(info)
[X,map] = dicomread(...)
[X,map,alpha] = dicomread(...)
[X,map,alpha,overlays] = dicomread(...)
[...] = dicomread(filename,'frames',v)
```

Description

X = dicomread(filename) reads the image data from the compliant Digital Imaging and Communications in Medicine (DICOM) file filename. For single-frame grayscale images, X is an M-by-N array. For single-frame true-color images, X is an M-by-N-by-3 array. Multiframe images are always 4-D arrays.

X = dicomread(info) reads the image data from the message referenced in the DICOM metadata structure info. The info structure is produced by the dicominfo function.

[X, map] = dicomread(...) returns the image X and the colormap map. If X is a grayscale or true-color image, map is empty.

[X,map,alpha] = dicomread(...) returns the image X, the colormap map, and an alpha channel matrix for X. The values of alpha are 0 if the pixel is opaque; otherwise they are row indices into map. The RGB value in map should be substituted for the value in X to use alpha. alpha has the same height and width as X and is 4-D for a multiframe image.

[X,map,alpha,overlays] = dicomread(...) returns the image X, the colormap map, an alpha channel matrix for X, and any overlays from the DICOM file. Each overlay is a 1-bit black and white image with the same height and width as X. If multiple overlays are present in the file, overlays is a 4-D multiframe image. If no overlays are in the file, overlays is empty.

[...] = dicomread(filename, 'frames', v) reads only the frames in the vector v from the image. v must be an integer scalar, a vector of integers, or the string 'all'. The default value is 'all'.

Class Support

X can be uint8, int8, uint16, or int16. map must be double. alpha has the same size and type as X. overlays is a logical array.

Examples

Retrieve the data matrix X and colormap matrix map and create a montage.

```
[X, map] = dicomread('US-PAL-8-10x-echo.dcm');
montage(X, map);
```

Call dicomread with the information retrieved from the DICOM file using dicominfo. Because a DICOM image is a 16-bit image, the example uses the imshow autoscaling syntax to display the image.

```
info = dicominfo('CT-MONO2-16-ankle.dcm');
Y = dicomread(info);
figure, imshow(Y, 'DisplayRange',[]);
```

See Also

dicomdict, dicominfo, dicomwrite

dicomuid

Purpose Generate a DICOM unique identifier

Syntax UID = dicomuid

Description UID = dicomuid creates a string UID containing a new DICOM unique

identifier.

Multiple calls to dicomuid produce globally unique values. Two calls to

dicomuid always return different values.

See Also dicominfo, dicomwrite

Write images as DICOM files

Syntax

```
dicomwrite(X, filename)
dicomwrite(X, map, filename)
dicomwrite(...,param1,value1,param2,value2,...)
dicomwrite(...,'ObjectType',IOD,...)
dicomwrite(...,'SOPClassUID',UID,...)
dicomwrite(...,meta_struct,...)
dicomwrite(...,info,...)
status = dicomwrite(...)
```

Description

dicomwrite(X, filename) writes the binary, grayscale, or truecolor image X to the file filename, where filename is a string specifying the name of the Digital Imaging and Communications in Medicine (DICOM) file to create.

dicomwrite(X, map, filename) writes the indexed image X with colormap map.

dicomwrite(...,param1,value1,param2,value2,...) specifies additional metadata to write to the DICOM file or parameters that affect how the file is written. param1 is a string containing the metadata attribute name or a dicomwrite-specific option. value1 is the corresponding value for the attribute or option.

To find a list of the DICOM attributes that you can specify, see the data dictionary file, dicom-dict.txt, included with the Image Processing Toolbox.

dicomwrite

The following table lists the options that you can specify, in alphabetical order. Default values are enclosed in braces $(\{\})$.

Option Name	Description
'CompressionMode'	String specifying the type of compression to use when storing the image. Possible values:
	<pre>{'None'} 'JPEG lossless' 'JPEG lossy' 'RLE'</pre>
'CreateMode'	Specifies the method used for creating the data to put in the new file. Possible values: {'Create'} — Verify input values and generate missing data values. 'Copy' — Copy all values from the input and do not generate missing values.
'Dictionary'	String specifying the name of a DICOM data dictionary.
'Endian'	String specifying the byte ordering of the file. 'Big' {'Little'} Note: If VR is set to 'Explicit', 'Endian' must be 'Big'. dicomwrite ignores this value if CompressionMode or TransferSyntax is set.
'TransferSyntax'	A DICOM UID specifying the Endian and VR mode. Note: If If specified, dicomwrite ignores any values specified for the Endian, VR, and CompressionMode options. The TransferSyntax value encodes values for these options.

Option Name	Description
'VR'	String specifying whether the two-letter value representation (VR) code should be written to the file.
	'explicit' — Write VR to file. {'implicit'} — Infer from data dictionary.
	Note: If you specify the 'Endian' value 'Big', you must specify 'Explicit'.
'WritePrivate'	Logical value indicating whether private data should be written to the file. Possible values: true — Write private data to file. {false} — Do not write private data.

dicomwrite(..., 'ObjectType', IOD,...) writes a file containing the necessary metadata for a particular type of DICOM Information Object (IOD). Supported IODs are

- 'Secondary Capture Image Storage' (default)
- 'CT Image Storage'
- 'MR Image Storage'

dicomwrite(..., 'SOPClassUID', UID,...) provides an alternate method for specifying the IOD to create. UID is the DICOM unique identifier corresponding to one of the IODs listed above.

dicomwrite(...,meta_struct,...) specifies optional metadata or file options in structure meta_struct. The names of fields in meta_struct must be the names of DICOM file attributes or options. The value of a field is the value you want to assign to the attribute or option.

dicomwrite(...,info,...) specifies metadata in the metadata structure info, which is produced by the dicominfo function. For more information about this structure, see dicominfo.

status = dicomwrite(...) returns information about the metadata and the descriptions used to generate the DICOM file. This syntax can be useful when

you specify an info structure that was created by dicominfo to the dicomwrite function. An info structure can contain many fields. If no metadata was specified, dicomwrite returns an empty matrix ([]).

The structure returned by dicomwrite contains these fields:

Field	Description
'BadAttribute'	The attribute's internal description is bad. It might be missing from the data dictionary or have incorrect data in its description.
'MissingCondition'	The attribute is conditional but no condition has been provided for when to use it.
'MissingData'	No data was provided for an attribute that must appear in the file.
'SuspectAttribute'	Data in the attribute does not match a list of enumerated values in the DICOM specification.

Example

This example reads a CT image from the sample DICOM file included with the toolbox. The example then writes the CT image to a file, creating a "secondary capture" image.

```
X = dicomread('CT-MONO2-16-ankle.dcm');
dicomwrite(X, 'sc_file.dcm');
```

This example writes the CT image, X, to a DICOM file along with its metadata. You use the dicominfo function to retrieve metadata from a DICOM file.

```
metadata = dicominfo('CT-MONO2-16-ankle.dcm');
dicomwrite(X, 'ct_file.dcm', metadata);
```

Copy all metadata from one file to another.

```
\label{linear_converse_converse} \verb|dicomwrite(X, 'ct_copy.dcm', metadata, 'CreateMode', 'copy'); \\
```

See Also

dicomdict, dicominfo, dicomread, dicomuid

Convert an image, increasing apparent color resolution by dithering

Syntax

```
X = dither(RGB,map)
BW = dither(I)
```

Description

X = dither(RGB, map) creates an indexed image approximation of the RGB image in the array RGB by dithering the colors in the colormap map. The colormap cannot have more than 65,536 colors.

X = dither(RGB, map, Qm, Qe) creates an indexed image from RGB, specifying the parameters Qm and Qe. Qm specifies the number of quantization bits to use along each color axis for the inverse color map, and Qe specifies the number of quantization bits to use for the color space error calculations. If Qe < Qm, dithering cannot be performed, and an undithered indexed image is returned in X. If you omit these parameters, dither uses the default values Qm = 5, Qe = 8.

BW = dither(I) converts the intensity image in the matrix I to the binary (black and white) image BW by dithering.

Class Support

RGB can be uint8, uint16, single, or double. I can be uint8, uint16, int16, single, or double. All other input arguments must be double. BW is logical. X is uint8, if it is an indexed image with 256 or fewer colors; otherwise, it is uint16.

Algorithm

dither increases the apparent color resolution of an image by applying Floyd-Steinberg's error diffusion dither algorithm.

Example

Convert intensity image to binary using dithering.

```
I = imread('cameraman.tif');
BW = dither(I);
imshow(I), figure, imshow(BW)
```

See Also

rgb2ind

References

[1] Floyd, R. W., and L. Steinberg, "An Adaptive Algorithm for Spatial Gray Scale," *International Symposium Digest of Technical Papers*, Society for Information Displays, 1975, p. 36.

dither

[2] Lim, Jae S., Two-Dimensional Signal and Image Processing, Englewood Cliffs, NJ, Prentice Hall, 1990, pp. 469-476.

Convert data to double precision

double is a MATLAB built-in function. To get help for this function, select **MATLAB Help** from the Help menu and view the online function reference page.

Find edges in an intensity image

Syntax

```
BW = edge(I, 'sobel')
BW = edge(I, 'sobel', thresh)
BW = edge(I, 'sobel', thresh, direction)
[BW,thresh] = edge(I,'sobel',...)
BW = edge(I, 'prewitt')
BW = edge(I, 'prewitt', thresh)
BW = edge(I, 'prewitt', thresh, direction)
[BW,thresh] = edge(I,'prewitt',...)
BW = edge(I, 'roberts')
BW = edge(I, 'roberts', thresh)
[BW,thresh] = edge(I,'roberts',...)
BW = edge(I, 'log')
BW = edge(I, 'log', thresh)
BW = edge(I,'log',thresh,sigma)
[BW,threshold] = edge(I,'log',...)
BW = edge(I, 'zerocross', thresh,h)
[BW,thresh] = edge(I, 'zerocross',...)
BW = edge(I, 'canny')
BW = edge(I, 'canny', thresh)
BW = edge(I, 'canny', thresh, sigma)
[BW,threshold] = edge(I, 'canny',...)
```

Description

edge takes an intensity image I as its input, and returns a binary image BW of the same size as I, with 1's where the function finds edges in I and 0's elsewhere.

edge supports six different edge-finding methods:

• The Sobel method finds edges using the Sobel approximation to the derivative. It returns edges at those points where the gradient of I is maximum.

- The Prewitt method finds edges using the Prewitt approximation to the derivative. It returns edges at those points where the gradient of I is maximum.
- The Roberts method finds edges using the Roberts approximation to the derivative. It returns edges at those points where the gradient of I is maximum.
- The Laplacian of Gaussian method finds edges by looking for zero crossings after filtering I with a Laplacian of Gaussian filter.
- The zero-cross method finds edges by looking for zero crossings after filtering I with a filter you specify.
- The Canny method finds edges by looking for local maxima of the gradient of I. The gradient is calculated using the derivative of a Gaussian filter. The method uses two thresholds, to detect strong and weak edges, and includes the weak edges in the output only if they are connected to strong edges. This method is therefore less likely than the others to be fooled by noise, and more likely to detect true weak edges.

The parameters you can supply differ depending on the method you specify. If you do not specify a method, edge uses the Sobel method.

Sobel Method

BW = edge(I, 'sobel') specifies the Sobel method.

BW = edge(I, 'sobel', thresh) specifies the sensitivity threshold for the Sobel method. edge ignores all edges that are not stronger than thresh. If you do not specify thresh, or if thresh is empty ([]), edge chooses the value automatically.

BW = edge(I, 'sobel', thresh, direction) specifies the direction of detection for the Sobel method. direction is a string specifying whether to look for 'horizontal' or 'vertical' edges or 'both' (the default).

BW = edge(I, 'sobel',...,options) provides an optional string input. String 'nothinning' speeds up the operation of the algorithm by skipping the additional edge thinning stage. By default, or when 'thinning' string is specified, the algorithm applies edge thinning.

[BW,thresh] = edge(I, 'sobel',...) returns the threshold value.

[BW,thresh,gv,gh] = edge(I, 'sobel',...) returns vertical and horizontal edge responses to Sobel gradient operators. You can also use the following expressions to obtain gradient responses:

```
if ~(isa(I,'double') || isa(I,'single')); I = im2single(I); end
gh = imfilter(I,fspecial('sobel') /8,'replicate'); and
gv = imfilter(I,fspecial('sobel')'/8,'replicate');
```

Prewitt Method

```
BW = edge(I, 'prewitt') specifies the Prewitt method.
```

BW = edge(I, 'prewitt', thresh) specifies the sensitivity threshold for the Prewitt method. edge ignores all edges that are not stronger than thresh. If you do not specify thresh, or if thresh is empty([]), edge chooses the value automatically.

BW = edge(I, 'prewitt', thresh, direction) specifies the direction of detection for the Prewitt method. direction is a string specifying whether to look for

```
'horizontal' or 'vertical' edges or 'both' (the default).
```

```
[BW, thresh] = edge(I, 'prewitt',...) returns the threshold value.
```

Roberts Method

```
BW = edge(I.'roberts') specifies the Roberts method.
```

BW = edge(I, 'roberts', thresh) specifies the sensitivity threshold for the Roberts method. edge ignores all edges that are not stronger than thresh. If you do not specify thresh, or if thresh is empty ([]), edge chooses the value automatically.

```
[BW, thresh] = edge(I, 'roberts',...) returns the threshold value.
```

Laplacian of Gaussian Method

```
BW = edge(I, 'log') specifies the Laplacian of Gaussian method.
```

BW = edge(I, 'log', thresh) specifies the sensitivity threshold for the Laplacian of Gaussian method. edge ignores all edges that are not stronger than thresh. If you do not specify thresh, or if thresh is empty([]), edge chooses the value automatically.

BW = edge(I, 'log', thresh, sigma) specifies the Laplacian of Gaussian method, using sigma as the standard deviation of the LoG filter. The default sigma is 2; the size of the filter is n-by-n, where n = ceil(sigma*3)*2+1.

```
[BW, thresh] = edge(I, 'log',...) returns the threshold value.
```

Zero-Cross Method

BW = edge(I, 'zerocross', thresh,h) specifies the zero-cross method, using the filter h. thresh is the sensitivity threshold; if the argument is empty([]), edge chooses the sensitivity threshold automatically.

```
[BW, thresh] = edge(I, 'zerocross',...) returns the threshold value.
```

Canny Method

```
BW = edge(I, 'canny') specifies the Canny method.
```

BW = edge(I, 'canny', thresh) specifies sensitivity thresholds for the Canny method. thresh is a two-element vector in which the first element is the low threshold, and the second element is the high threshold. If you specify a scalar for thresh, this value is used for the high threshold and 0.4*thresh is used for the low threshold. If you do not specify thresh, or if thresh is empty ([]), edge chooses low and high values automatically.

BW = edge(I, 'canny', thresh, sigma) specifies the Canny method, using sigma as the standard deviation of the Gaussian filter. The default sigma is 1; the size of the filter is chosen automatically, based on sigma.

[BW,thresh] = edge(I, 'canny',...) returns the threshold values as a two-element vector.

Class Support

I is a nonsparse numeric array. BW is of class logical.

Remarks

For the 'log' and 'zerocross' methods, if you specify a threshold of 0, the output image has closed contours, because it includes all the zero crossings in the input image.


Example


Find the edges of an image using the Prewitt and Canny methods.

```
I = imread('circuit.tif');
BW1 = edge(I,'prewitt');
BW2 = edge(I,'canny');
```

edge

imshow(BW1);
figure, imshow(BW2)





Prewitt Filter

Canny Filter

See Also

fspecial

References

- [1] Canny, John, "A Computational Approach to Edge Detection," *IEEE Transactions on Pattern Analysis and Machine Intelligence*, Vol. PAMI-8, No. 6, 1986, pp. 679-698.
- [2] Lim, Jae S., *Two-Dimensional Signal and Image Processing*, Englewood Cliffs, NJ, Prentice Hall, 1990, pp. 478-488.
- [3] Parker, James R., Algorithms for Image Processing and Computer Vision, New York, John Wiley & Sons, Inc., 1997, pp. 23-29.

Taper the discontinuities along the image edges

Syntax

J = edgetaper(I,PSF)

Description

J = edgetaper(I,PSF) blurs the edges of the input image I using the point spread function PSF. The output image J is the weighted sum of the original image I and its blurred version. The weighting array, determined by the autocorrelation function of PSF, makes J equal to I in its central region, and equal to the blurred version of I near the edges.

The edgetaper function reduces the ringing effect in image deblurring methods that use the discrete Fourier transform, such as deconvwnr, deconvreg, and deconvlucy.

Note The size of the PSF cannot exceed half of the image size in any dimension.

Class Support

I and PSF can be of class uint8, uint16, int16, single, or double. J is of the same class as I.

Example

```
original = imread('cameraman.tif');
PSF = fspecial('gaussian',60,10);
edgesTapered = edgetaper(original,PSF);
figure, imshow(original,[]);
figure, imshow(edgesTapered,[]);
```

See Also

deconvlucy, deconvreg, deconvwnr, otf2psf, padarray, psf2otf

entropy

Purpose

Entropy of an intensity image

Syntax

E = entropy(I)

Description

E = entropy(I) returns E, a scalar value representing the entropy of intensity image I. Entropy is a statistical measure of randomness that can be used to characterize the texture of the input image. Entropy is defined as

```
-sum(p.*log(p))
```

where p contains the histogram counts returned from imhist. By default, entropy uses two bins for logical arrays and 256 bins for uint8, uint16, or double arrays.

I can be a multidimensional image. If I has more than two dimensions, the entropy function treats it as a multidimensional intensity image and not as an RGB image.

Class Support

I can be logical, uint8, uint16, or double and must be real, nonempty, and nonsparse. E is double.

Notes

entropy converts any class other than logical to uint8 for the histogram count calculation so that the pixel values are discrete and directly correspond to a bin value.

Example

I = imread('circuit.tif');
J = entropy(I)

See Also

imhist, entropyfilt, blkproc

References

[1] Gonzalez, R.C., R.E. Woods, S.L. Eddins, *Digital Image Processing using MATLAB*, New Jersey: Prentice Hall, 2003. Chapter 11.

Local entropy of an intensity image

Syntax

```
J = entropyfilt(I)
J = entropyfilt(I,NHOOD)
```

Description

J = entropyfilt(I) returns the array J, where each output pixel contains the entropy value of the 9-by-9 neighborhood around the corresponding pixel in the input image I. I can have any dimension. If I has more than two dimensions, the entropyfilt function treats it as a multidimensional intensity image and not as a truecolor (RGB) image. The output image J is the same size as the input image I.

For pixels on the borders of I, entropyfilt uses symmetric padding. In symmetric padding, the values of padding pixels are a mirror reflection of the border pixels in I.

J = entropyfilt(I,NHOOD) performs entropy filtering of the input image I where you specify the neighborhood in NHOOD. NHOOD is a multidimensional array of zeros and ones where the nonzero elements specify the neighbors. NHOOD's size must be odd in each dimension.

By default, entropyfilt uses the neighborhood true(9). entropyfilt determines the center element of the neighborhood by floor((size(NHOOD) + 1)/2). To specify neighborhoods of various shapes, such as a disk, use the strel function to create a structuring element object and then use the getnhood function to extract the neighborhood from the structuring element object.

Class Support

I can be logical, uint8, uint16, or double, and must be real and nonsparse. NHOOD can be logical or numeric and must contain zeros or ones. The output array J is of class double.

entropyfilt converts any class other than logical to uint8 for the histogram count calculation so that the pixel values are discrete and directly correspond to a bin value.

Example

```
I = imread('circuit.tif');
J = entropyfilt(I);
imshow(I), figure, imshow(J,[]);
```

entropyfilt

See Also entropy, imhist, rangefilt, stdfilt

References [1] Gonzalez, R.C., R.E. Woods, S.L. Eddins, *Digital Image Processing using*

MATLAB, New Jersey: Prentice Hall, 2003. Chapter 11.

Compute parallel-beam projections from fan-beam tomography data

Syntax

```
P = fan2para(F,D)
P = fan2para(...,param1,val1,param2,val2,...)
[P,parallel locations,parallel rotation angles] = fan2para(...)
```

Description

P = fan2para(F,D) computes the parallel-beam data (sinogram) from the fan-beam data (sinogram) F. Each column of F contains the fan-beam spread angles at a single rotation angle. D is the distance from the fan-beam vertex to the center of rotation.

fan2para assumes the fan-beam spread angles are the same increments as the input rotation angles, split equally on either side of zero. The input rotation angles are assumed to be stepped in equal increments to cover [0,360) degrees. Output angles are calculated to cover [0,180) degrees in the same increments as the input.

P = fan2para(...,param1,val1,param2,val2,...) specifies parameters that control various aspects of the fan2para conversion, listed in the following table. Parameter names can be abbreviated, and case does not matter. Default values are in braces ({}).

Parameter	Description
'FanCoverage'	String specifying the range through which the beams are rotated.
	Possible values: { 'cycle'} or 'minimal'
	See ifanbeam for details.
'FanRotationIncrement'	Positive real scalar specifying the increment of the rotation angle of the fan-beam projections, measured in degrees. Default value is 1.

fan2para

Parameter	Description
'FanSensorGeometry'	String specifying how sensors are positioned.
	Possible values: {'arc'} or 'line'
	See fanbeam for details.
'FanSensorSpacing'	Positive real scalar specifying the spacing of the fan beams. Interpretation of the value depends on the setting of 'FanSensorGeometry':
	If 'FanSensorGeometry' is 'arc', the value defines the angular spacing in degrees. Default value is 1.
	If 'FanSensorGeometry' is 'line', the value defines the linear spacing in pixels.
'Interpolation'	Text string specifying the type of interpolation used between the parallel-beam and fan-beam data.
	'nearest' — Nearest-neighbor
	{'linear'} — Linear
	'spline' — Piecewise cubic spline
	'pchip' — Piecewise cubic Hermite (PCHIP)
	'cubic' — Same as 'pchip'
'ParallelCoverage'	Text string specifying the range of rotation.
	Possible values: 'cycle' or {'halfcycle'}.
	See para2fan for details.

Parameter	Description
'ParallelRotationIncrement'	Positive real scalar specifying the parallel-beam rotation angle increment, measured in degrees. Parallel beam angles are calculated to cover [0,180) degrees with increment PAR_ROT_INC, where PAR_ROT_INC is the value of 'ParallelRotationIncrement'. 180/PAR_ROT_INC must be an integer. If 'ParallelRotationIncrement' is not specified, the increment is assumed to be the same as the increment of the fan-beam rotation angles.
'ParallelSensorSpacing'	Positive real scalar specifying the spacing of the parallel-beam sensors in pixels. The range of sensor locations is implied by the range of fan angles and is given by [D*sin(min(FAN_ANGLES)),D*sin(max(FAN_ANGLES))] If 'ParallelSensorSpacing' is not specified, the spacing is assumed to be uniform and is set to the minimum spacing implied by the fan angles and sampled over the range implied by the fan angles.

[P,parallel_locations,parallel_rotation_angles] = fan2para(...) returns the parallel-beam sensor locations in parallel_locations and rotation angles in parallel rotation angles.

Class Support

The input arguments, F and D, can be double or single, and they must be nonsparse. All other numeric inputs are double. The output P is double.

Example

Create synthetic parallel-beam data, derive fan-beam data, and then use the fan-beam data to recover the parallel-beam data.

```
ph = phantom(128);
theta = 0:179;
[Psynthetic,xp] = radon(ph,theta);
imshow(theta,xp,Psynthetic,[],'n'), axis normal
title('Synthetic Parallel-Beam Data')
xlabel('\theta (degrees)')
ylabel('x''')
```

See Also

fanbeam, ifanbeam, iradon, para2fan, phantom, radon

Purpose Compute fan-beam transform

Syntax F = fanbeam(I,D)

F = fanbeam(...,param1,val1,param1,val2,...)

[F,sensor_positions,fan_rotation_angles] = fanbeam(...)

Description

F = fanbeam(I,D) computes the fan-beam data (sinogram) F from the image I. D is the distance in pixels from the from the fan-beam vertex to the center of rotation. Each column of F contains the fan-beam sensor samples at one rotation angle. The sensors are assumed to have a one-degree angular spacing. The rotation angles are spaced equally to cover [0:359] degrees.

F = fanbeam(...,param1,val1,param1,val2,...) specifies parameters that control various aspects of the fan-beam projection, listed in the following table. Parameter names can be abbreviated, and case does not matter. Default values are enclosed in braces ({}).

Parameter	Description
'FanRotationIncrement'	Positive real scalar specifying the increment of the rotation angle of the fan-beam projections, measured in degrees. Default value is 1.
'FanSensorGeometry'	Text string specifying how sensors are positioned.
	${\ \ \ }^{\ \ \ }$ — Sensors are spaced along a circular arc at distance D from the center of rotation.
	'line' — Sensors are spaced equally along a line, the closest point of which is distance D from the center of rotation.
'FanSensorSpacing'	Positive real scalar specifying the spacing of the fan beams. Interpretation of the value depends on the setting of 'FanSensorGeometry':
	If 'FanSensorGeometry' is 'arc', the value defines the angular spacing in degrees. Default value is 1.
	If 'FanSensorGeometry' is 'line', the value defines the linear spacing in pixels.

fanbeam

[F,sensor_positions,fan_rotation_angles] = fanbeam(...) returns information about the position of sensors and rotation angles. If 'FanSensorGeometry' is 'arc', sensor_positions contains the fan-beam sensor measurement angles, measured in degrees. If 'FanSensorGeometry' is 'line', sensor_positions contains the fan-beam sensor positions along the line of sensors, measured in pixels. fan_rotation_angles contains rotation angles.

Class Support

I can be logical or numeric. All other numeric inputs and outputs can be double. None of the inputs can be sparse.

Example

```
ph = phantom(128);
imshow(ph)
[F,Floc,Fangles] = fanbeam(ph,250);
imshow(Fangles,Floc,F,[],'n'), axis normal
xlabel('Rotation Angles (degrees)')
ylabel('Sensor Positions (degrees)')
colormap(hot), colorbar
```

See Also

fan2para, ifanbeam, iradon, para2fan, phantom, radon

Reference

[1] Kak, A.C., & Slaney, M., *Principles of Computerized Tomographic Imaging*, IEEE Press, NY, 1988, pp. 92-93.

Compute two-dimensional fast Fourier transform

fft2 is a function in MATLAB. To get help for this function, select **MATLAB Help** from the Help menu and view the online function reference page.

fftn

Purpose

Compute N-dimensional fast Fourier transform

fftn is a function in MATLAB. To get help for this function, select **MATLAB Help** from the Help menu and view the online function reference page.

Shift zero-frequency component of fast Fourier transform to center of spectrum

fftshift is a function in MATLAB. To get help for this function, select **MATLAB Help** from the Help menu and view the online function reference page.

filter2

Purpose

Perform two-dimensional linear filtering

filter2 is a function in MATLAB. To get help for this function, select **MATLAB Help** from the Help menu and view the online function reference page.

Find output bounds for spatial transformation

Syntax

outbounds = findbounds(TFORM,inbounds)

Description

outbounds = findbounds(TFORM,inbounds) estimates the output bounds corresponding to a given spatial transformation and a set of input bounds. TFORM is a spatial transformation structure as returned by maketform. inbounds is 2-by-NUM_DIMS matrix. The first row of inbounds specifies the lower bounds for each dimension, and the second row specifies the upper bounds. NUM DIMS has to be consistent with the ndims in field of TFORM.

outbounds has the same form as inbounds. It is an estimate of the smallest rectangular region completely containing the transformed rectangle represented by the input bounds. Since outbounds is only an estimate, it might not completely contain the transformed input rectangle.

Notes

imtransform uses findbounds to compute the 'OutputBounds' parameter if the user does not provide it.

If TFORM contains a forward transformation (a nonempty forward_fcn field), then findbounds works by transforming the vertices of the input bounds rectangle and then taking minimum and maximum values of the result.

If TFORM does not contain a forward transformation, then findbounds estimates the output bounds using the Nelder-Mead optimization function fminsearch. If the optimization procedure fails, findbounds issues a warning and returns outbounds = inbounds.

Example

```
inbounds = [0 0; 1 1]
tform = maketform('affine',[2 0 0; .5 3 0; 0 0 1])
outbounds = findbounds(tform, inbounds)
```

See Also

cp2tform, imtransform, maketform, tformarray, tformfwd, tforminv

fliptform

Purpose Flip the input and output roles of a TFORM structure

Syntax TFLIP = fliptform(T)

Description TFLIP = fliptform(T) creates a new spatial transformation structure, a TFORM

struct, by flipping the roles of the inputs and outputs in an existing TFORM

struct.

T = maketform('affine', [.5 0 0; .5 2 0; 0 0 1]);

T2 = fliptform(T)

The following are equivalent:

x = tformfwd([-3 7],T)
x = tforminv([-3 7],T2)

See Also maketform, tformfwd, tforminv

Determine frequency spacing for two-dimensional frequency response

freqspace is a function in MATLAB. To get help for this function, select **MATLAB Help** from the Help menu and view the online function reference page.

Compute two-dimensional frequency response

Syntax

```
[H,f1,f2] = freqz2(h,n1,n2)
[H,f1,f2] = freqz2(h,[n2 n1])
[H,f1,f2] = freqz2(h)
[H,f1,f2] = freqz2(h,f1,f2)
[...] = freqz2(h,...,[dx dy])
[...] = freqz2(h,...,dx)
freqz2(...)
```

Description

[H,f1,f2] = freqz2(h,n1,n2) returns H, the n2-by-n1 frequency response of h, and the frequency vectors f1 (of length n1) and f2 (of length n2). h is a two-dimensional FIR filter, in the form of a computational molecule. f1 and f2 are returned as normalized frequencies in the range -1.0 to 1.0, where 1.0 corresponds to half the sampling frequency, or π radians.

```
[H,f1,f2] = freqz2(h,[n2 n1]) returns the same result returned by [H,f1,f2] = freqz2(h,n1,n2). [H,f1,f2] = freqz2(h) uses [n2 n1] = [64 64].
```

[H,f1,f2] = freqz2(h,f1,f2) returns the frequency response for the FIR filter h at frequency values in f1 and f2. These frequency values must be in the range -1.0 to 1.0, where 1.0 corresponds to half the sampling frequency, or π radians.

[...] = freqz2(h,...,[dx dy]) uses [dx dy] to override the intersample spacing in h. dx determines the spacing for the x dimension and dy determines the spacing for the y dimension. The default spacing is 0.5, which corresponds to a sampling frequency of 2.0.

[...] = freqz2(h,...,dx) uses dx to determine the intersample spacing in both dimensions.

With no output arguments, freqz2(...) produces a mesh plot of the two-dimensional magnitude frequency response.


Class Support

The input matrix h can be of class double or of any integer class. All other inputs to freqz2 must be of class double. All outputs are of class double.

Example

Use the window method to create a 16-by-16 filter, then view its frequency response using freqz2.

```
Hd = zeros(16,16);
Hd(5:12,5:12) = 1;
Hd(7:10,7:10) = 0;
h = fwind1(Hd,bartlett(16));
colormap(jet(64))
freqz2(h,[32 32]); axis ([-1 1 -1 1 0 1])
```



See Also

freqz in the Signal Processing Toolbox User's Guide documentation

fsamp2

Purpose

Design two-dimensional FIR filter using frequency sampling

Syntax

Description

fsamp2 designs two-dimensional FIR filters based on a desired two-dimensional frequency response sampled at points on the Cartesian plane.

h = fsamp2(Hd) designs a two-dimensional FIR filter with frequency response Hd, and returns the filter coefficients in matrix h. (fsamp2 returns h as a computational molecule, which is the appropriate form to use with filter2.) The filter h has a frequency response that passes through points in Hd. If Hd is m-by-n, then h is also m-by-n.

Hd is a matrix containing the desired frequency response sampled at equally spaced points between -1.0 and 1.0 along the x and y frequency axes, where 1.0 corresponds to half the sampling frequency, or π radians.

$$H_d(f_1,f_2) = H_d(\boldsymbol{\omega}_1,\boldsymbol{\omega}_2)\big|_{\boldsymbol{\omega}_1 = \pi f_1,\,\boldsymbol{\omega}_2 = \pi f_2}$$

For accurate results, use frequency points returned by freqspace to create Hd. (See the entry for freqspace for more information.)

h=fsamp2(f1,f2,Hd,[m n]) produces an m-by-n FIR filter by matching the filter response at the points in the vectors f1 and f2. The frequency vectors f1 and f2 are in normalized frequency, where 1.0 corresponds to half the sampling frequency, or π radians. The resulting filter fits the desired response as closely as possible in the least squares sense. For best results, there must be at least m*n desired frequency points. fsamp2 issues a warning if you specify fewer than m*n points.

Class Support


The input matrix Hd can be of class double or of any integer class. All other inputs to fsamp2 must be of class double. All outputs are of class double.

Example

Use fsamp2 to design an approximately symmetric two-dimensional bandpass filter with passband between 0.1 and 0.5 (normalized frequency, where 1.0 corresponds to half the sampling frequency, or π radians):

1 Create a matrix Hd that contains the desired bandpass response. Use freqspace to create the frequency range vectors f1 and f2.


```
[f1,f2] = freqspace(21,'meshgrid');
Hd = ones(21);
r = sqrt(f1.^2 + f2.^2);
Hd((r<0.1)|(r>0.5)) = 0;
colormap(jet(64))
mesh(f1,f2,Hd)
```



2 Design the filter that passes through this response.

```
h = fsamp2(Hd);
freqz2(h)
```

fsamp2



Algorithm

fsamp2 computes the filter h by taking the inverse discrete Fourier transform of the desired frequency response. If the desired frequency response is real and symmetric (zero phase), the resulting filter is also zero phase.

See Also

 $\verb"conv2", \verb"filter2", \verb"freqspace", \verb"ftrans2", \verb"fwind1", \verb"fwind2"$

Reference

[1] Lim, Jae S., *Two-Dimensional Signal and Image Processing*, Englewood Cliffs, NJ, Prentice Hall, 1990, pp. 213-217.

Create 2-D special filters

Syntax

h = fspecial(type)

h = fspecial(type,parameters)

Description

h = fspecial(type) creates a two-dimensional filter h of the specified type. fspecial returns h as a correlation kernel, which is the appropriate form to use with imfilter. type is a string having one of these values.

Value	Description
'gaussian'	Gaussian lowpass filter
'sobel'	Sobel horizontal edge-emphasizing filter
'prewitt'	Prewitt horizontal edge-emphasizing filter
'laplacian'	Filter approximating the two-dimensional Laplacian operator
'log'	Laplacian of Gaussian filter
'average'	Averaging filter
'unsharp'	Unsharp contrast enhancement filter

h = fspecial(type,parameters) accepts a filter type plus additional modifying parameters particular to the type of filter chosen. If you omit these arguments, fspecial uses default values for the parameters.

The following list shows the syntax for each filter type. Where applicable, additional parameters are also shown.

- h = fspecial('average', hsize) returns an averaging filter h of size hsize. The argument hsize can be a vector specifying the number of rows and columns in h, or it can be a scalar, in which case h is a square matrix. The default value for hsize is [3 3].
- h = fspecial('disk',radius) returns a circular averaging filter (pillbox) within the square matrix of side 2*radius+1. The default radius is 5.

- h = fspecial('gaussian', hsize, sigma) returns a rotationally symmetric Gaussian lowpass filter of size hsize with standard deviation sigma (positive). hsize can be a vector specifying the number of rows and columns in h, or it can be a scalar, in which case h is a square matrix. The default value for hsize is [3 3]; the default value for sigma is 0.5.
- h = fspecial('laplacian',alpha) returns a 3-by-3 filter approximating the shape of the two-dimensional Laplacian operator. The parameter alpha controls the shape of the Laplacian and must be in the range 0.0 to 1.0. The default value for alpha is 0.2.
- h = fspecial('log',hsize,sigma) returns a rotationally symmetric Laplacian of Gaussian filter of size hsize with standard deviation sigma (positive). hsize can be a vector specifying the number of rows and columns in h, or it can be a scalar, in which case h is a square matrix. The default value for hsize is [5 5] and 0.5 for sigma.
- h = fspecial('motion',len,theta) returns a filter to approximate, once convolved with an image, the linear motion of a camera by len pixels, with an angle of theta degrees in a counterclockwise direction. The filter becomes a vector for horizontal and vertical motions. The default len is 9 and the default theta is 0, which corresponds to a horizontal motion of nine pixels.
- h = fspecial('prewitt') returns a 3-by-3 filter h (shown below) that emphasizes horizontal edges by approximating a vertical gradient. If you need to emphasize vertical edges, transpose the filter h'.

```
[1 1 1
0 0 0
-1-1-1]
```

To find vertical edges, or for *x*-derivatives, use h'.

• h = fspecial('sobel') returns a 3-by-3 filter h (shown below) that emphasizes horizontal edges using the smoothing effect by approximating a vertical gradient. If you need to emphasize vertical edges, transpose the filter h'.

```
\begin{bmatrix} 1 & 2 & 1 \\ 0 & 0 & 0 \\ -1 & -2 & -1 \end{bmatrix}
```

• h = fspecial('unsharp',alpha) returns a 3-by-3 unsharp contrast enhancement filter. The unsharp contrast enhancement filter enhances edges, and other high frequency components in an image, by subtracting a smoothed ("unsharp") version of an image from the original image. fspecial creates the unsharp filter from the negative of the Laplacian filter with parameter alpha. alpha controls the shape of the Laplacian and must be in the range 0.0 to 1.0. The default value for alpha is 0.2.

Class Support

h is of class double.

Example

```
I = imread('cameraman.tif');
subplot(2,2,1);
imshow(I); title('Original Image');

H = fspecial('motion',20,45);
MotionBlur = imfilter(I,H,'replicate');
subplot(2,2,2);
imshow(MotionBlur);title('Motion Blurred Image');

H = fspecial('disk',10);
blurred = imfilter(I,H,'replicate');
subplot(2,2,3);
imshow(blurred); title('Blurred Image');

H = fspecial('unsharp');
sharpened = imfilter(I,H,'replicate');
subplot(2,2,4);
imshow(sharpened); title('Sharpened Image');
```

fspecial



Original Image



Motion Blurred Image



Blurred Image



Sharpened Image

Algorithms

fspecial creates Gaussian filters using

$$\begin{split} h_g(n_1,n_2) &= e^{-(n_1^2 + n_2^2)/(2\sigma^2)} \\ h(n_1,n_2) &= \frac{h_g(n_1,n_2)}{\sum_{n_1} \sum_{n_2} h_g} \end{split}$$

fspecial creates Laplacian filters using

$$\nabla^2 = \frac{\partial^2}{\partial x^2} + \frac{\partial^2}{\partial y^2}$$

$$\nabla^2 \approx \frac{4}{(\alpha+1)} \begin{bmatrix} \frac{\alpha}{4} & \frac{1-\alpha}{4} & \frac{\alpha}{4} \\ \frac{1-\alpha}{4} & -1 & \frac{1-\alpha}{4} \\ \frac{\alpha}{4} & \frac{1-\alpha}{4} & \frac{\alpha}{4} \end{bmatrix}$$

fspecial creates Laplacian of Gaussian (LoG) filters using

$$\begin{split} h_g(n_1,n_2) &= e^{-(n_1^2+n_2^2)/(2\sigma^2)} \\ h(n_1,n_2) &= \frac{(n_1^{\ 2}+n_2^{\ 2}-2\sigma^2)h_g(n_1,n_2)}{2\pi\sigma^6\sum_{n_1,n_2}h_g} \end{split}$$

fspecial creates averaging filters using

fspecial creates unsharp filters using

$$\frac{1}{(\alpha+1)} \begin{bmatrix} -\alpha & \alpha-1 & -\alpha \\ \alpha-1 & \alpha+5 & \alpha-1 \\ -\alpha & \alpha-1 & -\alpha \end{bmatrix}$$

See Also

conv2, edge, filter2, fsamp2, fwind1, fwind2, imfilter del2 in the MATLAB Function Reference

Design two-dimensional FIR filter using frequency transformation

Syntax

h = ftrans2(b,t)
h = ftrans2(b)

Description

h = ftrans2(b,t) produces the two-dimensional FIR filter h that corresponds to the one-dimensional FIR filter b using the transform t. (ftrans2 returns h as a computational molecule, which is the appropriate form to use with filter2.) b must be a one-dimensional, odd-length (Type I) FIR filter such as can be returned by fir1, fir2, or remez in the Signal Processing Toolbox. The transform matrix t contains coefficients that define the frequency transformation to use. If t is m-by-n and b has length Q, then h is size ((m-1)*(Q-1)/2+1)-by-((n-1)*(Q-1)/2+1).

h = ftrans2(b) uses the McClellan transform matrix t.

$$t = [1 \ 2 \ 1; \ 2 \ -4 \ 2; \ 1 \ 2 \ 1]/8;$$

Remarks

The transformation below defines the frequency response of the two-dimensional filter returned by ftrans2,

$$H(\omega_1, \omega_2) = B(\omega)|_{\cos \omega = T(\omega_1, \omega_2)}$$

where $B(\omega)$ is the Fourier transform of the one-dimensional filter b,

$$B(\omega) = \sum_{n=-N}^{N} b(n)e^{-j\omega n}$$

and $\textit{T}(\omega_1,\omega_2)$ is the Fourier transform of the transformation matrix t.

$$T(\omega_1, \omega_2) = \sum_{n_2} \sum_{n_1} t(n_1, n_2) e^{-j\omega_1 n_1} e^{-j\omega_2 n_2}$$

The returned filter h is the inverse Fourier transform of $H(\omega_1,\omega_2)$.


$$h(n_1, n_2) = \frac{1}{(2\pi)^2} \int_{-\pi}^{\pi} \int_{-\pi}^{\pi} H(\omega_1, \omega_2) e^{j\omega_1 n_1} e^{j\omega_2 n_2} d\omega_1 d\omega_2$$

Example

Use ftrans2 to design an approximately circularly symmetric two-dimensional bandpass filter with passband between 0.1 and 0.6 (normalized frequency, where 1.0 corresponds to half the sampling frequency, or π radians):


1 Since ftrans2 transforms a one-dimensional FIR filter to create a two-dimensional filter, first design a one-dimensional FIR bandpass filter using the Signal Processing Toolbox function remez.

```
colormap(jet(64))
b = remez(10,[0 0.05 0.15 0.55 0.65 1],[0 0 1 1 0 0]);
[H,w] = freqz(b,1,128,'whole');
plot(w/pi-1,fftshift(abs(H)))
```



2 Use ftrans2 with the default McClellan transformation to create the desired approximately circularly symmetric filter.

```
h = ftrans2(b);
freqz2(h)
```



See Also

conv2, filter2, fsamp2, fwind1, fwind2

Reference

[1] Lim, Jae S., Two-Dimensional Signal and Image Processing, Englewood Cliffs, NJ, Prentice Hall, 1990, pp. 218-237.

Design two-dimensional FIR filter using one-dimensional window method

Syntax

```
h = fwind1(Hd,win)
```

h = fwind1(Hd,win1,win2)
h = fwind1(f1,f2,Hd,...)

Description

fwind1 designs two-dimensional FIR filters using the window method. fwind1 uses a one-dimensional window specification to design a two-dimensional FIR filter based on the desired frequency response Hd. fwind1 works with one-dimensional windows only; use fwind2 to work with two-dimensional windows.

h = fwind1(Hd,win) designs a two-dimensional FIR filter h with frequency response Hd. (fwind1 returns h as a computational molecule, which is the appropriate form to use with filter2.) fwind1 uses the one-dimensional window win to form an approximately circularly symmetric two-dimensional window using Huang's method. You can specify win using windows from the Signal Processing Toolbox, such as boxcar, hamming, hanning, bartlett, blackman, kaiser, or chebwin. If length(win) is n, then h is n-by-n.

Hd is a matrix containing the desired frequency response sampled at equally spaced points between -1.0 and 1.0 (in normalized frequency, where 1.0 corresponds to half the sampling frequency, or π radians) along the x and y frequency axes. For accurate results, use frequency points returned by freqspace to create Hd. (See the entry for freqspace for more information.)

h = fwind1(Hd,win1,win2) uses the two one-dimensional windows win1 and win2 to create a separable two-dimensional window. If length(win1) is n and length(win2) is m, then h is m-by-n.

h = fwind1(f1,f2,Hd,...) lets you specify the desired frequency response Hd at arbitrary frequencies (f1 and f2) along the x- and y-axes. The frequency vectors f1 and f2 should be in the range -1.0 to 1.0, where 1.0 corresponds to half the sampling frequency, or π radians. The length of the windows controls the size of the resulting filter, as above.

Class Support


The input matrix Hd can be of class double or of any integer class. All other inputs to fwind1 must be of class double. All outputs are of class double.

Example

Use fwind1 to design an approximately circularly symmetric two-dimensional bandpass filter with passband between 0.1 and 0.5 (normalized frequency, where 1.0 corresponds to half the sampling frequency, or π radians):


1 Create a matrix Hd that contains the desired bandpass response. Use freqspace to create the frequency range vectors f1 and f2.

```
[f1,f2] = freqspace(21,'meshgrid');
Hd = ones(21);
r = sqrt(f1.^2 + f2.^2);
Hd((r<0.1)|(r>0.5)) = 0;
colormap(jet(64))
mesh(f1,f2,Hd)
```



2 Design the filter using a one-dimensional Hamming window.

```
h = fwind1(Hd,hamming(21));
freqz2(h)
```



Algorithm

fwind1 takes a one-dimensional window specification and forms an approximately circularly symmetric two-dimensional window using Huang's method,

$$w(n_1, n_2) = w(t)\Big|_{t = \sqrt{n_1^2 + n_2^2}}$$

where w(t) is the one-dimensional window and $w(n_1,n_2)$ is the resulting two-dimensional window.

Given two windows, fwind1 forms a separable two-dimensional window.

$$w(n_1, n_2) = w_1(n_1)w_2(n_2)$$

fwind1 calls fwind2 with Hd and the two-dimensional window. fwind2 computes h using an inverse Fourier transform and multiplication by the two-dimensional window.

$$\begin{split} h_d(n_1,n_2) &= \frac{1}{(2\pi)^2} \!\! \int_{-\pi}^{\pi} \!\! \int_{-\pi}^{\pi} \!\! H_d(\omega_1,\omega_2) e^{j\omega_1 n_1} e^{j\omega_2 n_2} d\omega_1 d\omega_2 \\ h(n_1,n_2) &= h_d(n_1,n_2) w(n_1,n_2) \end{split}$$

fwind 1

See Also conv2, filter2, fsamp2, freqspace, ftrans2, fwind2

Reference [1] Lim, Jae S., Two-Dimensional Signal and Image Processing, Englewood

Cliffs, NJ, Prentice Hall, 1990.

Design two-dimensional FIR filter using two-dimensional window method

Syntax

```
h = fwind2(Hd,win)
h = fwind2(f1,f2,Hd,win)
```

Description

Use fwind2 to design two-dimensional FIR filters using the window method. fwind2 uses a two-dimensional window specification to design a two-dimensional FIR filter based on the desired frequency response Hd. fwind2 works with two-dimensional windows; use fwind1 to work with one-dimensional windows.

h = fwind2(Hd,win) produces the two-dimensional FIR filter h using an inverse Fourier transform of the desired frequency response Hd and multiplication by the window win. Hd is a matrix containing the desired frequency response at equally spaced points in the Cartesian plane. fwind2 returns h as a computational molecule, which is the appropriate form to use with filter2. h is the same size as win.

For accurate results, use frequency points returned by freqspace to create Hd. (See the entry for freqspace for more information.)

h = fwind2(f1,f2,Hd,win) lets you specify the desired frequency response Hd at arbitrary frequencies (f1 and f2) along the x- and y-axes. The frequency vectors f1 and f2 should be in the range -1.0 to 1.0, where 1.0 corresponds to half the sampling frequency, or π radians. h is the same size as win.

Class Support


The input matrix Hd can be of class double or of any integer class. All other inputs to fwind2 must be of class double. All outputs are of class double.

Example

Use fwind2 to design an approximately circularly symmetric two-dimensional bandpass filter with passband between 0.1 and 0.5 (normalized frequency, where 1.0 corresponds to half the sampling frequency, or π radians):


1 Create a matrix Hd that contains the desired bandpass response. Use freqspace to create the frequency range vectors f1 and f2.

```
[f1,f2] = freqspace(21,'meshgrid');
Hd = ones(21);
r = sqrt(f1.^2 + f2.^2);
Hd((r<0.1)|(r>0.5)) = 0;
```




2 Create a two-dimensional Gaussian window using fspecial.

```
win = fspecial('gaussian',21,2);
win = win ./ max(win(:)); % Make the maximum window value be 1.
mesh(win)
```



3 Design the filter using the window from step 2.

```
h = fwind2(Hd,win);
freqz2(h)
```



Algorithm

fwind2 computes h using an inverse Fourier transform and multiplication by the two-dimensional window win.

$$\begin{split} h_d(n_1,n_2) &= \frac{1}{(2\pi)^2} \!\! \int_{-\pi}^{\pi} \!\! \int_{-\pi}^{\pi} \!\! H_d(\omega_1,\omega_2) e^{j\omega_1 n_1} \!\! e^{j\omega_2 n_2} d\omega_1 d\omega_2 \\ h(n_1,n_2) &= h_d(n_1,n_2) w(n_1,n_2) \end{split}$$

See Also

conv2, filter2, fsamp2, freqspace, ftrans2, fwind1

Reference

[1] Lim, Jae S., *Two-Dimensional Signal and Image Processing*, Englewood Cliffs, NJ, Prentice Hall, 1990, pp. 202-213.

getheight

Purpose Get height of structuring element

Syntax H = getheight(SE)

Description H = getheight(SE) returns an array the same size as getnhood(SE)

containing the height associated with each of the structuring element

neighbors. H is all zeros for a flat structuring element.

Class Support SE is a STREL object. H is of class double.

Example se = strel(ones(3,3),magic(3));

getheight(se)

See Also strel, getnhood

getimage

Purpose

Get image data from axes

Syntax

```
A = getimage(h)
[x,y,A] = getimage(h)
[...,A,flag] = getimage(h)
[...] = getimage
```

Description

A = getimage(h) returns the first image data contained in the Handle Graphics object h. h can be a figure, axes, or image. A is identical to the image CData; it contains the same values and is of the same class (uint8, uint16, double, or logical) as the image CData. If h is not an image or does not contain an image, A is empty.

[x,y,A] = getimage(h) returns the image XData in x and the YData in y. XData and YData are two-element vectors that indicate the range of the x-axis and y-axis.

[...,A,flag] = getimage(h) returns an integer flag that indicates the type of image h contains. This table summarizes the possible values for flag.

Flag	Type of Image
0	Not an image; A is returned as an empty matrix
1	Indexed image
2	Intensity image with values in standard range ([0,1] for single and double arrays, [0,255] for uint8 arrays, [0,65535] for uint16 arrays)
3	Intensity data, but not in standard range
4	RGB image
5	Binary image

[...] = getimage returns information for the current axes. It is equivalent to [...] = getimage(gca).

Class Support

The output array A is of the same class as the image CData. All other inputs and outputs are of class double.

Note

For int16 and single images, the image data returned by getimage is of class double, not int16 or single. The getimage function queries the image object's CData property for the image data and image objects store int16 and single image data as class double.

```
For an image of class int16,
   h = imshow(ones(10,'int16'));
   class(get(h,'CData'))

class returns double. Therefore, using the syntax,
   [img,flag] = getimage(h);
   class(img)

also returns an image of class double, with flag set to 3.

For an image of class single,
   h = imshow(ones(10,'single'));
   class(get(h,'CData'))

class returns double. Therefore, using the syntax,
   [img,flag] = getimage(h);
   class(img)
```

Example

After using imshow or imtool to display an image directly from a file, use getimage to get the image data into the workspace.

also returns an image of class double, with flag set to 2, because single and

```
imshow rice.png
I = getimage;
imtool cameraman.tif
I = getimage(imgca);
```

double share the same range.

See Also

imshow, imtool

getimagemodel

Purpose Retrieve image model object from image object

Syntax imgmodel = getimagemodel(himage)

Description imgmodel = getimagemodel(himage) returns the image model object

associated with himage. himage must be a handle to an image object or an array

of handles to image objects.

The return value imgmodel is an image model object. If himage is an array of

handles to image objects, imgmodel is an array of image models.

If himage does not have an associated image model object, getimagemodel

creates one.

Example h = imshow('bag.png');

imgmodel = getimagemodel(h);

See Also imagemodel

Purpose Select polyline with mouse

Syntax [x,y] = getline(fig)

[x,y] = getline(ax)

[x,y] = getline

[x,y] = getline(...,'closed')

Description

[x,y] = getline(fig) lets you select a polyline in the current axes of figure fig using the mouse. Coordinates of the polyline are returned in X and Y. Use normal button clicks to add points to the polyline. A shift-, right-, or double-click adds a final point and ends the polyline selection. Pressing **Return** or **Enter** ends the polyline selection without adding a final point. Pressing **Backspace** or **Delete** removes the previously selected point from the polyline.

[x,y] = getline(ax) lets you select a polyline in the axes specified by the handle ax.

[x,y] = getline is the same as [x,y] = getline(gcf).

[x,y] = getline(..., 'closed') animates and returns a closed polygon.

See Also

getpts, getrect

getneighbors

Purpose

Get structuring element neighbor locations and heights

Syntax

[offsets,heights] = getneighbors(SE)

Description

[offsets,heights] = getneighbors(SE) returns the relative locations and corresponding heights for each of the neighbors in the structuring element object SE.

offsets is a P-by-N array where P is the number of neighbors in the structuring element and N is the dimensionality of the structuring element. Each row of offsets contains the location of the corresponding neighbor, relative to the center of the structuring element.

heights is a P-element column vector containing the height of each structuring element neighbor.

Class Support

SE is a STREL object. The return values offsets and heights are arrays of double-precision values.

Example

```
se = strel([1 0 1],[5 0 -5])
[offsets,heights] = getneighbors(se)
se =
Nonflat STREL object containing 2 neighbors.
```

```
Neighborhood:
```

1 0 1

Height:

5 0 -5

offsets =

0 -1

0

heights =

5 -5

See Also

strel, getnhood, getheight

getnhood

Purpose Get structuring element neighborhood

Syntax nhood = getnhood(SE)

Description nhood = getnhood(SE) returns the neighborhood associated with the

structuring element SE.

Class Support SE is a STREL object. nhood is a logical array.

Example se = strel(eye(5));

nhood = getnhood(se)

See Also strel, getneighbors

getpts

Purpose

Select points with mouse

Syntax

[x,y] = getpts(fig)
[x,y] = getpts(ax)
[x,y] = getpts

Description

[x,y] = getpts(fig) lets you choose a set of points in the current axes of figure fig using the mouse. Coordinates of the selected points are returned in X and Y.

Use normal button clicks to add points. A shift-, right-, or double-click adds a final point and ends the selection. Pressing **Return** or **Enter** ends the selection without adding a final point. Pressing **Backspace** or **Delete** removes the previously selected point.

[x,y] = getpts(ax) lets you choose points in the axes specified by the handle ax.

[x,y] = getpts is the same as [x,y] = getpts(gcf).

See Also

getline, getrect

getrangefromclass

Purpose Get dynamic range of image based on its class

Syntax range = getrangefromclass(I)

Description range = getrangefromclass(I) returns the dynamic range of the image I,

based on its class type. range is a two-element vector specifying the dynamic

range.

Class Support I can be uint8, uint16, int16, logical, single, or double. range is of class

double.

Note For single and double data, getrangefromclass returns the range [0 1] to

be consistent with the way double and single images are interpreted in MATLAB. For integer data, getrangefromclass returns the range of the class.

For example, if the class is uint8, the dynamic range is [0 255].

Example This example reads in the 16-bit DICOM image and gets the range.

CT = dicomread('CT-MONO2-16-ankle.dcm');

r = getrangefromclass(CT)

See Also intmin, intmax

getrect

Purpose Select rectangle with mouse

Syntax rect = getrect(fig)

rect = getrect(ax)
rect = getrect(fig)

Description rect = getrect(fig) lets you select a rectangle in the current axes of figure

fig using the mouse. Coordinates of the rectangle are returned in X and Y.

Use the mouse to click and drag the desired rectangle. rect is a four-element vector with the form [xmin ymin width height]. To constrain the rectangle to

be a square, use a shift- or right-click to begin the drag.

rect = getrect(ax) lets you select a rectangle in the axes specified by the

handle ax.

See Also getline, getpts

Extract sequence of decomposed structuring elements

Syntax

SEQ = getsequence(SE)

Description

SEQ = getsequence(SE), where SE is a structuring element array, returns another structuring element array SEQ containing the individual structuring elements that form the decomposition of SE. SEQ is equivalent to SE, but the elements of SEQ have no decomposition.

Class Support

SE and SEQ are arrays of STREL objects.

Example

The strel function uses decomposition for square structuring elements larger than 3-by-3. Use getsequence to extract the decomposed structuring elements.

```
se = strel('square',5)
seq = getsequence(se)
se =
```

Flat STREL object containing 25 neighbors.

Decomposition: 2 STREL objects containing a total of 10 neighbors

Neighborhood:

1	1	1	1
1	1	1	1
1	1	1	1
1	1	1	1
1	1	1	1
	1 1 1	1 1 1 1 1 1	1 1 1 1 1 1 1 1 1

seq =

2x1 array of STREL objects

Use imdilate with the 'full' option to see that dilating sequentially with the decomposed structuring elements really does form a 5-by-5 square:

```
imdilate(1,seq,'full')
```

See Also

imdilate, imerode, strel

gray2ind

Purpose

Convert an intensity image to an indexed image

Syntax

```
[X,map] = gray2ind(I,n)
[X,map] = gray2ind(BW,n)
```

Description

gray2ind scales, then rounds, an intensity image to produce an equivalent indexed image.

[X,map] = gray2ind(I,n) converts the intensity image I to an indexed image X with colormap gray(n). If n is omitted, it defaults to 64.

[X,map] = gray2ind(BW,n) converts the binary image BW to an indexed image X with colormap gray(n). If n is omitted, it defaults to 2.

n must be an integer between 1 and 65536.

Class Support

The input image I can be logical, uint8, uint16, int16, single, or double and must be a real and nonsparse. The image I can have any dimension. The class of the output image X is uint8 if the colormap length is less than or equal to 256; otherwise it is uint16.

Example

Convert an intensity image into an indexed image and then view the result.

```
I = imread('cameraman.tif');
[X, map] = gray2ind(I, 16);
imshow(X, map);
```

See Also

grayslice, ind2gray, mat2gray

Gray-level co-occurrence matrix from an image

Syntax

```
glcm = graycomatrix(I)
glcms = graycomatrix(I,param1,val1,param2,val2,...)
[glcms,SI] = graycomatrix(...)
```

Description

glcms = graycomatrix(I) creates a gray-level co-occurrence matrix (GLCM) from image I. graycomatrix creates the GLCM by calculating how often a pizel with gray-level (grayscale intensity) value i occurs horizontally adjacent to a pixel with the value j. (You can specify other pixel spatial relationships using the 'Offsets' parameter — see Parameters.) Each element (i,j) in glcm specifies the number of times that the pixel with value i occurred horizontally adjacent to a pixel with value j.

Because the processing required to calculate a GLCM for the full dynamic range of an image is prohibitive, graycomatrix scales the values in I. If I is a binary image, graycomatrix scales the image to two levels. If I is an intensity image, graycomatrix scales it to eight levels. The number of gray-levels determines the size of the GLCM. You can specify the number of gray-levels in the GLCM using the 'NumLevels' parameter, and the way that graycomatrix scales the values using the 'GrayLimits' parameter — see Parameters.

The following figure shows how graycomatrix calculates the value of glcm(1,1). This element contains the value 1 because there is only one instance in the image where two, horizontally adjacent pixels have the values 1 and 1. As the figure shows, glcm(1,2) contains the value 2 because there are two instances where two, horizontally adjacent pixels have the values 1 and 2.

graycomatrix

								1	2	3	4	5	6	7	8
1	1	1	5	6	8	GLCM	1	1	2	0	0	1	0	0	0
	2	3	5	7	1		2	0	9 0	1	0	1	0	0	0
	4	5	7(1	2)	3	8	0	0	0	1	0	0	0
	8	5 (1	2	5		4	0	0	0	0	1	0	0	0
							5	1	0	0	0	0	1	2	0
							6	0	0	0	0	0	0	0	1
							7	2	0	0	0	0	0	0	0
							8	0	0	0	0	1	0	0	0

glcms = graycomatrix(I,param1,val1,param2,val2,...) returns one or more gray-level co-occurrence matrices, depending on the values of the optional parameter/value pairs. Parameter names can be abbreviated, and case does not matter.

Parameters

The following table lists these parameters in alphabetical order.

Parameter	Description	Default
'GrayLimits'	A two-element vector, [low high], that specifies how the grayscale values in I are linearly scaled into gray levels. Grayscale values less than or equal to low are scaled to 1. Grayscale values greater than or equal to high are scaled to NumLevels. If graylimits is set to [], graycomatrix uses the minimum and maximum grayscale values in the image as limits, [min(I(:)) max(I(:))].	Minimum and maximum specified by class, e.g. double [0 1] int16[-32768 32767]

Parameter	Description	Default
'NumLevels'	An integer specifying the number of gray-levels to use when scaling the grayscale values in I. For example, if NumLevels is 8, graycomatrix scales the values in I so they are integers between 1 and 8. The number of gray-levels determines the size of the gray-level co-occurrence matrix (glcm).	8 (numeric) 2 (binary)
'Offset'	A p-by-2 array of integers specifying the distance between the pixel of interest and its neighbor. Each row in the array is a two-element vector, [row_offset, col_offset], that specifies the relationship, or offset, of a pair of pixels. row_offset is the number of rows between the pixel-of-interest and its neighbor. col_offset is the number of columns between the pixel-of-interest and its neighbor. Because the offset is often expressed as an angle, the following table lists the offset values that specify common angles, given the pixel distance D. Angle Offset 0 [0 D] 45 [-D D] 90 [-D O] The figure illustrates the array: offset = [0 1; -1 1; -1 0; -1 -1] 90' [-1 0] 135' [-1 -1] 90' [-1 0] 135' [-1 -1]	[0 1]

graycomatrix

[glcm, SI] = graycomatrix(...) returns the scaled image, SI, used to calculate the gray-level co-occurrence matrix. The values in SI are between 1 and NumLevels.

Class Support

I can be numeric or logical but must be two-dimensional, real, and nonsparse. SI is a double matrix having the same size as I. glcms is a

'NumLevels'-by-'NumLevels'-by-P double array where P is the number of offsets in 'Offset'.

Notes

Another name for a gray-level co-occurrence matrix is a gray-level spatial dependence matrix.

graycomatrix ignores pixel pairs if either of the pixels contains a NaN.

graycomatrix replaces positive Infs with the value NumLevels and replaces negative Infs with the value 1.

graycomatrix ignores border pixels, if the corresponding neighbor pixel falls outside the image boundaries.

Example

Calculate the gray-level co-occurrence matrix and return the scaled version of the image, SI, used by graycomatrix to generate the GLCM.

```
I = [ 1 1 5 6 8 8; 2 3 5 7 0 2; 0 2 3 5 6 7];
[glcm,SI] = graycomatrix(I,'NumLevels',9,'G',[])
```

Calculate the gray-level co-occurrence matrix for the grayscale image, circuit.tif.

```
I = imread('circuit.tif');
glcm = graycomatrix(I,'Offset',[2 0]);
```

See Also

gravcoprops

Properties of a gray-level co-occurrence matrix

Syntax

stats = graycoprops(glcm, properties)

Description

stats = graycoprops(glcm, properties) calculates the statistics specified in properties from the gray-level co-occurrence matrix glcm. glcm is an m-by-n-by-p array of valid gray-level co-occurrence matrices. If glcm is an array of GLCMs, stats is an array of statistics for each glcm.

graycoprops normalizes the gray-level co-occurrence matrix (GLCM) so that the sum of its elements is equal to 1. Each element (r,c) in the normalized GLCM is the joint probability occurrence of pixel pairs with a defined spatial relationship having gray level values r and c in the image. graycoprops uses the normalized GLCM to calculate properties.

properties can be a comma-separated list of strings, a cell array containing strings, the string 'all', or a space separated string. The property names can be abbreviated and are not case sensitive.

Property	Description	Formula
'Contrast'	Returns a measure of the intensity contrast between a pixel and its neighbor over the whole image.	$\sum_{i,j}\!\left i-j\right ^2p(i,j)$
	Range = [0 (size(GLCM,1)-1)^2]	
	Contrast is 0 for a constant image.	
'Correlation'	Returns a measure of how correlated a pixel is to its neighbor over the whole image.	$\sum_{i=1}^{n} \frac{(i-\mu i)(j-\mu j) \vec{p}(i,j)}{\sigma_i \sigma_i}$
	Range = [-1 1]	i, j $\sigma_i \sigma_j$
	Correlation is 1 or -1 for a perfectly positively or negatively correlated image. Correlation is NaN for a constant image.	

Property	Description	Formula
'Energy'	Returns the sum of squared elements in the GLCM. Range = [0 1]	$\sum_{i,j} {p(i,j)}^2$
	Energy is 1 for a constant image.	
'Homogeneity'	Returns a value that measures the closeness of the distribution of elements in the GLCM to the GLCM diagonal.	$\sum_{i,\ j} \frac{p(i,j)}{1+ i-j }$
	Range = [0 1]	
	Homogeneity is 1 for a diagonal GLCM.	

stats is a structure with fields that are specified by properties. Each field contains a $1 \times p$ array, where p is the number of gray-level co-occurrence matrices in GLCM. For example, if GLCM is an $8 \times 8 \times 3$ array and properties is 'Energy', then stats is a structure containing the field Energy, which contains a 1×3 array.

Notes

Energy is also known as uniformity, uniformity of energy, and angular second moment.

Contrast is also known as variance and inertia.

Class Support

glcm can be logical or numeric, and it must contain real, non-negative, finite, integers. stats is a structure.

Example

```
GLCM = [0 1 2 3;1 1 2 3;1 0 2 0;0 0 0 3];
stats = graycoprops(GLCM)

I = imread('circuit.tif');
GLCM2 = graycomatrix(I,'Offset',[2 0;0 2]);
stats = graycoprops(GLCM2,{'contrast','homogeneity'})
```

See Also

graycomatrix

Create indexed image from intensity image using multilevel thresholding

Syntax

Description

X = grayslice(I,n) thresholds the intensity image I using threshold values

$$\frac{1}{n}, \frac{2}{n}, \dots, \frac{n-1}{n}$$
 , returning an indexed image in X.

X = grayslice(I,v) thresholds the intensity image I using the values of v, where v is a vector of values between 0 and 1, returning an indexed image in X.

You can view the thresholded image using imshow(X,map) with a colormap of appropriate length.


Class Support

The input image I can be of class uint8, uint16, int16, single, or double, and must be nonsparse. Note that the threshold values are always between 0 and 1, even if I is of class uint8 or uint16. In this case, each threshold value is multiplied by 255 or 65535 to determine the actual threshold to use.

The class of the output image X depends on the number of threshold values, as specified by n or length(v). If the number of threshold values is less than 256, then X is of class uint8, and the values in X range from 0 to n or length(v). If the number of threshold values is 256 or greater, X is of class double, and the values in X range from 1 to n+1 or length(v)+1.

Example

```
I = imread('snowflakes.png');
X = grayslice(I,16);
imshow(I)
figure, imshow(X,jet(16))
```



See Also

gray2ind

graythresh

Purpose

Compute global image threshold using Otsu's method

Syntax

```
level = graythresh(I)
[level EM] = graythresh(I)
```

Description

level = graythresh(I) computes a global threshold (level) that can be used
to convert an intensity image to a binary image with im2bw. level is a
normalized intensity value that lies in the range [0, 1].

The graythresh function uses Otsu's method, which chooses the threshold to minimize the intraclass variance of the black and white pixels.

Multidimensional arrays are converted automatically to 2-D arrays using reshape. The graythresh function ignores any nonzero imaginary part of I.

[level EM] = graythresh(I) returns the effectiveness metric, EM, as the second output argument. The effectiveness metric is a value in the range [0 1] that indicates the effectiveness of the thresholding of the input image. The lower bound is attainable only by images having a single gray level, and the upper bound is attainable only by two-valued images.

Class Support

The input image I can be of class uint8, uint16, int16, single,or double and it must be nonsparse. The return value level is a double scalar. The effectiveness metric EM is a double scalar.

Example

```
I = imread('coins.png');
level = graythresh(I);
BW = im2bw(I,level);
imshow(BW)
```

See Also

im2bw

Reference

Otsu, N., "A Threshold Selection Method from Gray-Level Histograms," *IEEE Transactions on Systems, Man, and Cybernetics*, Vol. 9, No. 1, 1979, pp. 62-66.

Enhance contrast using histogram equalization

Syntax

```
J = histeq(I,hgram)
J = histeq(I,n)
[J,T] = histeq(I,...)

newmap = histeq(X,map,hgram)
newmap = histeq(X,map)
[newmap,T] = histeq(X,...)
```

Description

histeq enhances the contrast of images by transforming the values in an intensity image, or the values in the colormap of an indexed image, so that the histogram of the output image approximately matches a specified histogram.

J = histeq(I,hgram) transforms the intensity image I so that the histogram of the output intensity image J with length(hgram) bins approximately matches hgram. The vector hgram should contain integer counts for equally spaced bins with intensity values in the appropriate range: [0, 1] for images of class double, [0, 255] for images of class uint8, and [0, 65535] for images of class uint16. histeq automatically scales hgram so that sum(hgram) = prod(size(I)). The histogram of J will better match hgram when length(hgram) is much smaller than the number of discrete levels in I.

J = histeq(I,n) transforms the intensity image I, returning in J an intensity image with n discrete gray levels. A roughly equal number of pixels is mapped to each of the n levels in J, so that the histogram of J is approximately flat. (The histogram of J is flatter when n is much smaller than the number of discrete levels in I.) The default value for n is 64.

[J,T] = histeq(I,...) returns the grayscale transformation that maps gray levels in the intensity image I to gray levels in J.

newmap = histeq(X,map,hgram) transforms the colormap associated with the indexed image X so that the histogram of the gray component of the indexed image (X,newmap) approximately matches hgram. The histeq function returns the transformed colormap in newmap. length(hgram) must be the same as size(map,1).

histeq

newmap = histeq(X, map) transforms the values in the colormap so that the histogram of the gray component of the indexed image X is approximately flat. It returns the transformed colormap in newmap.

[newmap,T] = histeq(X,...) returns the grayscale transformation T that maps the gray component of map to the gray component of newmap.

Class Support

For syntaxes that include an intensity image I as input, I can be of class uint8, uint16, int16, single, or double. The output image J has the same class as I.

For syntaxes that include an indexed image X as input, X can be of class uint8, single, or double; the output colormap is always of class double. The optional output T (the gray-level transform) is always of class double..

Example

Enhance the contrast of an intensity image using histogram equalization.


```
I = imread('tire.tif');
J = histeq(I);
imshow(I)
figure, imshow(J)
```






Display the resulting histograms.

```
imhist(I,64)
figure; imhist(J,64)
```





Algorithm

When you supply a desired histogram hgram , histeq chooses the grayscale transformation T to minimize

$$\left|c_1(T(k)) - c_0(k)\right|$$

where c_0 is the cumulative histogram of A, c_1 is the cumulative sum of hgram for all intensities k. This minimization is subject to the constraints that T must be monotonic and $c_1(T(a))$ cannot overshoot $c_0(a)$ by more than half the distance between the histogram counts at a. histeq uses this transformation to map the gray levels in X (or the colormap) to their new values.

$$b = T(a)$$

If you do not specify hgram, histeq creates a flat hgram,

$$hgram = ones(1,n)*prod(size(A))/n;$$

and then applies the previous algorithm.

See Also

brighten, imadjust, imhist

hough

Purpose

Hough transform

Syntax

[H, theta, rho] = hough(bw)

Description

[H, theta, rho] = hough(BW) computes the Standard Hough Transform (SHT) of the binary image BW. You can use the hough function to detect lines in an image. The function returns H, the Hough transform matrix. theta (in degrees) and rho are the arrays of rho and theta values over which the Hough transform matrix was generated.

[H, theta, rho] = hough(BW,param1,val1,param2,val2) specifies parameter/value pairs, listed in the following table. Parameter names can be abbreviated, and case does not matter.

Parameter	Description	
'ThetaResolution'	Real scalar value between 0 and 90, exclusive, the specifies the spacing (in degrees) of the Hough transform bins along the theta axis. Default: 1.	
'RhoResolution'	Real scalar value between 0 and norm(size(BW)), exclusive, that specifies the spacing of the Hough transform bins along the rho axis. Default: 1	

Notes

The hough function implements the Standard Hough Transform (SHT). The SHT uses the parametric representation of a line:

```
rho = x*cos(theta) + y*sin(theta)
```

The variable rho is the distance from the origin to the line along a vector perpendicular to the line. theta is the angle between the x-axis and this vector. The hough function generates a parameter space matrix whose rows and columns correspond to rho and theta values respectively. Peak values in this space represent potential lines in the input image.

The Hough transform matrix, H, is NRHO-by-NTHETA where NRHO = 2*ceil(norm(size(BW))/RhoResolution)-1, and NTHETA = 2*ceil(90/ThetaResolution). Theta angle values are in the range [-90, 90) degrees and rho values range from -DIAGONAL to DIAGONAL where DIAGONAL = RhoResolution*ceil(norm(size(BW))/RhoResolution). Note that

if 90/DTHETA is not an integer, the actual angle spacing will be 90/ceil(90/DTHETA).

Class Support

BW can be logical or numeric and it must be real, 2-D, and nonsparse.

Example

Compute and display the Hough transform of an image

```
RGB = imread('gantrycrane.png');
I = rgb2gray(RGB); % convert to intensity
BW = edge(I, 'canny'); % extract edges
[H,T,R] = hough(BW, 'RhoResolution',0.5, 'ThetaResolution',0.5);
% display the original image
subplot(2,1,1);
imshow(RGB);
title('gantrycrane.png');
% display the hough matrix
subplot(2,1,2);
imshow(imadjust(mat2gray(H)), 'XData',T, 'YData',R,...
      'InitialMagnification','fit');
title('Hough transform of gantrycrane.png');
xlabel('\theta'), ylabel('\rho');
axis on, axis normal, hold on;
colormap(hot);
```

See also

houghpeaks, houghlines

houghlines

Purpose

Extract line segments based on the Hough transform

Syntax

lines = houghlines(BW, theta, rho, peaks)

Description

lines = houghlines(BW,theta, rho, peaks) extracts line segments in the image BW associated with particular bins in a Hough transform. theta and rho are vectors returned by function hough. peaks is a matrix returned by the houghpeaks function that contains the row and column coordinates of the Hough transform bins to use in searching for line segments.

The houghlines function returns lines, a structure array whose length equals the number of merged line segments found. Each element of the structure array has these fields:

Field	Description
point1	Two element vector [X Y] specifying the coordinates of the end-point of the line segment
point2	Two element vector [X Y] specifying the coordinates of the end-point of the line segment
theta	Angle in degrees of the Hough transform bin
rho	rho axis position of the Hough transform bin

lines = houghlines(...,param1,val1,param2,val2) specifies parameter/value pairs, listed in the following table. Parameter names can be abbreviated, and case does not matter.

Parameter	Description
'FillGap'	Positive real scalar value that specifies the distance between two line segments associated with the same Hough transform bin. When the distance between the line segments is less the value specified, the houghlines function merges the line segments into a single line segment. Default: 20
'MinLength'	Positive real scalar value that specifies whether merged lines should be kept or discarded. Lines shorter than the value specified are discarded. Default: 40

Class Support

BW can be logical or numeric and it must be real, 2-D, and nonsparse.

Example

This example searches for line segments in an image and highlights the longest segment.

```
I = imread('circuit.tif');
rotI = imrotate(I,33,'crop');
BW = edge(rotI, 'canny');
[H,T,R] = hough(BW);
imshow(H,[],'XData',T,'YData',R,'InitialMagnification','fit');
xlabel('\theta'), ylabel('\rho');
axis on, axis normal, hold on;
P = houghpeaks(H, 5, 'threshold', ceil(0.3*max(H(:))));
x = T(P(:,2)); y = R(P(:,1));
plot(x,y,'s','color','white');
% Find lines and plot them
lines = houghlines(BW,T,R,P,'FillGap',5,'MinLength',7);
figure, imshow(rotI), hold on
\max len = 0;
for k = 1:length(lines)
  xy = [lines(k).point1; lines(k).point2];
```

houghlines

```
plot(xy(:,1),xy(:,2),'LineWidth',2,'Color','green');
% Plot beginnings and ends of lines
plot(xy(1,1),xy(1,2),'x','LineWidth',2,'Color','yellow');
plot(xy(2,1),xy(2,2),'x','LineWidth',2,'Color','red');
% Determine the endpoints of the longest line segment
len = norm(lines(k).point1 - lines(k).point2);
if ( len > max_len)
    max_len = len;
    xy_long = xy;
end
end
% highlight the longest line segment
plot(xy_long(:,1),xy_long(:,2),'LineWidth',2,'Color','cyan');
```

See also

hough, houghpeaks

Identify peaks in the Hough transform

Syntax

peaks = houghpeaks(H, numpeaks)

Description

peaks = houghpeaks(H, numpeaks) locates peaks in the Hough transform matrix, H, generated by the hough function. numpeaks specifies the maximum number of peaks to identify.

The function returns peaks, a Q-by-2 matrix, where Q can range from 0 to numpeaks. Q holds the row and column coordinates of the peaks. If numpeaks is omitted, it defaults to 1.

peaks = houghpeaks(...,param1,val1,param2,val2) specifies parameter/value pairs, listed in the following table. Parameter names can be abbreviated, and case does not matter.

Parameter	Description
'Threshold'	Nonnegative scalar value that specifies the threshold at which values of H are considered to be peaks. Threshold can vary from 0 to Inf. Default is 0.5*max(H(:)).
'NHoodSize'	Two-element vector of positive odd integers: [M N]. 'NHoodSize' specifies the size of the suppression neighborhood. This is the neighborhood around each peak that is set to zero after the peak is identified. Default: smallest odd values greater than or equal to size(H)/50.

Class Support

H is the output of the hough function. numpeaks is a positive integer scalar.

Example

Locate and display two peaks in the Hough transform of the rotated circuit.tif image.

```
I = imread('circuit.tif');
BW = edge(imrotate(I,50,'crop'),'canny');
[H,T,R] = hough(BW);
P = houghpeaks(H,2);
```

houghpeaks

```
imshow(H,[],'XData',T,'YData',R,'InitialMagnification','fit');
xlabel('\theta'), ylabel('\rho');
axis on, axis normal, hold on;
plot(T(P(:,2)),R(P(:,1)),'s','color','white');
```

See also

hough, houghlines

Convert hue-saturation-value (HSV) values to RGB color space

hsv2rgb is a function in MATLAB. To get help for this function, select **MATLAB Help** from the Help menu and view the online function reference page.

iccread

Purpose

Read ICC profile

Syntax

P = iccread(filename)

Description

P = iccread(filename) reads the International Color Consortium (ICC) color profile information from the file specified by filename. The file can be either an ICC profile file or a TIFF file containing an embedded ICC profile. To determine if a TIFF file contains an embedded ICC profile, use the imfinfo function to get information about the file and look for the ICCProfileOffset field.

iccread returns the profile information in the structure P, a 1-by-1 structure array whose fields contain the data structures (called tags) defined in the ICC specification. iccread can read profiles that conform with either Version 2 (ICC.1:2001-04) or Version 4 (ICC.1:2001-12) of the ICC specification. For more information about ICC profiles, visit the ICC web site, www.color.org.

ICC profiles provide color management systems with the information necessary to convert color data between native device color spaces and device independent color spaces, called the Profile Connection Space (PCS). You can use the profile as the source or destination profile with the makecform function to compute color space transformations.

The number of fields in P depends on the profile class (input, output, or display) and the choices made by the profile creator. iccread returns all the tags for a given profile, both public and private. Private tags and certain public tags are left as encoded uint8 data. The following table lists fields that are found in any profile structure generated by iccread, in the order they appear in the structure.

Field	Data Type	Description
Header	1-by-1 struct array	Profile header fields
TagTable	n-by-3 cell array	Profile tag table
Copyright	Text string	Profile copyright notice

Field	Data Type	Description
Description	1-by-1 struct array	The Plain field in this structure contains a text string describing the profile.
MediaWhitepoint	double array	XYZ tristimulus values of the device's media white point
PrivateTags	m-by-2 cell array	Contents of all the private tags or tags not defined in the ICC specifications. The tag signatures are in the first column, and the contents of the tags are in the second column. Note that iccread leaves the contents of these tags in unsigned 8-bit encoding
Filename	Text string	Name of the file containing the profile

Additionally, P might contain one or more of the following transforms:

- Three-component, matrix-based transform: A simple transform that is often used to transform between the RGB and XYZ color spaces. If this transform is present, P contains a field called MatTRC.
- N-component LUT-based transform: A transform that is used for transforming between color spaces that have a more complex relationship. This type of transform is found in any of the following fields in P:

AToB0	BToA0	Preview0	Gamut
AToB1	BToA1	Preview1	
AToB2	BToA2	Preview2	

Example

The example reads the ICC profile that describes a typical PC computer monitor.

```
P = iccread('sRGB.icm')
P =
```

```
Header: [1x1 struct]
         TagTable: {17x3 cell}
        Copyright: 'Copyright (c) 1999 Hewlett-Packard Company'
      Description: [1x1 struct]
 MediaWhitePoint: [0.9505 1 1.0891]
 MediaBlackPoint: [0 0 0]
   DeviceMfgDesc: [1x1 struct]
  DeviceModelDesc: [1x1 struct]
  ViewingCondDesc: [1x1 struct]
ViewingConditions: [1x1 struct]
        Luminance: [76.0365 80 87.1246]
      Measurement: [1x36 uint8]
      Technology: [115 105 103 32 0 0 0 0 67 82 84 32]
           MatTRC: [1x1 struct]
      PrivateTags: {}
        Filename: 'sRGB.icm'
```

The profile header provides general information about the profile such as its class, color space, and PCS. For example, to determine the source color space, view the ColorSpace field in the Header structure.

```
P.Header.ColorSpace
ans =
   RGB
```

See Also

applycform, iccwrite, isicc, makecform

Write ICC color profile to disk file

Syntax

P new = iccwrite(P, filename)

Description

P_new = iccwrite(P, filename) writes the International Color Consortium (ICC) color profile data in structure P to the file specified by filename.

P is a structure representing an ICC profile in the data format returned by iccread and used by makecform and applycform to compute color-space transformations. P must contain all the tags and fields required by the ICC profile specification. Some fields may be inconsistent, however, because of interactive changes to the structure. For instance, the tag table may not be correct because tags may have been added, deleted, or modified since the tag table was constructed. iccwrite makes any necessary corrections to the profile structure before writing it to the file and returns this corrected structure in P_new.

iccwrite can write the color profile data using either Version 2 (ICC.1:2001-04) or Version 4 (ICC.1:2001-12) of the ICC specification, depending on the value of the Version field in the file profile header. If any required fields are missing, iccwrite errors. For more information about ICC profiles, visit the ICC web site, www.color.org.

Note iccwrite does not perform automatic conversions from one version of the ICC specification to another. Such conversions have to be done manually, by adding fields or modifying fields. Use isicc to validate a profile.

Note

Portions of the implementation of iccwrite are derived from the RSA Data Security, Inc. MD5 Mesage-Digest Algorithm.

Example

This example reads a profile into the MATLAB workspace and then exports it in a new file.

```
P = iccread('monitor.icm');
pmon = iccwrite(P, 'monitor2.icm');
```

See Also

applycform, iccread, isicc, makecform

Compute two-dimensional inverse discrete cosine transform

Syntax

B = idct2(A)
B = idct2(A,m,n)
B = idct2(A,[m n])

Description

B = idct2(A) returns the two-dimensional inverse discrete cosine transform (DCT) of A.

B = idct2(A, m, n) or B = idct2(A, [m n]) pads A with 0's to size m-by-n before transforming. If [m n] < size(A), idct2 crops A before transforming.

For any A, idct2(dct2(A)) equals A to within roundoff error.

Class Support

The input matrix A can be of class double or of any numeric class. The output matrix B is of class double.

Algorithm

idct2 computes the two-dimensional inverse DCT using

$$A_{mn} = \sum_{p=0}^{M-1} \sum_{q=0}^{N-1} \alpha_p \alpha_q B_{pq} \cos \frac{\pi (2m+1)p}{2M} \cos \frac{\pi (2n+1)q}{2N}, \quad 0 \le m \le M-1$$

$$\alpha_p = \begin{cases} 1/\sqrt{M}, & p = 0 \\ \sqrt{2/M}, & 1 \le p \le M - 1 \end{cases} \qquad \alpha_q = \begin{cases} 1/\sqrt{N}, & q = 0 \\ \sqrt{2/N}, & 1 \le q \le N - 1 \end{cases}$$

Example

Create a DCT matrix.

```
RGB = imread('autumn.tif');
I = rgb2gray(RGB);
J = dct2(I);
imshow(log(abs(J)),[]), colormap(jet), colorbar
```

Set values less than magnitude 10 in the DCT matrix to zero, then reconstruct the image using the inverse DCT function idct2.

```
J(abs(J)<10) = 0;
K = idct2(J);
figure, imshow(I)</pre>
```

figure, imshow(K,[0 255])

See Also dct2, dctmtx, fft2, ifft2

References [1] Jain, A. K., Fundamentals of Digital Image Processing, Englewood Cliffs,

NJ, Prentice Hall, 1989, pp. 150-153.

 $[2] \ Pennebaker, W. \ B., and \ J. \ L. \ Mitchell, \ \textit{JPEG: Still Image Data Compression}$

Standard, New York, Van Nostrand Reinhold, 1993.

ifanbeam

Purpose

Compute inverse fan-beam transform

Syntax

```
I = ifanbeam(F,D)
I = ifambeam(...,param1,val1,param2,val2,...)
[I,H] = ifanbeam(...)
```

Description

I = ifanbeam(F,D) reconstructs the image I from projection data in the two-dimensional array F. Each column of F contains fan-beam projection data at one rotation angle. ifanbeam assumes that the center of rotation is the center point of the projections, which is defined as ceil(size(F,1)/2).

The fan-beam spread angles are assumed to be the same increments as the input rotation angles split equally on either side of zero. The input rotation angles are assumed to be stepped in equal increments to cover [0:359] degrees.

D is the distance from the fan-beam vertex to the center of rotation.

I = ifanbeam(...,param1,val1,param2,val2,...) specifies parameters that control various aspects of the ifanbeam reconstruction, described in the following table. Parameter names can be abbreviated, and case does not matter. Default values are in braces ($\{\}$).

Parameter	Description	
'FanCoverage'	String specifying the range through which the beams are rotated.	
	{'cycle'} — Rotate through the full range [0,360).	
	'minimal' — Rotate the minimum range necessary to represent the object.	
'FanRotationIncrement'	Positive real scalar specifying the increment of the rotation angle of the fan-beam projections, measured in degrees. See fanbeam for details.	
'FanSensorGeometry'	String specifying how sensors are positioned. See fanbeam for details.	

Parameter	Description	
'FanSensorSpacing'	Positive real scalar specifying the spacing of the fan-beam sensors. Interpretation of the value depends on the setting of 'FanSensorGeometry'. See fanbeam for details.	
'Filter'	String specifying the name of a filter. See iradon for details.	
'FrequencyScaling'	Scalar in the range (0,1] that modifies the filter by rescaling its frequency axis. See iradon for details.	
'Interpolation'	String specifying an interpolation method. See iradon for details.	
'OutputSize'	Positive scalar specifying the number of rows and columns in the reconstructed image.	
	If 'OutputSize' is not specified, ifanbeam determines the size automatically.	
	If you specify 'OutputSize', ifanbeam reconstructs a smaller or larger portion of the image, but does not change the scaling of the data.	
	Note: If the projections were calculated with the fanbeam function, the reconstructed image might not be the same size as the original image.	

[I,H] = ifanbeam(...) returns the frequency response of the filter in the vector H.

Notes

ifanbeam converts the fan-beam data to parallel beam projections and then uses the filtered back projection algorithm to perform the inverse Radon transform. The filter is designed directly in the frequency domain and then multiplied by the FFT of the projections. The projections are zero-padded to a power of 2 before filtering to prevent spatial domain aliasing and to speed up the FFT.

Class Support

The input arguments, F and D, can be double or single. All other numeric input arguments must be double. The output arguments are double.

Example

ph = phantom(128);

ifanbeam

```
d = 100;
F = fanbeam(ph,d);
I = ifanbeam(F,d,'FanSensorSpacing',0.5);
imshow(ph), figure, imshow(I);
```

See Also

fan2para, fanbeam, iradon, para2fan, phantom, radon

References

[1] Kak, A. C., and M. Slaney, Principles of Computerized Tomographic Imaging, New York, NY, IEEE Press, 1988.

Compute two-dimensional inverse fast Fourier transform

ifft2 is a function in MATLAB. To get help for this function, select **MATLAB Help** from the Help menu and view the online function reference pages.

ifftn

Purpose

Compute N-dimensional inverse fast Fourier transform

ifftn is a function in MATLAB. To get help for this function, select **MATLAB Help** from the Help menu and view the online function reference pages.

Convert an image to a binary image, based on threshold

Syntax

```
BW = im2bw(I,level)
BW = im2bw(X,map,level)
BW = im2bw(RGB,level)
```

Description

im2bw produces binary images from indexed, intensity, or RGB images. To do this, it converts the input image to grayscale format (if it is not already an intensity image), and then uses thresholding to convert this grayscale image to binary. The output binary image BW has values of 1 (white) for all pixels in the input image with luminance greater than level and 0 (black) for all other pixels. (Note that you specify level in the range [0,1], regardless of the class of the input image.)

BW = im2bw(I,level) converts the intensity image I to black and white.

BW = im2bw(X,map,level) converts the indexed image X with colormap map to black and white.

BW = im2bw(RGB,level) converts the RGB image RGB to black and white.

Note The function graythresh can be used to compute the level argument automatically.

Class Support

The input image can be of class uint8, uint16, single, int16, or double, and must be nonsparse. The output image BW is of class logical.

Example

```
load trees
BW = im2bw(X,map,0.4);
imshow(X,map), figure, imshow(BW)
```

im2bw







See Also

graythresh, ind2gray, rgb2gray

Rearrange image blocks into columns

Syntax

```
B = im2col(A,[m n],block_type)
B = im2col(A,[m n])
B = im2col(A,'indexed',...)
```

Description

B = im2col(A,[m n],block_type) rearranges image blocks into columns. block_type is a string that can have one of these values. The default value is enclosed in braces ({}).

Value	Description
'distinct'	Rearranges each distinct m-by-n block in the image A into a column of B. im2col pads A with 0's, if necessary, so its size is an integer multiple of m-by-n. If $A = [A11 \ A12; A21 \ A22]$, where each A_{ij} is m-by-n, then $B = [A11(:) \ A12(:) \ A21(:) \ A22(:)]$.
{'sliding'}	Converts each sliding m-by-n block of A into a column of B, with no zero padding. B has $m*n$ rows and contains as many columns as there are m-by-n neighborhoods of A. If the size of A is $[mm \ nn]$, then the size of B is $(m*n)$ -by- $((mm-m+1)*(nn-n+1))$.

For the sliding block case, each column of B contains the neighborhoods of A reshaped as nhood(:) where nhood is a matrix containing an m-by-n neighborhood of A. im2col orders the columns of B so that they can be reshaped to form a matrix in the normal way. For example, suppose you use a function, such as sum(B), that returns a scalar for each column of B. You can directly store the result in a matrix of size (mm-m+1)-by-(nn-n+1), using these calls.

```
B = im2col(A,[m n],'sliding');
C = reshape(sum(B),mm-m+1,nn-n+1);
```

B = im2col(A, 'indexed', ...) processes A as an indexed image, padding with 0's if the class of A is uint8, or 1's if the class of A is double.

Class Support

The input image A can be numeric or logical. The output matrix B is of the same class as the input image.

im2col

See Also

blkproc, col2im, colfilt, nlfilter

Convert image to double precision

Syntax

```
I2 = im2double(I)
RGB2 = im2double(RGB)
I = im2double(BW)
X2 = im2double(X,'indexed')
```

Description

im2double takes an image as input, and returns an image of class double. If the input image is of class double, the output image is identical to it. If the input image is not double, im2double returns the equivalent image of class double, rescaling or offsetting the data as necessary.

I2 = im2double(I) converts the intensity image I to double precision,
rescaling the data if necessary.

RGB2 = im2double(RGB) converts the truecolor image RGB to double precision, rescaling the data if necessary.

I = im2double(BW) converts the binary image BW to a double-precision intensity image.

X2 = im2double(X, 'indexed') converts the indexed image X to double precision, offsetting the data if necessary.

Class Support

Intensity and truecolor images can be uint8, uint16, double, logical, single, or int16. Indexed images can be uint8, uint16, double or logical. Binary input images must be logical. The output image is double.

Example

```
I1 = reshape(uint8(linspace(1,255,25)),[5 5])
I2 = im2double(I1)
```

See Also

 $\ \, \text{double, im2single, im2int16, im2uint8, im2uint16.}$

Convert image to 16-bit signed integers

Syntax

I2 = im2int16(I)
RGB2 = im2int16(RGB)
I = im2int16(BW)

Description

im2int16 takes an image as input and returns an image of class int16. If the input image is of class int16, the output image is identical to it. If the input image is not of class int16, im2int16 returns the equivalent image of class int16, rescaling or offsetting the data as necessary.

I2 = im2int16(I) converts the intensity image I to int16, rescaling the data if necessary.

RGB2 = im2int16(RGB) converts the truecolor image RGB to int16, rescaling the data if necessary.

I = im2int16(BW) converts the binary image BW to a int16 intensity image, changing false-valued elements to -32768 and true-valued elements to 32767.

Class Support

Intensity and truecolor images can be uint8, uint16, int16, single, double, or logical. Binary input images must be logical. The output image is int16.

Example

```
I = reshape(linspace(0,1,20),[5 4])
```

I2 = im2int16(I)

See Also

im2double, im2single, im2uint8, im2uint16, int16

im2java

Purpose Convert image to Java image

im2java is a MATLAB function. To get help for this function, select **MATLAB Help** from the Help menu and view the online function reference pages.

im2java2d

Purpose

Convert image to Java buffered image

Syntax

```
jimage = im2java2d(I)
jimage = im2java2d(X,MAP)
```

Description

jimage = im2java2d(I) converts the image I to an instance of the Java image class java.awt.image.BufferedImage. The image I can be an intensity (grayscale), RGB, or binary image.

jimage = im2java2d(X,MAP) converts the indexed image X with colormap MAP to an instance of the Java class java.awt.image.BufferedImage.

Note The im2java2d function works with the Java 2D API. The im2java function works with the Java Abstract Windowing Toolkit (AWT).

Class Support

Intensity, indexed, and RGB input images can be of class uint8, uint16, or double. Binary input images must be of class logical.

Example

This example reads an image into the MATLAB workspace and then uses im2java2d to convert it into an instance of the Java class java.awt.image.BufferedImage.

```
I = imread('moon.tif');
javaImage = im2java2d(I);
frame = javax.swing.JFrame;
icon = javax.swing.ImageIcon(javaImage);
label = javax.swing.JLabel(icon);
frame.getContentPane.add(label);
frame.pack
frame.show
```

Convert image to single precision

Syntax

I2 = im2single(I)
RGB2 = im2single(RGB)
I = im2single(BW)

X2 = im2single(X,'indexed')

Description

im2single takes an image as input and returns an image of class single. If the input image is of class single, the output image is identical to it. If the input image is not of class single, im2single returns the equivalent image of class single, rescaling or offsetting the data as necessary.

I2 = im2single(I) converts the intensity image I to single, rescaling the data if necessary.

RGB2 = im2single(RGB) converts the truecolor image RGB to single, rescaling the data if necessary.

I = im2single(BW) converts the binary image BW to a single-precision intensity image.

X2 = im2single(X, 'indexed') converts the indexed image X to single precision, offsetting the data if necessary.

Class Support

Intensity and truecolor images can be uint8, uint16, int16, single, double, or logical. Indexed images can be uint8, uint16, double or logical. Binary input images must be logical. The output image is single.

Example

```
I = reshape(uint8(linspace(1,255,25)),[5 5])
I2 = im2single(I)
```

See Also

im2double, im2int16, im2uint8, im2uint16, single

im2uint16

Purpose

Convert image to 16-bit unsigned integers

Syntax

```
I2 = im2uint16(I)
RGB2 = im2uint16(RGB)
I = im2uint16(BW)
X2 = im2uint16(X,'indexed')
```

Description

im2uint16 takes an image as input and returns an image of class uint16. If the input image is of class uint16, the output image is identical to it. If the input image is not of class uint15, im2uint16 returns the equivalent image of class uint16, rescaling or offsetting the data as necessary.

I2 = im2uint16(I) converts the intensity image I to uint16, rescaling the data if necessary.

RGB2 = im2uint16(RGB) converts the truecolor image RGB to uint16, rescaling the data if necessary.

I = im2uint16(BW) converts the binary image BW to a uint16 intensity image, changing 1-valued elements to 65535.

X2 = im2uint16(X, 'indexed') converts the indexed image X to uint16, offsetting the data if necessary. If X is of class double, $\max(X(:))$ must be 65536 or less.

Class Support

Intensity and truecolor images can be uint8, uint16, double, logical, single, or int16. Indexed images can be uint8, uint16, double, or logical. Binary input images must be logical. The output image is uint16.

Example

```
I = reshape(linspace(0,1,20),[5 4])
I2 = im2uint16(I)
```

See Also

 $\verb|im2u| \verb|int8|, \verb|double|, \verb|im2double|, \verb|u| \verb|int8|, \verb|u| \verb|int16|, \verb|imapprox|$

Convert image to 8-bit unsigned integers

Syntax

```
I2 = im2uint8(I)
RGB2 = im2uint8(RGB)
I = im2uint8(BW)
X2 = im2uint8(X,'indexed')
```

Description

im2uint8 takes an image as input and returns an image of class uint8. If the input image is of class uint8, the output image is identical to it. If the input image is not of class uint8, im2uint8 returns the equivalent image of class uint8, rescaling or offsetting the data as necessary.

I2 = im2uint8(I) converts the intensity image I to uint8, rescaling the data if necessary.

RGB2 = im2uint8(RGB) converts the truecolor image RGB to uint8, rescaling the data if necessary.

I = im2uint8(BW) converts the binary image BW to a uint8 intensity image, changing 1-valued elements to 255

X2 = im2uint8(X, 'indexed') converts the indexed image X to uint8, offsetting the data if necessary. Note that it is not always possible to convert an indexed image to uint8. If X is of class double, the maximum value of X must be 256 or less; if X is of class uint16, the maximum value of X must be 255 or less.

Class Support

Intensity and truecolor images can be uint8, uint16, double, logical, single, or int16. Indexed images can be uint8, uint16, double, or logical. Binary input images must be logical. The output image is uint8.

Example

```
I = reshape(uint8(linspace(0,255,255)),[5 5])
I2 = im2uint8(I)
```

See Also

im2double, im2int16, im2single, im2uint16, uint8

Compute absolute difference of two images

Syntax

Z = imabsdiff(X,Y)

Description

Z = imabsdiff(X,Y) subtracts each element in array Y from the corresponding element in array X and returns the absolute difference in the corresponding element of the output array Z. X and Y are real, nonsparse numeric arrays with the same class and size. Z has the same class and size as X and Y. If X and Y are integer arrays, elements in the output that exceed the range of the integer type are truncated.

If X and Y are double arrays, you can use the expression abs(X-Y) instead of this function.

Note On Intel architecture processors, imabsdiff can take advantage of the Intel Performance Primitives Library (IPPL), thus accelerating its execution time. IPPL is activated only if arrays X, Y, and Z are of class logical, uint8, or single, and are of the same class.

Examples

This example calculates the absolute difference between two uint8 arrays. Note that the absolute value prevents negative values from being rounded to zero in the result, as they are with imsubtract.

```
X = uint8([ 255 10 75; 44 225 100]);
Y = uint8([ 50 50 50; 50 50 50 ]);
Z = imabsdiff(X,Y)

Z =
    205    40    25
    6   175    50
```

Display the absolute difference between a filtered image and the original.

```
I = imread('cameraman.tif');
J = uint8(filter2(fspecial('gaussian'), I));
K = imabsdiff(I,J);
imshow(K,[]) % [] = scale data automatically
```

imabsdiff

See Also

imadd, imcomplement, imdivide, imlincomb, immultiply, imsubtract, ippl

Add two images, or add a constant to an image

Syntax

```
Z = imadd(X,Y)
```

Description

Z = imadd(X,Y) adds each element in array X with the corresponding element in array Y and returns the sum in the corresponding element of the output array Z. X and Y are real, nonsparse numeric arrays with the same size and class, or Y is a scalar double. Z has the same size and class as X, unless X is logical, in which case Z is double.

If X and Y are integer arrays, elements in the output that exceed the range of the integer type are truncated, and fractional values are rounded.

If X and Y are double arrays, you can use the expression X+Y instead of this function.

Note On Intel architecture processors, imadd can take advantage of the Intel Performance Primitives Library (IPPL), thus accelerating its execution time. IPPL is activated if arrays X, Y, and Z are of class logical, uint8, or single and are of the same class. IPPL is also activated if Y is a double scalar and arrays X and Z are uint8, int16, or single and are of the same class.

Examples

Add two uint8 arrays. Note the truncation that occurs when the values exceed 255.

```
X = uint8([ 255 0 75; 44 225 100]);
Y = uint8([ 50 50 50; 50 50 50 ]);
Z = imadd(X,Y)
Z =

255    50    125
94    255    150
```

Add two images together and specify an output class.

```
I = imread('rice.png');
J = imread('cameraman.tif');
K = imadd(I,J,'uint16');
imshow(K,[])
```

Add a constant to an image.

```
I = imread('rice.png');
J = imadd(I,50);
subplot(1,2,1), imshow(I)
subplot(1,2,2), imshow(J)
```

See Also

 $imabs diff, imcomplement, imdivide, imlincomb, immultiply, imsubtract, \\ippl$

imadjust

Purpose

Adjust image intensity values or colormap

Syntax

```
J = imadjust(I)
J = imadjust(I,[low_in; high_in],[low_out; high_out])
J = imadjust(...,gamma)
newmap = imadjust(map,[low_in high_in],[low_out high_out],gamma)
RGB2 = imadjust(RGB1,...)
```

Description

J = imadjust(I) maps the values in intensity image I to new values in J such that 1% of data is saturated at low and high intensities of I. This increases the contrast of the output image J. This syntax is equivalent to imadjust(I,stretchlim(I)).

J = imadjust(I,[low_in; high_in],[low_out; high_out]) maps the values in intensity image I to new values in J such that values between low_in and high_in map to values between low_out and high_out. Values below low_in and above high_in are clipped; that is, values below low_in map to low_out, and those above high_in map to high_out. You can use an empty matrix ([]) for [low_in high_in] or for [low_out high_out] to specify the default of [0 1].

J = imadjust(I,[low_in; high_in],[low_out; high_out],gamma) maps the values in intensity image I to new values in J, where gamma specifies the shape of the curve describing the relationship between the values in I and J. If gamma is less than 1, the mapping is weighted toward higher (brighter) output values. If gamma is greater than 1, the mapping is weighted toward lower (darker) output values. If you omit the argument, gamma defaults to 1 (linear mapping).

newmap = imadjust(map,[low_in; high_in],[low_out; high_out],gamma) transforms the colormap associated with an indexed image. If low_in, high_in, low_out, high_out, and gamma are scalars, then the same mapping applies to red, green, and blue components. Unique mappings for each color component are possible when

 ${\tt low_in} \ and \ {\tt high_in} \ are \ both \ 1-by-3 \ vectors.$

low_out and high_out are both 1-by-3 vectors, or gamma is a 1-by-3 vector.

The rescaled colormap newmap is the same size as map.

RGB2 = imadjust(RGB1,...) performs the adjustment on each image plane (red, green, and blue) of the RGB image RGB1. As with the colormap adjustment, you can apply unique mappings to each plane.

Note If high_out < low_out, the output image is reversed, as in a photographic negative.

Class Support

For syntax variations that include an input image (rather than a colormap), the input image can be of class uint8, uint16, int16, single, or double. The output image has the same class as the input image. For syntax variations that include a colormap, the input and output colormaps are of class double.

Example

Adjust a low-contrast grayscale image.

```
I = imread('pout.tif');
J = imadjust(I);
imshow(I), figure, imshow(J)
```





Adjust the grayscale image, specifying the contrast limits.


```
K = imadjust(I,[0.3 0.7],[]);
figure, imshow(K)
```

Adjust an RGB image.

```
RGB1 = imread('football.jpg');
```

imadjust

RGB2 = imadjust(RGB1,[.2 .3 0; .6 .7 1],[]);
imshow(RGB1), figure, imshow(RGB2)





See Also

brighten, histeq, stretchlim

Create Image Information tool

Syntax

imageinfo
imageinfo(h)

imageinfo(filename)
imageinfo(info)

imageinfo(himage,filename)
imageinfo(himage,info)
hfig = imageinfo(...)

Description

imageinfo creates an Image Information tool associated with the image in the current figure. The tool displays in a separate figure information about the basic attributes of the target image. imageinfo gets the image attributes by querying the image object's CData.

The following table lists the basic image information included in the Image Information tool display. Note that the tool contains either four or six fields, depending on the type of image.

Attribute Name	Value				
Width (columns)	Number of columns in the image				
Height (rows)	Number of rows in the image				
Class	Data type used by the image, such as uint8. Note: For single or int16 images, imageinfo returns a class value of double, because image objects convert CData of these classes to double.				
Image type	One of the image types identified by the Image Processing Toolbox: 'intensity', 'truecolor', 'binary', or 'indexed'.				

Minimum intensity	For intensity images, this value represents the lowest intensity value of any pixel. For indexed images, this value represents the lowest index value into a color map. Not included for 'binary' or 'truecolor' images.			
Maximum intensity	For intensity images, this value represents the highest intensity value of any pixel. For indexed images, this value represents the highest index value into a color map. Not included for 'binary' or 'truecolor' images.			

imageinfo(h) creates an Image Information tool associated with h, where h is a handle to a figure, axes, or image object.

imageinfo(filename) creates an Image Information tool containing image metadata from the graphics file filename. The image does not have to be displayed in a figure window. filename can be any file type that has been registered with an information function in the file formats registry, imformats, so its information can be read by imfinfo. filename can also be a DICOM file with information readable by dicominfo.

imageinfo(info) creates an Image Information tool containing the image metadata in the structure info. info is a structure returned by the functions imfinfo or dicominfo, or info can be a user-created structure.

imageinfo(himage,filename) creates an Image Information tool containing information about the basic attributes of the image specified by the handle himage and the image metadata from the graphics file filename.

imageinfo(himage,info) creates an Image Information tool containing information about the basic attributes of the image specified by the handle himage and the image metadata in the structure info.

 $\mbox{hfig=imageinfo}(\dots)$ returns a handle to the Image Information tool figure.

Example

imageinfo('peppers.png')

imageinfo

```
h = imshow('bag.png');
info = imfinfo('bag.png');
imageinfo(h,info);

imshow('trees.tif');
imageinfo;

See Also

dicominfo, imattributes, imfinfo, imformats, imtool
```

imagemodel

Purpose Access to properties of an image relevant to its display

Syntax imgmodel = imagemodel(himage)

Description imgmodel = imagemodel(himage) create an image model object associated

with the target image $\verb|himage|$ is a handle to an image object or an array

of handles to image objects.

 $\verb|image| model| object or, if \verb|himage| is an array of image|$

objects, an array of image model objects.

An image model object stores information about an image such as class, type,

display range, width, height, minimum intensity value and maximum

intensity value.

The image model object supports methods that you can use to access this information, get information about the pixels in an image, and perform special text formatting. The following lists these methods with a brief description.

Use methods (imagmodel) to get a list of image model methods.

Method	Description			
getClassType	Returns a string indicating the class of the image.			
	<pre>str = getClassType(imgmodel)</pre>			
	where imgmodel is a valid image model and str is a text string, such as 'uint8'.			
getDisplayRange	Returns a double array containing the minimum and maximum values of the display range for an intensity image. For image types other than intensity, the value returned is an empty array.			
	<pre>disp_range = getDisplayRange(imgmodel)</pre>			
	where imgmodel is a valid image model and disp_range is an array of doubles, such as [0 255].			

Method	Description
getImageHeight	Returns a double scalar containing the number of rows. height = getImageHeight(imgmodel)
	where imgmodel is a valid image model and height is a double scalar.
getImageType	Returns a text string indicating the image type.
	<pre>str = getImageType(imgmodel)</pre>
	where imgmodel is a valid image model and str is one of the text strings 'intensity', 'truecolor', 'binary', or 'indexed'.
getImageWidth	Returns a double scalar containing the number of columns.
	<pre>width = getImageWidth(imgmodel)</pre>
	where imgmodel is a valid image model and width is a double scalar.
getMinIntensity	Returns the minimum value in the image calculated as min(Image(:)). For an intensity image, the value returned is the minimum intensity. For an indexed image, the value returned is the minimum index. For any other image type, the value returned is an empty array.
	<pre>minval = getMinIntensity(imgmodel)</pre>
	where imgmodel is a valid image model and minval is a numeric value. The class of minval depends on the class of the target image.

imagemodel

Method	Description				
getMaxIntensity	Returns the maximum value in the image calculated as max(Image(:)). For an intensity image, the value returned is the maximum intensity. For an indexed image, the value returned is the maximum index. For any other image type, the value returned is an empty array. maxval = getMaxIntensity(imgmodel) where imgmodel is a valid image model and maxval is a				
	numeric value. The class of maxval depends on the class of the target image.				
getNumberFormatFcn	Returns the handle to a function that converts a numeric value into a string. fun = getNumberFormatFcn(imgmodel) where imgmodel is a valid image model. fun is a handle to a function that accepts a numeric value and returns the value as a text string. For example, you can use this function to convert the numeric return value of the getPixelValue method into a text string.				
	<pre>str = fun(getPixelValue(imgmodel,100,100))</pre>				
getPixelInfoString	Returns a text string containing value of the pixel at the location specified by row and column. str = getPixelInfoString(imgmodel,row,column)				
	where imgmodel is a valid image model and row and column are numeric scalar values. str is a character array. For example, for an RGB image, the method returns a text string such as '[66 35 60]'.				

Method	Description				
getPixelRegionFormatFcn	Returns a handle to a function that formats the value of a pixel into a text string. fun = getPixelRegionFormatFcn(imgmodel)				
	where imgmodel is a valid image model. fun is a handle to a function that accepts the location (row,column) of a pixel in the target image and returns the value of the pixel as a specially formatted text string. For example, when used with an RGB image, this function returns a text string of the form 'R:000 G:000 B:000' where 000 is the actual pixel value.				
	str = fun(100,100)				
getPixelValue	Returns the value of the pixel at the location specified by row and column as a numeric array.				
	<pre>val = getPixelValue(imgmodel,row, column)</pre>				
	where imgmodel is a valid image model and row and column are numeric scalar values. The class of val depends on the class of the target image.				
getDefaultPixelInfoString	Returns a text string indicating the type of information returned in a pixel information string. This string can be used in place of actual pixel information values.				
	<pre>str = getDefaultPixelInfoString(imgmodel)</pre>				
	where imgmodel is a valid image model. Depending on the image type, str can be the text string 'Intensity','[R G B]','BW', or ' <index> [R G B]'.</index>				

imagemodel

Method	Description				
getDefaultPixelRegionString	Returns a text string indicating the type of information displayed in the Pixel Region tool for each image type. This string can be used in place of actual pixel values.				
	<pre>str = getDefaultPixelRegionString(imgmodel)</pre>				
	where imgmodel is a valid image model. Depending on the image type, str can be the text string '000', 'R:000 G:000 B:000]', '0', or '<000> R:0.00 G:0.00 B:0.00'.				
getScreenPixelRGBValue	Returns the screen display value of the pixel at the location specified by ROW and COLUMN as a double array.				
	<pre>val = getScreenPixelRGBValue(imgmodel,row, col)</pre>				
	where imgmodel is a valid image model and row and col are numeric scalar values. val is an array of doubles, such as [0.2 0.5 0.3].				

Note

imagemodel works by querying the image object's CData. For a single or int16
image, the image object converts its CData to double. For example, in the case
of h = imshow(int16(ones(10))), class(get(h, 'CData')) returns 'double'.
Therefore, getClassType(imgmodel) returns 'double'.

Examples

This example creates an image model.

```
h = imshow('peppers.png');
im = imagemodel(h);

figure,subplot(1,2,1)
h1 = imshow('hestain.png');
subplot(1,2,2)
h2 = imshow('coins.png');
im = imagemodel([h1 h2]);
```

See Also

getimagemodel

Approximate indexed image by one with fewer colors

Syntax

```
[Y,newmap] = imapprox(X,map,n)
[Y,newmap] = imapprox(X,map,tol)
Y = imapprox(X,map,newmap)
[...] = imapprox(...,dither option)
```

Description

[Y,newmap] = imapprox(X,map,n) approximates the colors in the indexed image X and associated colormap map by using minimum variance quantization. imapprox returns indexed image Y with colormap newmap, which has at most n colors.

[Y,newmap] = imapprox(X,map,tol) approximates the colors in X and map through uniform quantization. newmap contains at most (floor(1/tol)+1)^3 colors. tol must be between 0 and 1.0.

Y = imapprox(X, map, newmap) approximates the colors in map by using colormap mapping to find the colors in newmap that best match the colors in map.

Y = imapprox(...,dither_option) enables or disables dithering. dither_option is a string that can have one of these values. The default value is enclosed in braces ({}).

Value	Description
{'dither'}	Dithers, if necessary, to achieve better color resolution at the expense of spatial resolution.
'nodither'	Maps each color in the original image to the closest color in the new map. No dithering is performed.

Class Support

The input image X can be of class uint8, uint16, or double. The output image Y is of class uint8 if the length of newmap is less than or equal to 256. If the length of newmap is greater than 256, Y is of class double.

Algorithm

 $imapprox\ uses\ rgb2ind\ to\ create\ a\ new\ colormap\ that\ uses\ fewer\ colors.$

Example

Approximate the indexed image trees.tif by another indexed image containing only 16 colors.

imapprox

```
[X, map] = imread('trees.tif');
[Y, newmap] = imapprox(X, map, 16);
imshow(Y, newmap)
```

See Also

cmunique, dither, rgb2ind

Return information about image attributes

Syntax

attrs = imattributes

attrs = imattributes(himage)
attrs = imattributes(imgmodel)

Description

attrs = imattributes returns information about an image in the current figure. If the current figure does not contain an image, imattributes returns an empty array.

attrs = imattributes(himage) returns information about the image specified by himage, a handle to an image object. imattributes gets the image attributes by querying the image object's CData.

imattributes returns image attribute information in attrs, a 4-by-2 or 6-by-2 cell array, depending on the image type. The first column of the cell array contains the name of the attribute as a text string. The second column contains the value of the attribute, also represented as a text string. The following table lists these attributes in the order they appear in the cell array.

Attribute Name	Value				
'Width (columns)'	Number of columns in the image				
'Height (rows)'	Number of rows in the image				
'Class'	Data type used by the image, such as uint8. Note: For single or int16 images, imattributes returns a 'Class' value of double, because image objects convert CData of these classes to double.				
'Image type'	One of the image types identified by the Image Processing Toolbox: 'intensity', 'truecolor', 'binary', or 'indexed'.				

'Minimum intensity'	For intensity images, this value represents the lowest intensity value of any pixel. For indexed images, this value represents the lowest index
	value into a color map. Not included for 'binary' or 'truecolor' images.
'Maximum intensity'	For intensity images, this value represents the highest intensity value of any pixel. For indexed images, this value represents the highest index value into a color map. Not included for 'binary' or 'truecolor' images.

attrs = imattributes(imgmodel) returns information about the image represented by the image model object, imgmodel.

Example

Retrieve the attributes of an intensity image.

```
h = imshow('liftingbody.png');
attrs = imattributes(h)
attrs =

'Width (columns)' '512'
'Height (rows)' '512'
'Class' 'uint8'
'Image type' 'intensity'
'Minimum intensity' '0'
'Maximum intensity' '255'
```

Creates an image model object for a truecolor image and then get the attributes from the image model object.

```
h = imshow('gantrycrane.png');
im = imagemodel(h);
attrs = imattributes(im)
attrs =

'Width (columns)' '400'
'Height (rows)' '264'
'Class' 'uint8'
'Image type' 'truecolor'
```

imattributes

See Also

imagemodel

imbothat

Purpose

Perform bottom-hat filtering

Syntax

IM2 = imbothat(IM,SE)
IM2 = imbothat(IM,NHOOD)

Description

IM2 = imbothat(IM,SE) performs morphological bottom-hat filtering on the grayscale or binary input image, IM, returning the filtered image, IM2. The argument SE is a structuring element returned by the stre1 function. SE must be a single structuring element object, not an array containing multiple structuring element objects.

IM2 = imbothat(IM,NHOOD) performs morphological bottom-hat filtering where NHOOD is an array of 0's and 1's that specifies the size and shape of the structuring element. This is equivalent to imbothat(IM,strel(NHOOD)).

Class Support

IM can be numeric or logical and must be nonsparse. The output image has the same class as the input image. If the input is binary (logical), then the structuring element must be flat.

Example

Top-hat filtering and bottom-hat filtering can be used together to enhance contrast in an image.

1 Read the image into the MATLAB workspace.

```
I = imread('pout.tif');
imshow(I)
```



2 Create disk-shaped structuring element, needed for morphological processing.

```
se = strel('disk',3);
```

3 Add the original image I to the top-hat filtered image, and then subtract the bottom-hat filtered image.

```
J = imsubtract(imadd(I,imtophat(I,se)), imbothat(I,se));
figure, imshow(J)
```



See Also imtophat, strel

imclearborder

Purpose

Suppress light structures connected to image border

Syntax

IM2 = imclearborder(IM)

IM2 = imclearborder(IM,CONN)

Description

IM2 = imclearborder(IM) suppresses structures that are lighter than their surroundings and that are connected to the image border. IM can be an intensity or binary image. The output image, IM2, is intensity or binary, respectively. The default connectivity is 8 for two dimensions, 26 for three dimensions, and conndef(ndims(BW), 'maximal') for higher dimensions.

Note For intensity images, imclearborder tends to reduce the overall intensity level in addition to suppressing border structures.

IM2 = imclearborder(IM,CONN) specifies the desired connectivity. CONN can have any of the following scalar values.

Value	Meaning				
Two-dime	Two-dimensional connectivities				
4	4-connected neighborhood				
8 8-connected neighborhood					
Three-dim	Three-dimensional connectivities				
6	6-connected neighborhood				
18 18-connected neighborhood 26 26-connected neighborhood					

Connectivity can also be defined in a more general way for any dimension by using for CONN a 3-by-3-by- ... -by-3 matrix of 0's and 1's. The 1-valued elements define neighborhood locations relative to the center element of CONN. Note that CONN must be symmetric about its center element.

Note A pixel on the edge of the input image might not be considered to be a border pixel if a nondefault connectivity is specified. For example, if conn = [0 0 0; 1 1 1; 0 0 0], elements on the first and last row are not considered to be border pixels because, according to that connectivity definition, they are not connected to the region outside the image.

Class Support

IM can be a numeric or logical array of any dimension, and it must be nonsparse and real. IM2 has the same class as IM.

Example

The following examples use this simple binary image to illustrate the effect of imclearborder when you specify different connectivities.

В١	N =								
	0	0	0	0	0	0	0	0	0
	0	0	0	0	0	0	0	0	0
	0	0	0	0	0	0	0	0	0
	1	0	0	1	1	1	0	0	0
	0	1	0	1	1	1	0	0	0
	0	0	0	1	1	1	0	0	0
	0	0	0	0	0	0	0	0	0
	0	0	0	0	0	0	0	0	0
	0	0	0	0	0	0	0	0	0

Using a 4-connected neighborhood, the pixel at (5,2) is not considered connected to the border pixel (4,1), so it is not cleared.

BWc1	=	imclearb	order	(BW,4)					
BWc1	=								
	0	0	0	0	0	0	0	0	0
	0	0	0	0	0	0	0	0	0
	0	0	0	0	0	0	0	0	0
	0	0	0	1	1	1	0	0	0
	0	1	0	1	1	1	0	0	0
	0	0	0	1	1	1	0	0	0
	0	0	0	0	0	0	0	0	0
	0	0	0	0	0	0	0	0	0
	0	0	0	0	0	0	0	0	0

imclearborder

Using an 8-connected neighborhood, pixel (5,2) is considered connected to pixel (4,1) so both are cleared.

BWc2 = imclearborder(BW,8)

BWc2 =

0	0	0	0	0	0	0	0	0
0	0	0	0	0	0	0	0	0
0	0	0	0	0	0	0	0	0
0	0	0	1	1	1	0	0	0
0	0	0	1	1	1	0	0	0
0	0	0	1	1	1	0	0	0
0	0	0	0	0	0	0	0	0
0	0	0	0	0	0	0	0	0
0	0	0	0	0	0	0	0	0

Algorithm

imclearborder uses morphological reconstruction where

- Mask image is the input image.
- Marker image is zero everywhere except along the border, where it equals the mask image.

See Also

conndef

Reference

[1] Soille, P., Morphological Image Analysis: Principles and Applications, Springer, 1999, pp. 164-165.

Close an image

Syntax

IM2 = imclose(IM,SE)
IM2 = imclose(IM,NHOOD)

Description

IM2 = imclose(IM,SE) performs morphological closing on the grayscale or binary image IM, returning the closed image, IM2. The structuring element, SE, must be a single structuring element object, as opposed to an array of objects.

IM2 = imclose(IM,NHOOD) performs closing with the structuring element strel(NHOOD), where NHOOD is an array of 0's and 1's that specifies the structuring element neighborhood.


Class Support

IM can be any numeric or logical class and any dimension, and must be nonsparse. If IM is logical, then SE must be flat. IM2 has the same class as IM.

Example

This example uses imclose to join the circles in the image together by filling in the gaps between them and by smoothening their outer edges.

1 Read the image into the MATLAB workspace and view it.
 originalBW = imread('circles.png');
 imshow(originalBW);




2 Create a disk-shaped structuring element. Use a disk structuring element to preserve the circular nature of the object. Specify a radius of 10 pixels so that the largest gap gets filled.

```
se = strel('disk',10);
```

imclose

3 Perform a morphological close operation on the image.

```
closeBW = imclose(originalBW,se);
figure, imshow(closeBW)
```



See Also

imdilate, imerode, imopen, strel

Complement image

Syntax

IM2 = imcomplement(IM)

Description

IM2 = imcomplement (IM) computes the complement of the image IM. IM can be a binary, intensity, or RGB image. IM2 has the same class and size as IM.

In the complement of a binary image, zeros become ones and ones become zeros; black and white are reversed. In the complement of an intensity or RGB image, each pixel value is subtracted from the maximum pixel value supported by the class (or 1.0 for double-precision images) and the difference is used as the pixel value in the output image. In the output image, dark areas become lighter and light areas become darker.

If IM is an intensity or RGB image of class double, you can use the expression 1-IM instead of this function. If IM is a binary image, you can use the expression ~IM instead of this function.

Examples

Create the complement of a uint8 array.


Reverse black and white in a binary image.


```
bw = imread('text.png');
bw2 = imcomplement(bw);
subplot(1,2,1),imshow(bw)
subplot(1,2,2),imshow(bw2)
```

Create the complement of an intensity image.

```
I = imread('glass.png');
J = imcomplement(I);
imshow(I), figure, imshow(J)
```

imcomplement





Original Image

Complement Image

See Also

 $\verb|imabsdiff|, \verb|imadd|, \verb|imdivide|, \verb|imlincomb|, \verb|immultiply|, \verb|imsubtract||$

Create a contour plot of image data

Syntax

```
imcontour(I)
imcontour(I,n)
imcontour(I,v)
imcontour(x,y,...)
imcontour(...,LineSpec)
[C,h] = imcontour(...)
```

Description

imcontour(I) draws a contour plot of the intensity image I, automatically setting up the axes so their orientation and aspect ratio match the image.

imcontour(I,n) draws a contour plot of the intensity image I, automatically setting up the axes so their orientation and aspect ratio match the image. n is the number of equally spaced contour levels in the plot; if you omit the argument, the number of levels and the values of the levels are chosen automatically.

imcontour (I, v) draws a contour plot of I with contour lines at the data values specified in vector v. The number of contour levels is equal to length(v).

imcontour(x, y, ...) uses the vectors x and y to specify the x- and y-axis limits.

imcontour(...,LineSpec) draws the contours using the line type and color specified by LineSpec. Marker symbols are ignored.

[C,h] = imcontour(...) returns the contour matrix C and a vector of handles to the objects in the plot. (The objects are actually patches, and the lines are the edges of the patches.) You can use the clabel function with the contour matrix C to add contour labels to the plot.


Class Support

The input image can be of class uint8, uint16, int16, single, double, or logical.

Example

```
I = imread('circuit.tif');
imcontour(I,3)
```

imcontour



See Also

clabel, contour, LineSpec in the MATLAB Function Reference

Adjust contrast tool

Syntax

imcontrast
imcontrast(h)
h = imcontrast(h)

Description

imcontrast creates an Adjust Contrast tool associated with the intensity image in the current figure, called the target image. If the figure contains multiple images, the target image is the first intensity image in the figure (last created). imcontrast creates the tool in a separate figure window.

The Adjust Contrast tool is an interactive contrast and brightness adjustment tool. When an image contains more gray values than can be displayed at one time, you can use this tool to choose which values to display. For images with limited contrast, you can use this tool to stretch the image histogram to fill the dynamic range.

Note The Adjust Contrast tool only works with intensity (grayscale) images. imcontrast adjusts the CLim property of the axes containing the image and does not work with RGB images. Changing the CLim of indexed images may produce unexpected results.

imcontrast(h) creates the Adjust Contrast tool associated with the image specified by the handle h. h can be a handle to a figure, axes, uipanel, or image object. If h is a handle to a figure or axes, imcontrast associates the tool with the first image found in the first figure or axes.

h=imcontrast(...) returns a handle to the Adjust Contrast tool figure.

When there are more possible gray values in the image than can be displayed at one time, this tool helps you interactively pick which values to display. For images with limited contrast this tool also helps you stretch the image histogram to fill the dynamic range.

Remarks

The Adjust Contrast tool presents a scaled histogram of pixel values (overly represented pixel values are truncated for clarity). Dragging on the left red bar in the histogram display changes the minimum value. The minimum value

imcontrast

(and any value less than the minimum) displays as black. Dragging on the right red bar in the histogram changes the maximum value. The maximum value (and any value greater than the maximum) displays as white. Values in between the red bars display as intermediate shades of gray.

Together the minimum and maximum values create a "window". Stretching the window reduces contrast. Shrinking the window increases contrast. Changing the center of the window changes the brightness of the image. It is possible to manually enter the minimum, maximum, width, and center values for the window. Changing one value automatically updates the other values and the image.

Window/Level Interactivity

Clicking and dragging the mouse within the target image interactively changes the image's window values. Dragging the mouse horizontally from left to right changes the window width (i.e., contrast). Dragging the mouse vertically up and down changes the window center (i.e., brightness). Holding down the CTRL key when clicking accelerates changes. Holding down the SHIFT key slows the rate of change. Keys must be pressed before clicking and dragging.

Example

```
imshow('pout.tif')
imcontrast(gca)
```

See Also

imadjust, imtool, stretchlim

Crop an image

Syntax

```
I2 = imcrop(I)
X2 = imcrop(X,map)
RGB2 = imcrop(RGB)

I2 = imcrop(I,rect)
X2 = imcrop(X,map,rect)
RGB2 = imcrop(RGB,rect)

[...] = imcrop(x,y,...)
[A,rect] = imcrop(...)
[x,y,A,rect] = imcrop(...)
```

Description

imcrop crops an image to a specified rectangle. In the syntaxes below, imcrop displays the input image and waits for you to specify the crop rectangle with the mouse.

```
I2 = imcrop(I)
X2 = imcrop(X,map)
RGB2 = imcrop(RGB)
```

If you omit the input arguments, imcrop operates on the image in the current axes.

To specify the rectangle,

- For a single-button mouse, press the mouse button and drag to define the crop rectangle. Finish by releasing the mouse button.
- For a two- or three-button mouse, press the left mouse button and drag to define the crop rectangle. Finish by releasing the mouse button.

If you hold down the **Shift** key while dragging, or if you press the right mouse button on a two- or three-button mouse, imcrop constrains the bounding rectangle to be a square.

When you release the mouse button, imcrop returns the cropped image in the supplied output argument. If you do not supply an output argument, imcrop displays the output image in a new figure.

You can also specify the cropping rectangle noninteractively, using these syntaxes

```
I2 = imcrop(I,rect)
X2 = imcrop(X,map,rect)
RGB2 = imcrop(RGB,rect)
```

rect is a four-element vector with the form [xmin ymin width height]; these values are specified in spatial coordinates.

To specify a nondefault spatial coordinate system for the input image, precede the other input arguments with two, two-element vectors specifying the XData and YData. For example:

```
[\ldots] = imcrop(x,y,\ldots)
```

If you supply additional output arguments, imcrop returns information about the selected rectangle and the coordinate system of the input image. For example:

```
[A,rect] = imcrop(...)
[x,y,A,rect] = imcrop(...)
```

A is the output image. x and y are the XData and YData of the input image.

Class Support

If you specify RECT as an input argument, the input image can be logical or numeric, and must be real and nonsparse. RECT is of class double.

If you do not specify RECT as an input argument, imcrop calls imshow imshow expects I to be logical, uint8, uint16, int16, single, or double. RGB can be uint8, int16, uint16, single, or double. X can be logical, uint8, uint16, single, or double. The input image must be real and nonsparse.

If you specify an image as an input argument, the output image has the same class as the input image.


If you don't specify an image as an input argument, i.e., you call imcrop with no input arguments, the output image has the same class as the input image except for the int16 or single. The output image is double if the input image is int16 or single.

Remarks

Because rect is specified in terms of spatial coordinates, the width and height elements of rect do not always correspond exactly with the size of the output image. For example, suppose rect is [20 20 40 30], using the default spatial coordinate system. The upper-left corner of the specified rectangle is the center of the pixel (20,20) and the lower-right corner is the center of the pixel (50,60). The resulting output image is 31-by-41, not 30-by-40, because the output image includes all pixels in the input image that are completely *or partially* enclosed by the rectangle.

Example

```
I = imread('circuit.tif');
I2 = imcrop(I,[75 68 130 112]);
imshow(I), figure, imshow(I2)
```





See Also

zoom

imdilate

Purpose

Dilate image

Syntax

IM2 = imdilate(IM,SE)
IM2 = imdilate(IM,NHOOD)

IM2 = imdilate(IM,SE,PACKOPT)
IM2 = imdilate(...,PADOPT)

Description

IM2 = imdilate(IM, SE) dilates the grayscale, binary, or packed binary image IM, returning the dilated image, IM2. The argument SE is a structuring element object, or array of structuring element objects, returned by the strel function.

If IM is logical and the structuring element is flat, imdilate performs binary dilation; otherwise, it performs grayscale dilation. If SE is an array of structuring element objects, imdilate performs multiple dilations of the input image, using each structuring element in SE in succession.

IM2 = imdilate(IM,NHOOD) dilates the image IM, where NHOOD is a matrix of
O's and 1's that specifies the structuring element neighborhood. This is
equivalent to the syntax imdilate(IM, strel(NHOOD)). The imdilate function
determines the center element of the neighborhood by
floor((size(NHOOD)+1)/2).

IM2 = imdilate(IM,SE,PACKOPT) or imdilate(IM,NHOOD,PACKOPT) specifies whether IM is a packed binary image. PACKOPT can have either of the following values. Default value is enclosed in braces ({}).

Value	Description
'ispacked'	IM is treated as a packed binary image as produced by bwpack. IM must be a 2-D uint32 array and SE must be a flat 2-D structuring element. If the value of PACKOPT is 'ispacked', PADOPT must be 'same'.
{'notpacked'}	IM is treated as a normal array.

IM2 = imdilate(..., PADOPT) specifies the size of the output image. PADOPT can have either of the following values. Default value is enclosed in braces ({}).

Value	Description	
{'same'}	Make the output image the same size as the input image. If the value of PACKOPT is 'ispacked', PADOPT must be 'same'.	
'full'	Compute the full dilation.	

PADOPT is analogous to the optional SHAPE argument to the conv2 and filter2 functions.

Class Support


IM can be logical or numeric and must be real and nonsparse. It can have any dimension. If IM is logical, SE must be flat. The output has the same class as the input. If the input is packed binary, then the output is also packed binary.

Examples

This example dilates a binary image with a vertical line structuring element.

```
bw = imread('text.png');
se = strel('line',11,90);
bw2 = imdilate(bw,se);
imshow(bw), title('Original')
figure, imshow(bw2), title('Dilated')
```





This example dilates a grayscale image with a rolling ball structuring element.

```
I = imread('cameraman.tif');
```

```
se = strel('ball',5,5);
I2 = imdilate(I,se);
imshow(I), title('Original')
figure, imshow(I2), title('Dilated')
```





To determine the domain of the composition of two flat structuring elements, dilate the scalar value 1 with both structuring elements in sequence, using the 'full' option.

Algorithm

imdilate automatically takes advantage of the decomposition of a structuring element object (if it exists). Also, when performing binary dilation with a structuring element object that has a decomposition, imdilate automatically uses binary image packing to speed up the dilation.

Dilation using bit packing is described in [2].

See Also

bwpack, bwunpack, conv2, filter2, imclose, imerode, imopen, strel

References

[1] Haralick, R.M., and L. G. Shapiro, *Computer and Robot Vision*, Vol. I, Addison-Wesley, 1992, pp. 158-205.

[2] van den Boomgaard and van Balen, "Image Transforms Using Bitmapped Binary Images," Computer Vision, Graphics, and Image Processing: Graphical Models and Image Processing, Vol. 54, No. 3, May, 1992, pp. 254-258.

imdisplayrange

Purpose

Display range tool

Syntax

imdisplayrange


imdisplayrange(h)

imdisplayrange(hparent,himage)
hpanel=imdisplayrange(...)

Description

imdisplayrange creates a display range tool in the current figure. The display range tool shows the display range of the intensity image or images in the figure.

The tool is a uipanel object, positioned in the lower-right corner of the figure. It contains the text string "Display range:" followed by the display range values for the image, as shown in the following figure.



For an indexed, truecolor, or binary image, the display range is not applicable and is set to empty ([]).

imdisplayrange(h) Creates a display range tool in the figure specified by the handle h, where h is a handle to an image, axes, uipanel, or figure object. Axes, uipanel, or figure objects must contain at least one image object.

imdisplayrange (hparent, himage) creates a display range tool in hparent that shows the display range of himage. himage is a handle to an image or an array of image handles. hparent is a handle to the figure or uipanel object that contains the display range tool.

hpanel=imdisplayrange (...) returns a handle to the display range tool uipanel.

Note

The display range tool can work with multiple images in a figure. When the cursor is not in an image in a figure, the display range tool displays the text string, [black white].

Examples

Display an image and include the Display Range tool.

im display range

```
imshow('bag.png');
imdisplayrange;
```

Import a 16-bit DICOM image and display it with its default range and scaled range in the same figure.

```
dcm = dicomread('CT-MONO2-16-ankle.dcm');
subplot(1,2,1), imshow(dcm);
subplot(1,2,2), imshow(dcm,[]);
imdisplayrange;
```

See also

imtool

Divide one image into another, or divide an image by a constant

Syntax

```
Z = imdivide(X,Y)
```

Description

Z = imdivide(X,Y) divides each element in the array X by the corresponding element in array Y and returns the result in the corresponding element of the output array Z. X and Y are real, nonsparse numeric arrays with the same size and class, or Y can be a scalar double. Z has the same size and class as X and Y.

If X is an integer array, elements in the output that exceed the range of integer type are truncated, and fractional values are rounded.

If X and Y are double arrays, you can use the expression X. /Y instead of this function.

Note On Intel architecture processors, imdivide can take advantage of the Intel Performance Primitives Library (IPPL), thus accelerating its execution time. IPPL is activated only if arrays X and Y are of class uint8, int16, or single and are of the same size and class.

Example

Divide two uint8 arrays. Note that fractional values greater than or equal to 0.5 are rounded up to the nearest integer.

Estimate and divide out the background of the rice image.

```
I = imread('rice.png');
background = imopen(I,strel('disk',15));
Ip = imdivide(I,background);
imshow(Ip,[])
```

Divide an image by a constant factor.

imdivide

```
I = imread('rice.png');
J = imdivide(I,2);
subplot(1,2,1), imshow(I)
subplot(1,2,2), imshow(J)
```

See Also

imabsdiff, imadd, imcomplement, imlincomb, immultiply, imsubtract, ippl

imerode

Purpose

Erode image

Syntax

IM2 = imerode(IM,SE)

IM2 = imerode(IM, NHOOD)

IM2 = imerode(IM,SE,PACKOPT,M)

IM2 = imerode(...,PADOPT)

Description

IM2 = imerode(IM,SE) erodes the grayscale, binary, or packed binary image IM, returning the eroded image IM2. The argument SE is a structuring element object or array of structuring element objects returned by the strel function.

If IM is logical and the structuring element is flat, imerode performs binary dilation; otherwise it performs grayscale erosion. If SE is an array of structuring element objects, imerode performs multiple erosions of the input image, using each structuring element in SE in succession.

IM2 = imerode(IM,NHOOD) erodes the image IM, where NHOOD is an array of 0's and 1's that specifies the structuring element neighborhood. This is equivalent to the syntax imerode(IM,strel(NHOOD)). The imerode function determines the center element of the neighborhood by floor((size(NHOOD)+1)/2)

IM2 = imerode(IM,SE,PACKOPT,M) or imerode(IM,NHOOD,PACKOPT,M) specifies whether IM is a packed binary image and, if it is, provides the row dimension M of the original unpacked image. PACKOPT can have either of the following values. Default value is enclosed in braces ({}).

Value	Description
'ispacked'	IM is treated as a packed binary image as produced by bwpack. IM must be a 2-D uint32 array and SE must be a flat 2-D structuring element.
{'notpacked'}	IM is treated as a normal array.

If PACKOPT is 'ispacked', you must specify a value for M.

IM2 = imerode(..., PADOPT) specifies the size of the output image. PADOPT can have either of the following values. Default value is enclosed in braces ($\{\}$).

Value	Description	
{'same'}	Make the output image the same size as the input image. If the value of PACKOPT is 'ispacked', PADOPT must be 'same'.	
'full'	Compute the full erosion.	

PADOPT is analogous to the SHAPE input to the CONV2 and FILTER2 functions.


Class Support


IM can be numeric or logical and it can be of any dimension. If IM is logical and the structuring element is flat, the output image is logical; otherwise the output image has the same class as the input. If the input is packed binary, then the output is also packed binary.

Examples

This example erodes a binary image with a disk structuring element.

```
originalBW = imread('circles.png');
se = strel('disk',11);
erodedBW = imerode(originalBW,se);
imshow(originalBW), figure, imshow(erodedBW)
```





This example erodes a grayscale image with a rolling ball.

```
I = imread('cameraman.tif');
se = strel('ball',5,5);
```

imerode

```
I2 = imerode(I,se);
imshow(I), title('Original')
figure, imshow(I2), title('Eroded')
```





Algorithm Notes

imerode automatically takes advantage of the decomposition of a structuring element object (if a decomposition exists). Also, when performing binary dilation with a structuring element object that has a decomposition, imerode automatically uses binary image packing to speed up the dilation.

Erosion using bit packing is described in [2].

See Also

bwpack, bwunpack, conv2, filter2, imclose, imdilate, imopen, strel

References

[1] Haralick, Robert M., and Linda G. Shapiro, *Computer and Robot Vision*, Vol. I, Addison-Wesley, 1992, pp. 158-205.

[2] van den Boomgaard and van Balen, "Image Transforms Using Bitmapped Binary Images," Computer Vision, Graphics, and Image Processing: Graphical Models and Image Processing, Vol. 54, No. 3, May, 1992, pp. 254-258.

Extended-maxima transform

Syntax

BW = imextendedmax(I,H)

BW = imextendedmax(I,H,CONN)

Description

BW = imextendedmax(I,H) computes the extended-maxima transform, which is the regional maxima of the H-maxima transform. H is a nonnegative scalar.

Regional maxima are connected components of pixels with the same intensity value, t, whose external boundary pixels all have a value less than t.

By default, imextendedmax uses 8-connected neighborhoods for 2-D images and 26-connected neighborhoods for 3-D images. For higher dimensions, imextendedmax uses conndef(ndims(I), 'maximal').

BW = imextendedmax(I,H,CONN) computes the extended-maxima transform, where CONN specifies the connectivity. CONN can have any of the following scalar values.

Value	Meaning	
Two-dimensional connectivities		
4	4-connected neighborhood	
8	8-connected neighborhood	
Three-dimensional connectivities		
6	6-connected neighborhood	
18	18-connected neighborhood	
26	26-connected neighborhood	

Connectivity can be defined in a more general way for any dimension by using for CONN a 3-by-3-by- ...-by-3 matrix of 0's and 1's. The 1-valued elements define neighborhood locations relative to the center element of CONN. Note that CONN must be symmetric about its center element.


Class Support

 ${\tt I}$ can be of any nonsparse numeric class and any dimension. BW has the same size as ${\tt I}$ and is always logical.

imextendedmax

Example

I = imread('glass.png');
BW = imextendedmax(I,80);
imshow(I), figure, imshow(BW)





Original Image

Extended Maxima Image

See Also

conndef, imextendedmin, imreconstruct

Reference

[1] Soille, P., Morphological Image Analysis: Principles and Applications, Springer-Verlag, 1999, pp. 170-171.

Extended-minima transform

Syntax

BW = imextendedmin(I,h)

BW = imextendedmin(I,h,CONN)

Description

BW = imextendedmin(I,h) computes the extended-minima transform, which is the regional minima of the H-minima transform. h is a nonnegative scalar.

Regional minima are connected components of pixels with the same intensity value, t, whose external boundary pixels all have a value greater than t.

By default, imextendedmin uses 8-connected neighborhoods for 2-D images, and 26-connected neighborhoods for 3-D images. For higher dimensions, imextendedmin uses conndef(ndims(I), 'maximal').

BW = imextendedmin(I,h,CONN) computes the extended-minima transform, where CONN specifies the connectivity. CONN can have any of the following scalar values.

Value	Meaning	
Two-dime	Two-dimensional connectivities	
4	4-connected neighborhood	
8	8-connected neighborhood	
Three-dimensional connectivities		
6	6-connected neighborhood	
18	18-connected neighborhood	
26	26-connected neighborhood	

Connectivity can be defined in a more general way for any dimension by using for CONN a 3-by-3-by-...-by-3 matrix of 0's and 1's. The 1-valued elements define neighborhood locations relative to the center element of CONN. Note that CONN must be symmetric about its center element.


Class Support

I can be of any nonsparse numeric class and any dimension. BW has the same size as I and is always logical.

imextendedmin

Example

I = imread('glass.png');
BW = imextendedmin(I,50);
imshow(I), figure, imshow(BW)





Original Image

Extended Minima Image

See Also

conndef, imextendedmax, imreconstruct

Reference

[1] Soille, P., Morphological Image Analysis: Principles and Applications, Springer-Verlag, 1999, pp. 170-171.

Fill image regions

Syntax

```
BW2 = imfill(BW,locations)
BW2 = imfill(BW,'holes')
I2 = imfill(I)

BW2 = imfill(BW)
[BW2 locations] = imfill(BW)

BW2 = imfill(BW,locations,CONN)
BW2 = imfill(BW,CONN,'holes')
I2 = imfill(I,CONN)
```

Description

BW2 = imfill(BW,locations) performs a flood-fill operation on background pixels of the binary image BW, starting from the points specified in locations. If locations is a P-by-1 vector, it contains the linear indices of the starting locations. If locations is a P-by-ndims(BW) matrix, each row contains the array indices of one of the starting locations.

BW2 = imfill(BW, 'holes') fills holes in the binary image BW. A hole is a set of background pixels that cannot be reached by filling in the background from the edge of the image.

I2 = imfill(I) fills holes in the intensity image I. In this case, a hole is an area of dark pixels surrounded by lighter pixels.

Interactive Use

BW2 = imfill(BW) displays the binary image BW on the screen and lets you select the starting locations using the mouse. Click the mouse button to add points. Press **Backspace** or **Delete** to remove the previously selected point. A shift-click, right-click, or double-click selects a final point and then starts the fill operation; pressing **Return** finishes the selection without adding a point.

Note imfill supports interactive use only for 2-D images.

[BW2,locations] = imfill(BW) lets you select the starting points selected using the mouse, returning the locations of points in locations. locations is a vector of linear indices into the input image.

Specifying Connectivity

By default, imfill uses 4-connected background neighbors for 2-D inputs and 6-connected background neighbors for 3-D inputs. For higher dimensions the default background connectivity is determined by using conndef(NUM_DIMS, 'minimal'). You can override the default connectivity with these syntaxes:

```
BW2 = imfill(BW,LOCATIONS,CONN)
BW2 = imfill(BW,CONN,'holes')
I2 = imfill(I,CONN)
```

To override the default connectivity and interactively specify the starting locations, use this syntax:

```
BW2 = imfill(BW, 0, CONN)
```

CONN can have any of the following scalar values.

Value	Meaning	
Two-dime	Two-dimensional connectivities	
4	4-connected neighborhood	
8	8-connected neighborhood	
Three-dimensional connectivities		
6	6-connected neighborhood	
18	18-connected neighborhood	
26	26-connected neighborhood	

Connectivity can be defined in a more general way for any dimension by using for CONN a 3-by-3-by- ... -by-3 matrix of 0's and 1's. The 1-valued elements define neighborhood locations relative to the center element of CONN. Note that CONN must be symmetric about its center element.

Class Support

The input image can be numeric or logical, and it must be real and nonsparse. It can have any dimension. The output image has the same class as the input image.


Examples


Fill in the background of a binary image from a specified starting location.

BW2 = imfill(BW1,[3 3],8)

Fill in the holes of a binary image.

```
BW4 = im2bw(imread('coins.png'));
BW5 = imfill(BW4,'holes');
imshow(BW4), figure, imshow(BW5)
```





Original Image


Filled Image

Fill in the holes of an intensity image.

```
I = imread('tire.tif');
I2 = imfill(I,'holes');
figure, imshow(I), figure, imshow(I2)
```

imfill





Original Image

Filled Image

Algorithm

imfill uses an algorithm based on morphological reconstruction [1].

See Also

bwselect, imreconstruct, roifill

Reference

[1] Soille, P., Morphological Image Analysis: Principles and Applications, Springer-Verlag, 1999, pp. 173-174.

Multidimensional image filtering

Syntax

B = imfilter(A, H)

B = imfilter(A,H,option1,option2,...)

Description

B = imfilter(A,H) filters the multidimensional array A with the multidimensional filter H. The array A can be a nonsparse numeric array of any class and dimension. The result B has the same size and class as A.

Each element of the output B is computed using double-precision floating point. If A is an integer array, then output elements that exceed the range of the integer type are truncated, and fractional values are rounded.

B = imfilter(A,H,option1,option2,...) performs multidimensional filtering according to the specified options. Option arguments can have the following values.

Boundary Options

Option	Description
X	Input array values outside the bounds of the array are implicitly assumed to have the value X. When no boundary option is specified, imfilter uses X = 0.
'symmetric'	Input array values outside the bounds of the array are computed by mirror-reflecting the array across the array border.
'replicate'	Input array values outside the bounds of the array are assumed to equal the nearest array border value.
'circular'	Input array values outside the bounds of the array are computed by implicitly assuming the input array is periodic.

Output Size Options

Option	Description	
'same'	The output array is the same size as the input array. This is the default behavior when no output size options are specified.	
'full'	The output array is the full filtered result, and so is larger than the input array.	

Correlation and Convolution Options

Option	Description
'corr'	imfilter performs multidimensional filtering using correlation, which is the same way that filter2 performs filtering. When no correlation or convolution option is specified, imfilter uses correlation.
'conv'	imfilter performs multidimensional filtering using convolution.

N-D convolution is related to N-D correlation by a reflection of the filter matrix.

Note On Intel architecture processors, imfilter can take advantage of the Intel Performance Primitives Library (IPPL), thus accelerating its execution time. IPPL is activated only if A and H are both two-dimensional and A is of class uint8, int16, or single.

Examples

Read a color image into the workspace and view it.

```
originalRGB = imread('peppers.png');
imshow(originalRGB)
```

Create a filter, h, that can be used to approximate linear camera motion.

```
h = fspecial('motion', 50, 45);
```

Apply the filter, using imfilter, to the image rgb to create a new image, rgb2.

```
filteredRGB = imfilter(originalRGB, h);
figure, imshow(filteredRGB)
```

Note that imfilter is more memory efficient than some other filtering operations in that it outputs an array of the same data type as the input image array. In this example, the output is an array of uint8.

whos rgb2	2		
Name	Size	Bytes	Class
h	37x37	10952	double array
rgb	384x512x3	589824	uint8 array
rgb2	384x512x3	589824	uint8 array

This example specifies the replicate boundary option.

```
boundaryReplicateRGB = imfilter(originalRGB, h, 'replicate');
figure, imshow(boundaryReplicateRGB)
```

See Also

conv2, convn, filter2, fspecial, ippl

imfinfo

Purpose

Information about graphics file

imfinfo is a MATLAB function. To get help for this function, select **MATLAB Help** from the Help menu and view the online function reference pages.

Get handle to most recent current axis containing an image

Syntax

```
hax = imgca
hax = imgca(hfig)
```

Description

hax = imgca returns the handle of the of the most recent current axis that contains an image. The current axis may be in a regular figure window or in an Image Tool window.

If no figure contains an axis that contains an image, imgca creates a new axis.

hax = imgca(hfig) returns the handle to the current axis that contains an image in the specified figure (it need not be the current figure).

Note

imgca can be useful in getting the handle to the Image Tool axis. Because the Image Tool turns graphics object handle visibility off, you cannot retrieve a handle to the tool figure using gca.

Example

Label the coins in the image, compute their centroids, and superimpose the centroid locations on the image. View the results using imtool and imgca.

```
I = imread('coins.png');
figure, imshow(I)

bw = im2bw(I, graythresh(getimage));
figure, imshow(bw)

bw2 = imfill(bw, 'holes');
L = bwlabel(bw2);
s = regionprops(L, 'centroid');
centroids = cat(1, s.Centroid);
```

Display original image I and superimpose centroids.

```
imtool(I)
hold(imgca,'on')
plot(imgca,centroids(:,1), centroids(:,2), 'r*')
hold(imgca,'off')
```

See also

```
qca, qcf, imqcf
```

imgcf

Purpose Get handle to most recent current figure containing an image

Syntax hfig = imgcf

Description hfig = imgcf returns the handle of the most recent current figure that

contains an image. The figure may be a regular figure window that contains at

least one image or an Image Tool window.

If none of the figures currently open contains an image, imgcf creates a new

figure.

Note imgcf can be useful in getting the handle to the Image Tool figure window.

Because the Image Tool turns graphics object handle visibility off, you cannot

retrieve a handle to the tool figure using gcf.

Example imtool rice.png

cmap = copper(256);

set(imgcf, 'Colormap',cmap)

See also gca, gcf, imgca

imgetfile

Purpose Displays Open Image dialog box

Syntax [filename, user_canceled] = imgetfile

Description [filename, user canceled] = imgetfile displays the Open Image dialog

box for the user to fill in, and returns the full path to the file selected in filename. If the user presses the **Cancel** button, user_canceled will be TRUE.

Otherwise, user canceled will be FALSE.

The Open Image dialog box is modal; it blocks the MATLAB command line until the user responds. The file types listed in the dialog are all formats listed

in imformats plus DICOM.

See Also imformats, imtool, uigetfile

imhandles

Purpose Get all image handles within a handle

Syntax himage = imhandles(H)

Description himage = imhandles(H) takes a graphics handle h as an input and returns all

of the image handles whose ancestor is h. h can be an array of valid figure, axes,

uipanel, or image handles.

himage is an array of image handles.

Note imhandles errors if the image objects in himage do not have the same figure as

their parent.

Examples This example returns the handle to the image object in the current figure.

```
figure, imshow('moon.tif');
himage = imhandles(gcf)
```

This example displays two images in a figure and uses imhandles to get handles to both of the image objects in the figure.

```
subplot(1,2,1), imshow('autumn.tif');
subplot(1,2,2), imshow('glass.png');
himages = imhandles(gca)
```

See Also imgca, imgcf

Display histogram of image data

Syntax

```
imhist(I,n)
imhist(X,map)
[counts,x] = imhist(...)
```

Description

imhist(I) displays a histogram for the intensity image I above a grayscale colorbar. The number of bins in the histogram is specified by the image type. If I is a grayscale image, imhist uses a default value of 256 bins. If I is a binary image, imhist uses 2 bins.

imhist (I,n) displays a histogram where n specifies the number of bins used in the histogram. n also specifies the length of the colorbar. If I is a binary image, n can only have the value 2.

imhist (X, map) displays a histogram for the indexed image X. This histogram shows the distribution of pixel values above a colorbar of the colormap map. The colormap must be at least as long as the largest index in X. The histogram has one bin for each entry in the colormap.

[counts,x] = imhist(...) returns the histogram counts in counts and the bin locations in x so that stem(x,counts) shows the histogram. For indexed images, it returns the histogram counts for each colormap entry; the length of counts is the same as the length of the colormap.

Note For intensity images, the n bins of the histogram are each half-open intervals of width A/(n-1). In particular, for intensity images that are not int16, the p th bin is the half-open

interval $A(p-1.5)/(n-1) \le x < A(p-0.5)/(n-1)$, where x is the intensity value. For int16 intensity images, the p th bin is the half-open interval $A(p-1.5)/(n-1) - 32768 \le x < A(p-0.5)/(n-1) - 32768$, where x is the intensity value. The scale factor A depends on the image class. A is 1 if the intensity image is double or single, A is 255 if the intensity image is uint8, and A is 65535 if the intensity image is uint16 or int16.


imhist

Class Support

An input intensity image can be of class uint8, uint16, int16, single, double, or logical. An input indexed image can be of class uint8, uint16, single, double, or logical.

Example

I = imread('pout.tif');
imhist(I)



See Also

histeq

hist in the MATLAB Function Reference

H-maxima transform

Syntax

I2 = imhmax(I,h)

I2 = imhmax(I,h,CONN)

Description

I2 = imhmax(I,h) suppresses all maxima in the intensity image I whose height is less than h, where h is a scalar.

Regional maxima are connected components of pixels with the same intensity value, t, whose external boundary pixels all have a value less than t.

By default, imhmax uses 8-connected neighborhoods for 2-D images, and 26-connected neighborhoods for 3-D images. For higher dimensions, imhmax uses conndef(ndims(I), 'maximal').

I2 = imhmax(I,h,CONN) computes the H-maxima transform, where CONN specifies the connectivity. CONN can have any of the following scalar values.

Value	Meaning	
Two-dime	Two-dimensional connectivities	
4	4-connected neighborhood	
8	8-connected neighborhood	
Three-dimensional connectivities		
6	6-connected neighborhood	
18	18-connected neighborhood	
26	26-connected neighborhood	

Connectivity can be defined in a more general way for any dimension by using for CONN a 3-by-3-by- ...-by-3 matrix of 0's and 1's. The 1-valued elements define neighborhood locations relative to the center element of CONN. Note that CONN must be symmetric about its center element.

Class Support

I can be of any nonsparse numeric class and any dimension. I2 has the same size and class as I.

imhmax

```
a = zeros(10,10);
a(2:4,2:4) = 3; % maxima 3 higher than surround
a(6:8,6:8) = 8; % maxima 8 higher than surround
b = imhmax(a,4); % only the maxima higher than 4 survive.

See Also

Conndef, imhmin, imreconstruct

Reference
[1] Soille, P., Morphological Image Analysis: Principles and Applications,
Springer-Verlag, 1999, pp. 170-171.
```

H-minima transform

Syntax

I2 = imhmin(I,h)

I2 = imhmin(I,h,CONN)

Description

I2 = imhmin(I,h) suppresses all minima in the intensity image I whose depth is less than h, where h is a scalar.

Regional minima are connected components of pixels with a constant intensity value, and whose external boundary pixels all have a higher value.

By default, imhmin uses 8-connected neighborhoods for 2-D images, and 26-connected neighborhoods for 3-D images. For higher dimensions, imhmin uses conndef(ndims(I), 'maximal').

I2 = imhmin(I,h,CONN) computes the H-minima transform, where CONN specifies the connectivity. CONN can have any of the following scalar values.

Value	Meaning	
Two-dimensional connectivities		
4	4-connected neighborhood	
8	8-connected neighborhood	
Three-dimensional connectivities		
6	6-connected neighborhood	
18	18-connected neighborhood	
26	26-connected neighborhood	

Connectivity can be defined in a more general way for any dimension by using for CONN a 3-by-3-by- ...-by-3 matrix of 0's and 1's. The 1-valued elements define neighborhood locations relative to the center element of CONN. Note that CONN must be symmetric about its center element.

Class Support

I can be of any nonsparse numeric class and any dimension. I2 has the same size and class as I.

imhmin

Example

Create a sample image with two regional minima.

```
a = 10*ones(10,10);
a(2:4,2:4) = 7;
a(6:8,6:8) = 2
a =
     10
            10
                   10
                          10
                                  10
                                         10
                                                10
                                                       10
                                                               10
                                                                      10
                    7
     10
             7
                           7
                                  10
                                         10
                                                        10
                                                               10
                                                                      10
                                                10
     10
             7
                    7
                           7
                                  10
                                         10
                                                10
                                                        10
                                                               10
                                                                      10
     10
             7
                    7
                           7
                                  10
                                         10
                                                10
                                                       10
                                                               10
                                                                      10
     10
            10
                   10
                          10
                                  10
                                         10
                                                10
                                                        10
                                                               10
                                                                      10
                          10
                                  10
                                          2
                                                 2
                                                         2
     10
            10
                   10
                                                               10
                                                                      10
     10
            10
                   10
                          10
                                  10
                                          2
                                                 2
                                                         2
                                                               10
                                                                      10
                                                         2
     10
            10
                   10
                          10
                                  10
                                          2
                                                 2
                                                               10
                                                                      10
                                  10
                                         10
                                                        10
     10
            10
                   10
                          10
                                                10
                                                               10
                                                                      10
     10
            10
                   10
                          10
                                  10
                                         10
                                                10
                                                        10
                                                               10
                                                                      10
```

Suppress all minima below a specified value. Note how the region with pixel valued 7 disappears in the transformed image.

```
b = imhmin(a,4)
b =
     10
            10
                   10
                           10
                                  10
                                          10
                                                 10
                                                        10
                                                                10
                                                                       10
            10
                   10
                                  10
                                          10
                                                        10
                                                                       10
     10
                           10
                                                 10
                                                                10
     10
            10
                   10
                           10
                                  10
                                          10
                                                 10
                                                        10
                                                                10
                                                                       10
     10
            10
                   10
                           10
                                  10
                                          10
                                                 10
                                                        10
                                                                10
                                                                       10
     10
            10
                   10
                           10
                                  10
                                          10
                                                 10
                                                        10
                                                                10
                                                                       10
     10
            10
                   10
                           10
                                  10
                                           6
                                                  6
                                                         6
                                                                10
                                                                       10
            10
                   10
                                  10
                                           6
                                                  6
                                                         6
                                                                       10
     10
                           10
                                                                10
     10
            10
                   10
                           10
                                  10
                                           6
                                                  6
                                                         6
                                                                10
                                                                       10
     10
            10
                   10
                           10
                                  10
                                          10
                                                 10
                                                        10
                                                                10
                                                                       10
     10
            10
                   10
                           10
                                  10
                                         10
                                                 10
                                                        10
                                                                10
                                                                       10
```

See Also

conndef, imhmax, imreconstruct

Reference

[1] Soille, P., Morphological Image Analysis: Principles and Applications, Springer-Verlag, 1999, pp. 170-171.

Impose minima

Syntax

I2 = imimposemin(I,BW)

I2 = imimposemin(I,BW,CONN)

Description

I2 = imimposemin(I,BW) modifies the intensity image I using morphological reconstruction so it only has regional minima wherever BW is nonzero. BW is a binary image the same size as I.

By default, imimposemin uses 8-connected neighborhoods for 2-D images and 26-connected neighborhoods for 3-D images. For higher dimensions, imimposemin uses conndef(ndims(I), 'minimum').

I2 = imimposemin(I,BW,CONN) specifies the connectivity, where CONN can have any of the following scalar values.

Value	Meaning
Two-dimensional connectivities	
4	4-connected neighborhood
8	8-connected neighborhood
Three-dimensional connectivities	
6	6-connected neighborhood
18	18-connected neighborhood
26	26-connected neighborhood

Connectivity can also be defined in a more general way for any dimension by using for CONN a 3-by-3-by-...-by-3 matrix of 0's and 1's. The 1-valued elements define neighborhood locations relative to the center element of CONN. Note that CONN must be symmetric about its center element.

Class Support


I can be of any nonsparse numeric class and any dimension. BW must be a nonsparse numeric array with the same size as I. I2 has the same size and class as I.

imimposemin

Example

Modify an image so that it only has regional minima at one location.

1 Read an image and display it. This image is called the mask image.
mask = imread('glass.png');
imshow(mask)




2 Create the marker image that will be used to process the mask image.

The example creates a binary image that is the same size as the mask image and sets a small area of the binary image to 1. These pixels define the location in the mask image where a regional minimum will be imposed.

```
marker = false(size(mask));
marker(65:70,65:70) = true;
```

To show where these pixels of interest fall on the original image, this code superimposes the marker over the mask. The small white square marks the spot. This code is not essential to the impose minima operation.

```
J = mask;
J(marker) = 255;
figure, imshow(J); title('Marker Image Superimposed on Mask');
```



3 Impose the regional minimum on the input image using the imimposemin function.

The imimposemin function uses morphological reconstruction of the mask image with the marker image to impose the minima at the specified location. Note how all the dark areas of the original image, except the marked area, are lighter.


```
K = imimposemin(mask,marker);
figure, imshow(K);
```




4 To illustrate how this operation removes all minima in the original image except the imposed minimum, compare the regional minima in the original image with the regional minimum in the processed image. These calls to imregionalmin return binary images that specify the locations of all the regional minima in both images.

```
BW = imregionalmin(mask);
figure, imshow(BW); title('Regional Minima in Original Image')
BW2 = imregionalmin(K);
figure, imshow(BW2), title('Regional Minima After Processing');
```

imimposemin





Regional Minima in Original Image

Regional Minima After Processing

Algorithm

imimposemin uses a technique based on morphological reconstruction.

See Also

conndef, imreconstruct, imregionalmin

Purpose

Compute linear combination of images

Syntax

```
Z = imlincomb(K1,A1,K2,A2,...,Kn,An)
Z = imlincomb(K1,A1,K2,A2,...,Kn,An,K)
Z = imlincomb(..., output class)
```

Description

$$Z = imlincomb(K1,A1,K2,A2,...,Kn,An)$$
 computes
 $K1*A1 + K2*A2 + ... + Kn*An$

where K1, K2, through Kn are real, double scalars and A1, A2, through An are real, nonsparse, numeric arrays with the same class and size. Z has the same class and size as A1.

```
Z = imlincomb(K1,A1,K2,A2,...,Kn,An,K) computes
K1*A1 + K2*A2 + ... + Kn*An + K
```

where imlincomb adds K, a real, double scalar, to the sum of the products of K1 through Kn and A1 through An.

Z = imlincomb(...,output_class) lets you specify the class of Z. output_class is a string containing the name of a numeric class.

When performing a series of arithmetic operations on a pair of images, you can achieve more accurate results if you use imlincomb to combine the operations, rather than nesting calls to the individual arithmetic functions, such as imadd. When you nest calls to the arithmetic functions, and the input arrays are of an integer class, each function truncates and rounds the result before passing it to the next function, thus losing accuracy in the final result. imlincomb computes each element of the output Z individually, in double-precision floating point. If Z is an integer array, imlincomb truncates elements of Z that exceed the range of the integer type and rounds off fractional values.

On Intel architecture processors, imlincomb can take advantage of the Intel Performance Primitives Library (IPPL), thus accelerating its execution time. IPPL is activated only in the following cases:

```
Z = imlincomb( 1.0, A1, 1.0, A2)
Z = imlincomb( 1.0, A1, -1.0, A2)
Z = imlincomb(-1.0, A1, 1.0, A2)
```

```
Z = imlincomb(1.0, A1, K)
```

where A1, A2, and Z are of class uint8, int16, or single and are of the same class.

Examples

Example 1

Scale an image by a factor of 2.

```
I = imread('cameraman.tif');
J = imlincomb(2,I);
imshow(J)
```

Example 2

Form a difference image with the zero value shifted to 128.

```
I = imread('cameraman.tif');
J = uint8(filter2(fspecial('gaussian'), I));
K = imlincomb(1,I,-1,J,128); % K(r,c) = I(r,c) - J(r,c) + 128
figure, imshow(K)
```

Example 3

Add two images with a specified output class.

```
I = imread('rice.png');
J = imread('cameraman.tif');
K = imlincomb(1,I,1,J,'uint16');
figure, imshow(K,[])
```

Example 4

To illustrate how imlincomb performs all the arithmetic operations before truncating the result, compare the results of calculating the average of two arrays, X and Y, using nested arithmetic functions and then using imlincomb.

In the version that uses nested arithmetic functions, imadd adds 255 and 50 and truncates the result to 255 before passing it to imdivide. The average returned in Z(1,1) is 128.

```
X = uint8([ 255 10 75; 44 225 100]);
Y = uint8([ 50 20 50; 50 50 50 ]);
Z = imdivide(imadd(X,Y),2)
Z =
```

imlincomb

imlincomb performs the addition and division in double precision and only truncates the final result. The average returned in Z2(1,1) is 153.

See Also

imadd, imcomplement, imdivide, immultiply, imsubtract

immagbox

Purpose

Magnification box for scroll panel

Syntax

hbox = immagbox(hparent,himage)

Description

hbox = immagbox(hparent,himage) creates a Magnification box for the image displayed in a scroll panel created by imscrollpanel. hparent is a handle to the figure or uipanel object that will contain the Magnification box. himage is a handle to the target image (the image in the scroll panel). immagbox returns hbox, which is a handle to the Magnification box uicontrol object

A Magnification box is an editable text box uicontrol that contains the current magnification of the target image. When you enter a new value in the magnification box, the magnification of the target image changes. When the magnification of the target image changes for any reason, the magnification box updates the magnification value.

API Functions

A magnification box contains a structure of function handles, called an API. You can use the functions in this API to manipulate magnification box. To retrieve this structure, use the iptgetapi function.

api = iptgetapi(hbox)

The API for the Magnification box includes the following function.

Field	Description
setMagnification	Sets the magnification in units of screen pixels per image pixel.
	<pre>api.setMagnification(new_mag)</pre>
	where new_mag is a scalar magnification factor. Multiply new_mag by 100 to get percent magnification. For example if you call api.setMagnification(2), the magnification box will show the string '200%'.

Example

This example adds a magnification box to a scrollable image. Because the toolbox scrollable navigation is incompatible with standard MATLAB figure window navigation tools, the example suppresses the toolbar and menu bar in

the figure window. The example positions the scroll panel in the figure window to allow room for the magnification box.

Change the magnification of the image in the scroll panel, using the scroll panel API function setMagnification. Notice how the magnification box updates.

```
apiSP = iptgetapi(hSP);
apiSP.setMagnification(2)
```

See also

imscrollpanel, iptgetapi

immovie

Purpose

Make movie from multiframe indexed image

Syntax

mov = immovie(X,map)
mov = immovie(RGB)

Description

mov = immovie(X,map) returns the movie structure array mov from the images in the multiframe indexed image X with the colormap map. As it creates the movie array, immovie displays the movie frames on the screen. You can play the movie using the MATLAB movie function. For details about the movie structure array, see the reference page for getframe.

X comprises multiple indexed images, all having the same size and all using the colormap map. X is an m-by-n-by-1-by-k array, where k is the number of images.

mov = immovie(RGB) returns the movie structure array mov from the images in the multiframe, truecolor image RGB.

RGB comprises multiple truecolor images, all having the same size. RGB is an m-by-n-by-3-by-k array, where k is the number of images.

Remarks

You can also use the MATLAB function avifile to make movies from images. The avifile function creates AVI files. To convert an existing MATLAB movie into an AVI file, use the movie2avi function.

Class Support

An indexed image can be uint8, uint16, single, double, or logical. A truecolor image can be uint8, uint16, single, or double. mov is a MATLAB movie structure.

Example

```
load mri
mov = immovie(D,map);
movie(mov,3)
```

See Also

avifile, getframe, montage, movie, movie2avi

Purpose

Multiply two images, or multiply an image by a constant

Syntax

```
Z = immultiply(X,Y)
```

Description

Z = immultiply(X,Y) multiplies each element in array X by the corresponding element in array Y and returns the product in the corresponding element of the output array Z.

If X and Y are real numeric arrays with the same size and class, then Z has the same size and class as X. If X is a numeric array and Y is a scalar double, then Z has the same size and class as X.

If X is logical and Y is numeric, then Z has the same size and class as Y. If X is numeric and Y is logical, then Z has the same size and class as X.

immultiply computes each element of Z individually in double-precision floating point. If X is an integer array, then elements of Z exceeding the range of the integer type are truncated, and fractional values are rounded.

If X and Y are double arrays, you can use the expression X.*Y instead of this function.

Note On Intel architecture processors, immultiply can take advantage of the Intel Performance Primitives Library (IPPL), thus accelerating its execution time. IPPL is activated only if arrays X, Y, and Z are of class logical, uint8, or single, and are of the same class.

Example

Multiply an image by itself. Note how the example converts the class of the image from uint8 to uint16 before performing the multiplication to avoid truncating the results.

```
I = imread('moon.tif');
I16 = uint16(I);
J = immultiply(I16,I16);
imshow(I), figure, imshow(J)
```

Scale an image by a constant factor:

```
I = imread('moon.tif');
```

immultiply

```
J = immultiply(I,0.5);
subplot(1,2,1), imshow(I)
subplot(1,2,2), imshow(J)
```

See also

imabsdiff, imadd, imcomplement, imdivide, imlincomb, imsubtract, ippl

Purpose

Add noise to an image

Syntax

J = imnoise(I,type)

J = imnoise(I,type,parameters)

Description

J = imnoise(I, type) adds noise of a given type to the intensity image I. type is a string that can have one of these values.

Value	Description
'gaussian'	Gaussian white noise with constant mean and variance
'localvar'	Zero-mean Gaussian white noise with an intensity-dependent variance
'poisson'	Poisson noise
'salt & pepper'	On and off pixels
'speckle'	Multiplicative noise

Depending on which type of noise you specify, imnoise accepts additional parameters. If you omit these arguments, imnoise uses default values for the parameters. All numerical parameters are normalized; they correspond to operations with images with intensities ranging from 0 to 1.

J = imnoise(I, 'gaussian', m, v) adds Gaussian white noise of mean m and variance v to the image I. The default is zero mean noise with 0.01 variance.

J = imnoise(I, 'localvar', V) adds zero-mean, Gaussian white noise of local variance V to the image I. V is an array of the same size as I.

J = imnoise(I, 'localvar', image_intensity, var) adds zero-mean, Gaussian noise to an image I, where the local variance of the noise, var, is a function of the image intensity values in I. The image_intensity and var arguments are vectors of the same size, and plot(image_intensity, var) plots the functional relationship between noise variance and image intensity. The image_intensity vector must contain normalized intensity values ranging from 0 to 1.

J = imnoise(I, 'poisson') generates Poisson noise from the data instead of adding artificial noise to the data. In order to respect Poisson statistics, the intensities of unit8 and uint16 images must correspond to the number of photons (or any other quanta of information). Double-precision images are used when the number of photons per pixel can be much larger than 65535 (but less than 10^12); the intensity values vary between 0 and 1 and correspond to the number of photons divided by 10^12.

J = imnoise(I, 'salt & pepper',d) adds salt and pepper noise to the image I, where d is the noise density. This affects approximately d*prod(size(I)) pixels. The default is 0.05 noise density.

J = imnoise(I, 'speckle', v) adds multiplicative noise to the image I, using the equation J = I+n*I, where n is uniformly distributed random noise with mean 0 and variance v. The default for v is 0.04.

Note The mean and variance parameters for 'gaussian', 'localvar', and 'speckle' noise types are always specified as if the image were of class double in the range [0, 1]. If the input image is of class uint8 or uint16, the imnoise function converts the image to double, adds noise according to the specified type and parameters, and then converts the noisy image back to the same class as the input.

Class Support


I can be of class uint8, uint16, int16, single, or double. The output image J is of the same class as I. If I has more than two dimensions it is treated as a multidimensional intensity image and not as an RGB image.

Example

```
I = imread('eight.tif');
J = imnoise(I, 'salt & pepper',0.02);
imshow(I)
figure, imshow(J)
```

imnoise





See Also rand, randn in the MATLAB Function Reference

imopen

Purpose

Open an image

Syntax

IM2 = imopen(IM,SE)
IM2 = imopen(IM,NHOOD)

Description

IM2 = imopen(IM,SE) performs morphological opening on the grayscale or binary image IM with the structuring element SE. The argument SE must be a single structuring element object, as opposed to an array of objects.

IM2 = imopen(IM,NHOOD) performs opening with the structuring element strel(NHOOD), where NHOOD is an array of 0's and 1's that specifies the structuring element neighborhood.

Class Support


IM can be any numeric or logical class and any dimension, and must be nonsparse. If IM is logical, then SE must be flat. IM2 has the same class as IM.

Example

This example uses imopen to filter out the smaller objects in an image.

1 Read the image into the MATLAB workspace and display it.

```
I = imread('snowflakes.png');
imshow(I)
```




2 Create a disk-shaped structuring element with a radius of 5 pixels.

```
se = strel('disk',5);
```

3 Remove snowflakes having a radius less than 5 pixels by opening it with the disk-shaped structuring element created in step 2.

```
I_opened = imopen(I,se);
figure, imshow(I opened,[])
```

imopen



See Also

imclose, imdilate, imerode, strel

imoverview

Purpose

Overview navigation tool for image displayed in scroll panel

Syntax

```
imoverview(himage)
hfig = imoverview(himage)
```

Description

imoverview(himage) creates an Overview tool associated with the image specified by the handle himage, called the target image. The target image must be contained in a scroll panel created by imscrollpanel.

The Overview tool is a navigation aid for images displayed in a scroll panel. imoverview creates the tool in a separate figure window that displays the target image in its entirety, scaled to fit. Over this scaled version of the image, the tool draws a rectangle, called the detail rectangle, that shows the portion of the target image that is currently visible in the scroll panel. To view portions of the image that are not currently visible in the scroll panel, move the detail rectangle in the Overview tool.

hfig = imoverview(...) returns ta handle to the Overview tool figure.

Note

To create an Overview tool that can be embedded in an existing figure or uipanel object, use imoverviewpanel.

Example

This example creates a figure, disabling the toolbar and menubar, because the toolbox navigation tools are not compatible with the standard MATLAB zoom and pan tools. The example then creates a scroll panel in the figure and uses scroll panel API functions to set the magnification.

```
hFig = figure('Toolbar','none',...
'Menubar','none');
hIm = imshow('tape.png');
hSP = imscrollpanel(hFig,hIm);
api = iptgetapi(hSP);
api.setMagnification(2) % 2X = 200%
imoverview(hIm)
```

See Also

imoverviewpanel, imscrollpanel

Purpose

Overview navigation tool uipanel for image displayed in scroll panel

Syntax

hpanel = imoverviewpanel(hparent,himage)

Description

hpanel=imoverviewpanel(hparent, himage) creates creates an Overview tool panel associated with the image specified by the handle himage, called the target image. himage must be contained in a scroll panel created by imsrollpanel. hparent is a handle to the figure or uipanel object that will contain the Overview tool panel. imoverviewpanel returns hpanel, a handle to the Overview tool uipanel object

The Overview tool is a navigation aid for images displayed in a scroll panel. imoverviewpanel creates the tool in a uipanel object that can be embedded in a figure or uipanel object. The tool displays the target image in its entirety, scaled to fit. Over this scaled version of image, the tool draws a rectangle, called the detail rectangle, that shows the portion of the target image that is currently visible in the scroll panel. To view portions of the image that are not currently visible in the scroll panel, move the detail rectangle in the Overview tool.

Note

To create an Overview tool in a separate figure, use imoverview. When created using imoverview, the Overview tool includes zoom-in and zoom-out buttons.

Example

This example creates an Overview navigation tool that is embedded in the same figure that contains the target image.

See also

imoverview, imscrollpanel

impixel

Purpose

Determine pixel color values

Syntax

```
P = impixel(I)
P = impixel(X,map)
P = impixel(RGB)

P = impixel(I,c,r)
P = impixel(X,map,c,r)
P = impixel(RGB,c,r)
[c,r,P] = impixel(...)

P = impixel(x,y,I,xi,yi)
P = impixel(x,y,X,map,xi,yi)
P = impixel(x,y,RGB,xi,yi)
[xi,yi,P] = impixel(x,y,...)
```

Description

impixel returns the red, green, and blue color values of specified image pixels. In the syntaxes below, impixel displays the input image and waits for you to specify the pixels with the mouse.

```
P = impixel(I)
P = impixel(X,map)
P = impixel(RGB)
```

If you omit the input arguments, impixel operates on the image in the current axes.

Use normal button clicks to select pixels. Press **Backspace** or **Delete** to remove the previously selected pixel. A shift-click, right-click, or double-click adds a final pixel and ends the selection; pressing **Return** finishes the selection without adding a pixel.

When you finish selecting pixels, impixel returns an m-by-3 matrix of RGB values in the supplied output argument. If you do not supply an output argument, impixel returns the matrix in ans.

You can also specify the pixels noninteractively, using these syntaxes.

```
P = impixel(I,c,r)
P = impixel(X,map,c,r)
P = impixel(RGB,c,r)
```

r and c are equal-length vectors specifying the coordinates of the pixels whose RGB values are returned in P. The kth row of P contains the RGB values for the pixel (r(k), c(k)).

If you supply three output arguments, impixel returns the coordinates of the selected pixels. For example,

```
[c,r,P] = impixel(...)
```

To specify a nondefault spatial coordinate system for the input image, use these syntaxes.

```
P = impixel(x,y,I,xi,yi)
P = impixel(x,y,X,map,xi,yi)
P = impixel(x,y,RGB,xi,yi)
```

x and y are two-element vectors specifying the image XData and YData. xi and yi are equal-length vectors specifying the spatial coordinates of the pixels whose RGB values are returned in P. If you supply three output arguments, impixel returns the coordinates of the selected pixels.

```
[xi,yi,P] = impixel(x,y,...)
```

Class Support

The input image can be of class uint8, uint16, int16, single, double, or logical. All other inputs are of class double.

If the input is double, the output P is double. For all other input classes the output is single. The rest of the outputs are double.

Remarks

impixel works with indexed, intensity, and RGB images. impixel always returns pixel values as RGB triplets, regardless of the image type:

- For an RGB image, impixel returns the actual data for the pixel. The values are either uint8 integers or double floating-point numbers, depending on the class of the image array.
- For an indexed image, impixel returns the RGB triplet stored in the row of the colormap that the pixel value points to. The values are double floating-point numbers.
- For an intensity image, impixel returns the intensity value as an RGB triplet, where R=G=B. The values are either uint8 integers or double floating-point numbers, depending on the class of the image array.

impixel

```
Example
                     RGB = imread('peppers.png');
                     c = [12 \ 146 \ 410];
                     r = [104 \ 156 \ 129];
                     pixels = impixel(RGB,c,r)
                     pixels =
                          62
                                34
                                      63
                         166
                                54
                                      60
                          59
                                28
                                      47
See Also
                   improfile, pixval
```

impixelinfo

Purpose

Pixel information tool

Syntax


impixelinfo
impixelinfo(h)

impixelinfo(hparent,himage)
hpanel = impixelinfo(...)

Description

impixelinfo creates a pixel information tool in the current figure. The pixel information tool displays information about the pixel in an image that the cursor is positioned over. The tool displays pixel information for all the images in a figure..

The tool is a uipanel object, positioned in the lower-left corner of the figure. It contains the text string "Pixel info:" followed by the *x* and *y* coordinates of the pixel and its value, as shown in the following figure.



The information displayed depends on the image type. The following table shows the information displayed for each image type. If the cursor is outside of the image area in the figure, the pixel information tool displays the default pixel information string.

Image Type	Default Pixel Information String	Example
Intensity	(X,Y) Intensity	(13,30) 82
Indexed	(X,Y) <index> [R G B]</index>	(2.6) <4> [0.29 0.05 0.32]
Binary	(X,Y) BW	(12,1) 0
Truecolor	(X,Y) [R G B]	(19,10) [15 255 10]

If you want to display the pixel information without the "Pixel Info" label, use the impixelinfoval function.

impixelinfo

impixelinfo(h) creates a pixel information tool in the figure specified by h, where h is a handle to an image, axes, uipanel, or figure object. Axes, uipanel, or figure objects must contain at least one image object.

impixelinfo(hparent, himage) creates a pixel information tool in hparent that provides information about the pixels in himage. himage is a handle to an image or an array of image handles. hparent is a handle to the figure or uipanel object that contains the pixel information tool.

hpanel=impixelinfo(...) returns a handle to the pixel information tool uipanel.

Note

To copy the pixel information string to the clipboard, right-click while the cursor is positioned over a pixel. In the context menu displayed, choose **Copy pixel info**.

Examples

This example displays an image and adds a pixel information tool to the figure. The example shows how you can change the position of the tool in the figure using properties of the tool uipanel object.

```
h = imshow('hestain.png');
hp = impixelinfo;
set(hp,'Position',[150 290 300 20]);
```

This example shows how the pixel information tool works in a figure containing multiple images of different types.

```
figure
subplot(1,2,1), imshow('liftingbody.png');
subplot(1,2,2), imshow('autumn.tif');
impixelinfo;
```

See Also

impixelinfoval, impixelregion, imshow, imtool

Purpose

Pixel information tool without the text label

Syntax

hcontrol = impixelinfoval(hparent,himage)

Description

hcontrol = impixelinfoval(hparent,himage) creates a pixel information tool in hparent that provides information about the pixels in the image specified by himage. hparent is a handle to a figure or uipanel object. himage can be a handle to an image or an array of image handles.

The pixel information tool displays information about the pixel in an image that the cursor is positioned over. The tool displays pixel information for all the images in a figure.

When created with impixelinfo, the tool is a uipanel object, positioned in the lower-left corner of the figure, that contains the text label "Pixel Info:" followed by the the *x*- and *y*-coordinates of the pixel and its value. When created with impixelinfoval, the tool is a uicontrol object positioned in the lower-left corner of the figure, that displays the pixel information without the text label, as shown in the following figure.

```
X and Y Pixel coordinates Value
```

The information displayed depends on the image type. See impixelinfo for details.

To copy the pixel value string to the clipboard, right-click while the cursor is positioned over a pixel. In the context menu displayed, choose **Copy pixel info**.

Example

This example shows how to add a pixel value tool to a figure. Note how you can change the style and size of the font used to display the value in the tool using standard Handle Graphics commands.

```
ankle = dicomread('CT-MONO2-16-ankle.dcm');
h = imshow(ankle,[]);
hText = impixelinfoval(gcf,h);
set(hText, 'FontWeight', 'bold')
set(hText, 'FontSize',10)
```

impixelinfoval

See also

impixelinfo

impixelregion

Purpose Pixel Region tool


Syntax impixelregion impixelregion(h)

hfig = impixelregion(...)

Description

impixelregion creates a Pixel Region display tool associated with the image displayed in the current figure, called the target image.

The Pixel Region tool opens a separate figure window containing an extreme close-up view of a small region of pixels in the target image, shown in the following figure. The tool superimposes the numeric value of the pixel over each pixel. To define the region being examined, the tool overlays a rectangle on the target image, called the pixel region rectangle. To view pixels in a different region, click and drag the rectangle over the target image.



impixelregion

impixelregion(h) creates a Pixel Region tool associated with the object specified by the handle h. h can be a handle to a figure, axes, uipanel, or image object. If h is a handle to an axes or figure, impixelregion associates the tool with the first image found in the axes or figure.

hfig=impixelregion(...) returns hfig, a handle of the Pixel Region tool figure.

Note

To create a Pixel Region tool that can be embedded in an existing figure window or uipanel, use impixelregionpanel.

Example

This example displays an image and then creates a Pixel Region tool associated with the image.

imshow peppers.png
impixelregion

See Also

impixelinfo, impixelregionpanel, imtool

impixelregionpanel

Purpose Pixel Region tool panel

Syntax hpanel = impixelregionpanel(hparent, himage)

Description

hpanel = impixelregionpanel(hparent,himage) creates a Pixel Region tool panel associated with the image specified by the handle himage, called the target image. This is the image whose pixels are to be displayed. hparent is the handle to the figure or uipanel object that will contain the Pixel Region tool panel. hpanel is the handle to the Pixel Region tool scroll panel.

The Pixel Region tool is a uipanel object that contains an extreme close-up view of a small region of pixels in the target image. The tool superimposes the numeric value of the pixel over each pixel. To define the region being examined, the tool overlays a rectangle on the target image, called the pixel region rectangle. To view pixels in a different region, click and drag the rectangle over the target image.

Note

To create a Pixel Region tool in a separate figure window, use impixelregion.

Example

```
himage = imshow('peppers.png');
hfigure = figure;
hpanel = impixelregionpanel(hfigure, himage);
```

Set the panel's position to the lower-left quadrant of the figure.

```
set(hpanel, 'Position', [0 0 .5 .5])
```

See Also

impixelregion, impositionrect, imtool

impositionrect

Purpose

Create draggable position rectangle

Syntax

H = impositionrect(hparent, position)

Description

H = impositionrect(hparent, position) creates a position rectangle on the object specified by hparent. The function returns H, a handle to the position rectangle, which is an hggroup object. hparent specifies the hggroup's parent, which is typically an axes object, but can also be any other object that can be the parent of an hggroup. position is a four-element position vector that specifies the initial location of the rectangle. position has the form [XMIN YMIN WIDTH HEIGHT]

All measurements are in units specified by the Units property axes object. When you do not specify the position argument, impositionrect uses [0 0 1 1] as the default value.

Remarks

A position rectangle can be dragged interactively using the mouse. When the position rectangle occurpies a small number of screen pixels, its appearance changes to aid visibility.

The position rectangle has a context menu associated with it that you can use to copy the current position to the clipboard and change the color used to display the rectangle.

API Function Syntaxes

A position rectangle contains a structure of function handles, called an API, that can be used to manipulate it. To retrieve this structure from the position rectangle, use the iptgetapi function.

API = iptgetapi(H)

The following lists the functions in the position rectangle API in the order

they appear in the API structure.

Function	Description
setPosition	Sets the position rectangle to a new position. api.setPosition(new_position)
	where new_position is a four-element position vector.
getPosition	Returns the current position of the position rectangle. position = api.getPosition() position is a four-element position vector.
delete	Deletes the position rectangle associated with the API. api.delete()
setColor	Sets the color used to draw the position rectangle. api.setColor(new_color) where new_color is a three-element vector specifying an RGB value.
addNewPositionCallback	Adds the function handle fun to the list of new-position callback functions. id = api.addNewPositionCallback(fun) Whenever the position rectangle changes its position, each function in the list is called with the syntax: fun(position) The return value, id, is used only with removeNewPositionCallback.

impositionrect

Function	Description
removeNewPositionCallback	Removes the corresponding function from the new-position callback list.
	<pre>api.removeNewPositionCallback(id)</pre>
	where id is the identifier returned by api.addNewPositionCallback
setDragConstraintCallback	Sets the drag constraint function to be the specified function handle, fcn.
	api.setDragConstraintCallback(fcn)
	Whenever the position rectangle is moved because of a mouse drag, the constraint function is called using the syntax:
	<pre>constrained_position = fcn(new_position)</pre>
	where new_position is a four-element position vector. This allows a client, for example, to control where the position rectangle may be dragged.

Examples

Display in the command window the updated position of the position rectangle as it moves in the axes.

```
close all, plot(1:10)
h = impositionrect(gca, [4 4 2 2]);
api = iptgetapi(h);
api.addNewPositionCallback(@(p) disp(p));
```

Constrain the position rectangle to move only up and down.

```
close all, plot(1:10)
h = impositionrect(gca, [4 4 2 2]);
api = getappdata(h, 'API');
api.setDragConstraintCallback(@(p) [4 p(2:4)]);
```

Specify the color of the position rectangle.

```
close all, plot(1:10)
h = impositionrect(gca, [4 4 2 2]);
api = iptgetapi(h, 'API');
api.setColor([1 0 0]);
```

When the position rectangle occupies only a few pixels on the screen, the rectangle is drawn in a different style to increase its visibility.

```
close all, imshow cameraman.tif
h = impositionrect(gca, [100 100 10 10]);
```

See Also

iptgetapi

improfile

Purpose

Compute pixel-value cross-sections along line segments

Syntax

```
c = improfile
c = improfile(n)

c = improfile(I,xi,yi)
c = improfile(I,xi,yi,n)

[cx,cy,c] = improfile(...)
[cx,cy,c,xi,yi] = improfile(...)

[...] = improfile(x,y,I,xi,yi)
[...] = improfile(x,y,I,xi,yi,n)
```

Description

improfile computes the intensity values along a line or a multiline path in an image. improfile selects equally spaced points along the path you specify, and then uses interpolation to find the intensity value for each point. improfile works with grayscale intensity images and RGB images.

If you call improfile with one of these syntaxes, it operates interactively on the image in the current axes.

```
c = improfile
c = improfile(n)
```

n specifies the number of points to compute the intensity value for. If you do not provide this argument, improfile chooses a value for n, roughly equal to the number of pixels the path traverses.

You specify the line or path using the mouse, by clicking points in the image. Press **Backspace** or **Delete** to remove the previously selected point. A shift-click, right-click, or double-click adds a final point and ends the selection; pressing **Return** finishes the selection without adding a point. When you finish selecting points, improfile returns the interpolated data values in c. c is an n-by-1 vector if the input is a grayscale intensity image, or an n-by-1-by-3 array if the input is an RGB image.

If you omit the output argument, improfile displays a plot of the computed intensity values. If the specified path consists of a single line segment, improfile creates a two-dimensional plot of intensity values versus the distance along the line segment; if the path consists of two or more line segments, improfile creates a three-dimensional plot of the intensity values versus their *x*- and *y*-coordinates.

You can also specify the path noninteractively, using these syntaxes.

```
c = improfile(I,xi,yi)
c = improfile(I,xi,yi,n)
```

xi and yi are equal-length vectors specifying the spatial coordinates of the endpoints of the line segments.

You can use these syntaxes to return additional information.

```
[cx,cy,c] = improfile(...)
[cx,cy,c,xi,yi] = improfile(...)
```

cx and cy are vectors of length n, containing the spatial coordinates of the points at which the intensity values are computed.

To specify a nondefault spatial coordinate system for the input image, use these syntaxes.

```
[...] = improfile(x,y,I,xi,yi)
[...] = improfile(x,y,I,xi,yi,n)
```

x and y are two-element vectors specifying the image XData and YData.

[...] = improfile(...,method) uses the specified interpolation method. method is a string that can have one of these values. The default value is enclosed in braces $(\{\})$.

Value	Description
{'nearest'}	Nearest-neighbor interpolation
'bilinear'	Bilinear interpolation
'bicubic'	Bicubic interpolation


improfile

Class Support

The input image can be uint8, uint16, int16, single, double, or logical. All other inputs and outputs must be double.

Example

```
I = imread('liftingbody.png');
x = [19 427 416 77];
y = [96 462 37 33];
improfile(I,x,y),grid on;
```



See Also

impixel

interp2 in the MATLAB Function Reference

imread

Purpose Read image from graphics file

imread is a MATLAB function. To get help for this function, select **MATLAB Help** from the Help menu and view the online function reference page.

imreconstruct

Purpose

Morphological reconstruction

Syntax

IM = imreconstruct(MARKER,MASK)

IM = imreconstruct(MARKER, MASK, CONN)

Description

IM = imreconstruct(MARKER,MASK) performs morphological reconstruction of the image MARKER under the image MASK. MARKER and MASK can be two intensity images or two binary images with the same size. The returned image IM is an intensity or binary image, respectively. MARKER must be the same size as MASK, and its elements must be less than or equal to the corresponding elements of MASK.

By default, imreconstruct uses 8-connected neighborhoods for 2-D images and 26-connected neighborhoods for 3-D images. For higher dimensions, imreconstruct uses conndef(ndims(I), 'maximal').

IM = imreconstruct(MARKER, MASK, CONN) performs morphological reconstruction with the specified connectivity. CONN can have any of the following scalar values.

Value	Meaning	
Two-dime	Two-dimensional connectivities	
4	4-connected neighborhood	
8	8-connected neighborhood	
Three-dimensional connectivities		
6	6-connected neighborhood	
18	18-connected neighborhood	
26	26-connected neighborhood	

Connectivity can be defined in a more general way for any dimension by using for CONN a 3-by-3-by- ... -by-3 matrix of 0's and 1's. The 1-valued elements define neighborhood locations relative to the center element of CONN. Note that CONN must be symmetric about its center element.

imreconstruct

Morphological reconstruction is the algorithmic basis for several other Image Processing Toolbox functions, including imclearborder, imextendedmax, imextendedmin, imfill, imhmax, imhmin, and imimposemin.

Class Support MARKER and MASK must be nonsparse numeric or logical arrays with the same

class and any dimension. IM is of the same class as MARKER and MASK.

Algorithm imreconstruct uses the fast hybrid grayscale reconstruction algorithm

described in [1].

See Also imclearborder, imextendedmax, imextendedmin, imfill, imhmax, imhmin,

imimposemin

Reference [1] Vincent, L., "Morphological Grayscale Reconstruction in Image Analysis:

Applications and Efficient Algorithms," IEEE Transactions on Image

Processing, Vol. 2, No. 2, April, 1993, pp. 176-201.

imregionalmax

Purpose

Find regional maxima

Syntax

BW = imregionalmax(I)

BW = imregionalmax(I,CONN)

Description

BW = imregionalmax(I) finds the regional maxima of I. imregionalmax returns the binary image BW that identifies the locations of the regional maxima in I. BW is the same size as I. In BW, pixels that are set to 1 identify regional maxima; all other pixels are set to 0.

Regional maxima are connected components of pixels with the same intensity value, t, whose external boundary pixels all have a value less than t.

By default, imregionalmax uses 8-connected neighborhoods for 2-D images and 26-connected neighborhoods for 3-D images. For higher dimensions, imregionalmax uses conndef(ndims(I), 'maximal').

BW = imregionalmax(I,CONN) computes the regional maxima of I using the specified connectivity. CONN can have any of the following scalar values.

Value	Meaning
Two-dimensional connectivities	
4	4-connected neighborhood
8	8-connected neighborhood
Three-dimensional connectivities	
6	6-connected neighborhood
18	18-connected neighborhood
26	26-connected neighborhood

Connectivity can be defined in a more general way for any dimension by using for CONN a 3-by-3-by- ...-by-3 matrix of 0's and 1's. The 1-valued elements define neighborhood locations relative to the center element of CONN. Note that CONN must be symmetric about its center element.

Class Support

I can be any nonsparse, numeric class and any dimension. BW is logical.

Example

Create a sample image with several regional maxima.

```
A = 10*ones(10,10);
A(2:4,2:4) = 22;
A(6:8,6:8) = 33;
A(2,7) = 44;
A(3,8) = 45;
A(4,9) = 44;
A =
   10
          10
                 10
                        10
                               10
                                      10
                                              10
                                                    10
                                                           10
                                                                  10
   10
          22
                 22
                        22
                               10
                                      10
                                             44
                                                    10
                                                           10
                                                                   10
          22
                 22
   10
                        22
                               10
                                       10
                                                    45
                                                           10
                                                                   10
                                              10
   10
          22
                 22
                        22
                               10
                                      10
                                              10
                                                    10
                                                           44
                                                                   10
   10
          10
                 10
                        10
                               10
                                      10
                                              10
                                                    10
                                                           10
                                                                   10
   10
          10
                 10
                        10
                               10
                                      33
                                             33
                                                    33
                                                           10
                                                                  10
   10
          10
                 10
                        10
                               10
                                      33
                                             33
                                                    33
                                                           10
                                                                   10
   10
          10
                 10
                        10
                               10
                                      33
                                             33
                                                    33
                                                           10
                                                                   10
   10
          10
                 10
                        10
                               10
                                      10
                                              10
                                                    10
                                                           10
                                                                   10
   10
          10
                 10
                        10
                               10
                                      10
                                              10
                                                    10
                                                           10
                                                                  10
```

Find the regional maxima.

```
regmax = imregionalmax(A)
regmax =
             0
      0
                     0
                             0
                                    0
                                            0
                                                   0
                                                           0
                                                                   0
                                                                          0
      0
             1
                     1
                             1
                                    0
                                            0
                                                   0
                                                           0
                                                                   0
                                                                          0
      0
             1
                     1
                             1
                                    0
                                            0
                                                   0
                                                           1
                                                                   0
                                                                          0
      0
             1
                     1
                             1
                                    0
                                            0
                                                   0
                                                           0
                                                                   0
                                                                          0
      0
             0
                                                                          0
                             0
                                    0
                                            0
                                                   0
                                                           0
                                                                   0
                     0
      0
             0
                     0
                             0
                                    0
                                            1
                                                    1
                                                           1
                                                                   0
                                                                          0
      0
             0
                     0
                             0
                                    0
                                            1
                                                   1
                                                           1
                                                                   0
                                                                          0
      0
             0
                     0
                             0
                                    0
                                            1
                                                   1
                                                           1
                                                                   0
                                                                          0
      0
                                    0
             0
                     0
                             0
                                            0
                                                   0
                                                           0
                                                                   0
                                                                          0
      0
             0
                             0
                                    0
                                            0
                                                   0
                                                           0
                                                                          0
                     0
                                                                   0
```

See Also

conndef, imreconstruct, imregionalmin

imregionalmin

Purpose

Find regional minima

Syntax

BW = imregionalmin(I)

BW = imregionalmin(I,CONN)

Description

BW = imregionalmin(I) computes the regional minima of I. The output binary image BW has value 1 corresponding to the pixels of I that belong to regional minima and 0 otherwise. BW is the same size as I.

Regional minima are connected components of pixels with the same intensity value, t, whose external boundary pixels all have a value greater than t.

By default, imregionalmin uses 8-connected neighborhoods for 2-D images and 26-connected neighborhoods for 3-D images. For higher dimensions, imregionalmin uses conndef(ndims(I), 'maximal').

BW = imregionalmin(I,CONN) specifies the desired connectivity. CONN can have any of the following scalar values.

Value	Meaning		
Two-dime	Two-dimensional connectivities		
4	4-connected neighborhood		
8	8-connected neighborhood		
Three-din	Three-dimensional connectivities		
6	6-connected neighborhood		
18	18-connected neighborhood		
26	26-connected neighborhood		

Connectivity can be defined in a more general way for any dimension by using for CONN a 3-by-3-by- ...-by-3 matrix of 0's and 1's. The 1-valued elements define neighborhood locations relative to the center element of CONN. Note that CONN must be symmetric about its center element.

Class Support

I can be any nonsparse, numeric class and any dimension. BW is logical.

Example

Create a 10-by-10 pixel sample image that contains two regional minima.

```
A = 10*ones(10,10);
A(2:4,2:4) = 2;
A(6:8,6:8) = 7;
A =
     10
           10
                   10
                          10
                                 10
                                        10
                                               10
                                                      10
                                                             10
                                                                    10
     10
             2
                    2
                           2
                                 10
                                        10
                                               10
                                                      10
                                                             10
                                                                    10
     10
             2
                    2
                           2
                                 10
                                        10
                                               10
                                                      10
                                                             10
                                                                    10
            2
                    2
                           2
     10
                                                             10
                                 10
                                        10
                                               10
                                                      10
                                                                    10
     10
           10
                  10
                          10
                                 10
                                        10
                                               10
                                                      10
                                                             10
                                                                    10
     10
           10
                  10
                          10
                                 10
                                         7
                                                7
                                                       7
                                                             10
                                                                    10
     10
           10
                  10
                          10
                                 10
                                         7
                                                7
                                                       7
                                                             10
                                                                    10
     10
           10
                  10
                          10
                                 10
                                         7
                                                7
                                                      7
                                                             10
                                                                    10
     10
           10
                  10
                          10
                                 10
                                        10
                                               10
                                                      10
                                                             10
                                                                    10
     10
           10
                  10
                          10
                                 10
                                        10
                                               10
                                                      10
                                                             10
                                                                    10
```

Pass the sample image A to imregionalmin. The function returns a binary image, the same size as A, in which pixels with the value 1 represent the regional minima in A. imregionalmin sets all other pixels in to zero (0).

В	=	imregi	onalmi	n(A)							
В	=										
		0	0	0	0	0	0	0	0	0	0
		0	1	1	1	0	0	0	0	0	0
		0	1	1	1	0	0	0	0	0	0
		0	1	1	1	0	0	0	0	0	0
		0	0	0	0	0	0	0	0	0	0
		0	0	0	0	0	1	1	1	0	0
		0	0	0	0	0	1	1	1	0	0
		0	0	0	0	0	1	1	1	0	0
		0	0	0	0	0	0	0	0	0	0
		0	0	0	0	0	0	0	0	0	0

See Also

conndef, imreconstruct, imregionalmax

imresize

Purpose

Resize an image

Syntax

```
B = imresize(A, m)
```

B = imresize(A, m, method)

B = imresize(A,[mrows ncols],method)

B = imresize(..., method, n)

B = imresize(...,method,h)

Description

B = imresize(A,m) returns an image B that is m times the size of A, using nearest-neighbor interpolation. A can be an indexed image, grayscale image, RGB, or binary image. If m is between 0 and 1.0, B is smaller than A. If m is greater than 1.0, B is larger than A.

B = imresize(A, m, method) returns an image that is m times the size of A using the interpolation method specified by method. method is a string that can have one of these values. The default value is enclosed in braces ($\{\}$).

Value	Description
{'nearest'}	Nearest-neighbor interpolation
'bilinear'	Bilinear interpolation
'bicubic'	Bicubic interpolation

B = imresize(A,[mrows ncols],method) returns an image of the size specified by [mrows ncols]. If the specified size does not produce the same aspect ratio as the input image has, the output image is distorted.

When the specified output size is smaller than the size of the input image, and method is 'bilinear' or 'bicubic', imresize applies a lowpass filter before interpolation to reduce aliasing. The default filter size is 11-by-11.

You can specify a different order for the default filter using

```
B = imresize(..., method, n)
```

n is an integer scalar specifying the size of the filter, which is n-by-n. If n is 0 (zero), imresize omits the filtering step.

You can also specify your own filter using this syntax.

B = imresize(...,method,h)

h is any two-dimensional FIR filter (such as those returned by ftrans2, fwind1, fwind2, or fsamp2).

Class Support

The input image A can be numeric or logical and it must be nonsparse. The output image B is of the same class as the input image.

See Also

imrotate, imtransform, tformarray

interp2 in the MATLAB Function Reference

imrotate

Purpose

Rotate an image

Syntax

B = imrotate(A, angle)

B = imrotate(A, angle, method)

B = imrotate(A, angle, method, bbox)

Description

B = imrotate(A, angle) rotates the image A by angle degrees in a counterclockwise direction, using the nearest-neighbor interpolation. To rotate the image clockwise, specify a negative angle.

B = imrotate(A, angle, method) rotates the image A by angle degrees in a counterclockwise direction, using the interpolation method specified by method. method is a string that can have one of these values. The default value is enclosed in braces ({}).

Value	Description
{'nearest'}	Nearest-neighbor interpolation
'bilinear'	Bilinear interpolation
'bicubic'	Bicubic interpolation Note: Bicubic interpolation can produce pixel values outside the original range.

B = imrotate(A, angle, method, bbox) rotates the image A through angle degrees. The bbox argument specifies the bounding box of the returned image. bbox is a string that can have one of these values. The default value is enclosed in braces ({}).

Value	Description
'crop'	Output image B includes only the central portion of the rotated image and is the same size as A.
{'loose'}	Output image B includes the whole rotated image and is generally larger than the input image A. imrotate sets pixels in areas outside the original image to zero.


Class Support


The input image A can be numeric or logical and it must be nonsparse. The output image B is of the same class as the input image.

Example

This example reads solar spectra image, stored in FITS format, and rotates the the image to bring it into horizontal alignment. A rotation of -1 degree is all that is required.

```
I = fitsread('solarspectra.fts');
I = mat2gray(I);
J = imrotate(I,-1,'bilinear','crop');
imshow(I)
figure, imshow(J)
```





Original Image

Rotated Image

See Also

imcrop, imresize, imtransform, tformarray

imscrollpanel

Purpose

Scroll panel for interactive image navigation

Syntax

hpanel = imscrollpanel(hparent, himage)

Description

hpanel = imscrollpanel(hparent, himage) creates a scroll panel containing the target image (the image to be navigated).. himage is a handle to the target image. hparent is a handle to the figure or uipanel that will contain the new scroll panel. hpanel is the handle to the scroll panel, which is a uipanel object.

A scroll panel makes an image scrollable. If the size or magnification makes an image too large to display in a figure on the screen, the scroll panel displays a portion of the image at 100% magnification (one screen pixel represents one image pixel). The scroll panel adds horizontal and vertical scroll bars to enable navigation around the image.

imscrollpanel changes the object hierarchy of the target image. Instead of the familiar figure->axes->image object hierarchy, imscrollpanel inserts several uipanel and uicontrol objects between the figure and the axes object.

API functions

A scroll panel contains a structure of function handles, called an API. You can use the functions in this API to manipulate the scroll panel. To retrieve this structure, use the iptgetapi function, as in the following example.

api = iptgetapi(hpanel)

imscroll panel

This table lists the scroll panel API functions, in the order they appear in the structure.

Scroll Panel API Function	Description
setMagnification	Sets the magnification in units of screen pixels per image pixel.
	<pre>mag = api.getMagnification(new_mag)</pre>
	where new_mag is a scalar magnification factor.
getMagnification	Returns the current magnification factor in units of screen pixels per image pixel.
	<pre>mag = api.getMagnification()</pre>
	Multiply mag by 100 to convert to percentage. For example if mag=2, that's equivalent to 200% magnification.
setMagnificationAndCenter	Changes the magnification and makes the point cx, cy appear in the center of the scroll panel. This operation is equivalent to a simultaneous zoom and recenter.
	<pre>api.setMagnificationAndCenter(mag,cx,cy)</pre>
findFitMag	Returns the magnification factor that would make the image just fit in the scroll panel.
	<pre>mag = api.findFitMag()</pre>
setVisibleLocation	Moves the target image so that the specified location is visible. Scrollbars update.
	<pre>api.setVisibleLocation(xmin,ymin)</pre>
	<pre>api.setVisibleLocation([xmin ymin])</pre>

imscrollpanel

Scroll Panel API Function	Description
getVisibleLocation	Returns the location of the currently visible portion of the target image.
	<pre>loc = api.getVisibleLocation()</pre>
	where loc is a vector [xmin ymin].
getVisibleImageRect	Returns the current visible portion of the image.
	<pre>r = api.getVisibleImageRect()</pre>
	where r is a rectangle [xmin ymin width height].
addNewMagnificationCallback	Adds the function handle fcn to the list of new-magnification callback functions.
	<pre>id = api.addNewMagnificationCallback(fcn)</pre>
	Whenever the scroll panel magnification changes, each function in the list is called with the syntax:
	fcn(mag)
	where mag is a scalar magnification factor.
	The return value, id, is used only with removeNewMagnificationCallback.
removeNewMagnificationCallback	Removes the corresponding function from the new-magnification callback list.
	api.removeNewMagnificationCallback(id)
	where id is the identifier returned by addNewMagnificationCallback.

Scroll Panel API Function	Description
addNewLocationCallback	Adds the function handle fcn to the list of new-location callback functions.
	<pre>id = api.addNewLocationCallback(fcn)</pre>
	Whenever the scroll panel location changes, each function in the list is called with the syntax:
	fcn(loc)
	where loc is [xmin ymin].
	The return value, id, is used only with removeNewLocationCallback.
removeNewLocationCallback	Removes the corresponding function from the new-location callback list.
	api.removeNewLocationCallback(id)
	where id is the identifier returned by addNewLocationCallback.

Note

Scrollbar navigation as provided by imscrollpanel is incompatible with the default MATLAB figure navigation buttons (pan, zoom in, zoom out). The corresponding menu items and toolbar buttons should be removed in a custom GUI that includes a scrollable uipanel created by imscrollpanel.

When you run imscrollpanel, it appears to take over the entire figure because, by default, an hpanel object has 'Units' set to 'normalized' and 'Position' set to [0 0 1 1]. If you want to see other children of hparent while using your new scroll panel, you must manually set the 'Position' property of hpanel.

Example

This example creates a scroll panel with a magnification box and an overview tool.

1 Create a scroll panel

```
hFig = figure('Toolbar','none',...
'Menubar','none');
```

```
hIm = imshow('saturn.png');
  hSP = imscrollpanel(hFig,hIm);
  set(hSP, 'Units', 'normalized',...
           'Position',[0 .1 1 .9])
2 Add a magnification box and an overview tool.
  hMagBox = immagbox(hFig,hIm);
  pos = get(hMagBox, 'Position');
  set(hMagBox, 'Position',[0 0 pos(3) pos(4)])
  imoverview(hIm)
3 Get the scroll panel API to programmatically control the view.
  api = iptgetapi(hSP);
4 Get the current magnification and position.
  mag = api.getMagnification()
  r = api.getVisibleImageRect()
5 View the top left corner of the image.
  api.setVisibleLocation(0.5,0.5)
6 Change the magnification to the value that just fits.
  api.setMagnification(api.findFitMag())
7 Zoom in to 1600% on the dark spot.
```

See also

immagbox, imoverview, imoverviewpanel, imtool, iptgetapi

api.setMagnificationAndCenter(16,306,800)

Purpose Display image

Syntax

```
imshow
imshow(I)
imshow(I,[low high])
imshow(RGB)
imshow(BW)
imshow(X,map)
imshow(filename)
himage = imshow(...)
imshow(...,param1,val1,param2,val2)
```

Description

imshow displays the file chooser dialog box so you can select an image file interactively.

imshow(I) displays the intensity image I.

imshow(I,[low high]) displays I as a grayscale intensity image, specifying the display range for I. The value low (and any value less than low) displays as black; the value high (and any value greater than high) displays as white. Values in between are displayed as intermediate shades of gray, using the default number of gray levels. If you use an empty matrix ([]) for [low high], imshow uses [min(I(:)) max(I(:))]; that is, the minimum value in I is displayed as black, and the maximum value is displayed as white.

imshow(RGB) displays the truecolor image RGB.

imshow(BW) displays the binary image BW. imshow displays pixels with the value 0 (zero) as black and pixels with the value 1 as white.

imshow(X,map) displays the indexed image X with the colormap map. A color map matrix may have any number of rows, but it must have exactly 3 columns. Each row is interpreted as a color, with the first element specifying the intensity of red light, the second green, and the third blue. Color intensity can be specified on the interval 0.0 to 1.0.

imshow(filename) displays the image stored in the graphics file filename. The file must contain an image that can be read by imread or dicomread. imshow calls imread or dicomread to read the image from the file, but does not store the image data in the MATLAB workspace. If the file contains multiple images,

imshow

the first one will be displayed. The file must be in the current directory or on the MATLAB path.

himage = imshow(...) returns the handle to the image object created by imshow.

imshow(...,param1,val1,param2,val2,...) displays the image, specifying parameters and corresponding values that control various aspects of the image display. The following table lists all imshow parameters. Parameter names can be abbreviated, and case does not matter..

Parameter	Value
'DisplayRange'	Two-element vector [LOW HIGH] that controls the display range of an intensity image. See above for more details about how to set [LOW HIGH]. Note: Including the parameter name is optional, except when the image is specified by a filename. The syntax imshow(I,[LOW HIGH]) is equivalent to imshow(I, 'DisplayRange',[LOW HIGH]). However, the 'DisplayRange' parameter must be specified when calling imshow with a filename, for example imshow(filename, 'DisplayRange' [LOW HIGH]).
'InitialMagnification'	Any scalar value, or the text string 'fit' that specifies the initial magnification used to display the image. When set to 100 imshow displays the image at 100% magnification (one screen pixel for each image pixel). When set to 'fit', imshow scales the entire image to fit in the window. Initially, imshow always displays the entire image. If the magnification value is large enough that the image would be too big to display on the screen, imshow warns and displays the image at the largest magnification that fits on the screen. By default, the initial magnification parameter is set to the value returned by iptgetpref('ImshowInitialMagnification').

Parameter	Value
'XData'	Two-element vector that establishes a nondefault spatial coordinate system by specifying the image XData. The value can have more than two elements, but only the first and last elements are actually used
'YData'	Two-element vector that establishes a nondefault spatial coordinate system by specifying the image YData. The value can have more than two elements, but only the first and last elements are actually used

Class Support

A truecolor image can be uint8, uint16, double, or single. An indexed image can be logical, uint8, double, or single. An intensity image can be logical, uint8, double, single, int16, or uint16. The input image must be nonsparse.

If your image is int16 or single, the CData in the resulting image object will be double. For all other classes, the CData matches the input image class..

Related Toolbox Preferences

You can use the iptsetpref function to set several toolbox preferences that modify the behavior of imshow.

- 'ImshowBorder' controls whether imshow displays the image with a border around it.
- 'ImshowAxesVisible' controls whether imshow displays the image with the axes box and tick labels.
- 'ImshowInitialMagnification' controls the initial magnification for image display, unless you override it in a particular call by specifying imshow(..., 'InitialMagnification',initial_mag).

For more information about these preferences, see iptsetpref.

Remarks

imshow is the toolbox's fundamental image display function, optimizing figure, axes, and image object property settings for image display. imtool provides all the image display capabilities of imshow but also provides access to several other tools for navigating and exploring images, such as the Pixel Region tool, Image Information tool, and the Adjust Contrast tool. imtool presents an integrated environment for displaying images and performing some common image processing tasks.

imshow

image, imagesc in the MATLAB Function Reference

Purpose

Subtract one image from another, or subtract a constant from an image

Syntax

Z = imsubtract(X,Y)

Description

Z = imsubtract(X,Y) subtracts each element in array Y from the corresponding element in array X and returns the difference in the corresponding element of the output array Z. X and Y are real, nonsparse numeric arrays of the same size and class, or Y is a double scalar. The array returned, Z, has the same size and class as X.

If X is an integer array, then elements of the output that exceed the range of the integer type are truncated, and fractional values are rounded.

If X and Y are double arrays, then you can use the expression X-Y instead of this function.

Note On Intel architecture processors, imsubtract can take advantage of the Intel Performance Primitives Library (IPPL), thus accelerating its execution time. IPPL is activated only if array X is of class uint8, int16, or single.

Examples

Subtract two uint8 arrays. Note that negative results are rounded to 0.

Estimate and subtract the background of an image:

```
I = imread('rice.png');
background = imopen(I,strel('disk',15));
Ip = imsubtract(I,background);
imshow(Ip,[])
```

Subtract a constant value from an image:

imsubtract

```
I = imread('rice.png');
Iq = imsubtract(I,50);
figure, imshow(I), figure, imshow(Iq)
```

See Also

imabsdiff, imadd, imcomplement, imdivide, imlincomb, immultiply, ippl

Purpose

Display image in the Image Tool

Syntax

```
imtool
imtool(I)
imtool(I,[LOW HIGH])
imtool(RGB)
imtool(BW)
imtool(X,map)
imtool(filename)
hfig = imtool(...)
imtool close all
imtool(...,param1,val1,param2,val2,...)
```

Description

imtool opens a new Image Tool in an empty state. Use the **File** menu options **Open** or **Import From Workspace** to choose an image for display.

imtool(I) displays the intensity image I.

imtool(I,[LOW HIGH]) displays I as a grayscale intensity image, specifying the display range for I. The value LOW (and any value less than LOW) displays as black, the value HIGH (and any value greater than HIGH) displays as white. Values in between display as intermediate shades of gray. imtool uses the default number of gray levels. If you use an empty matrix ([]) for [LOW HIGH], imtool uses $[\min(I(:)) \max(I(:))]$; the minimum value in I displays as black, and the maximum value displays as white.

imtool(RGB) displays the truecolor image RGB.

imtool(BW) displays the binary image BW. Values of 0 display as black, and values of 1 display as white.

imtool(X,map) displays the indexed image X with colormap map.

imtool(filename) displays the image contained in the graphics file filename. The file must contain an image that can be read by imread or dicomread. imtool calls imread or dicomread to read the image from the file, but the image data is not stored in the MATLAB workspace. If the file contains multiple images, the first one will be displayed. The file must be in the current directory or on the MATLAB path.

imtool

hfig = imtool(...) returns a handle Hfig to the figure created by imtool. close(Hfig) closes the image tool.

imtool close all closes all image tools.

imtool(...,param1,val1,param2,val2,...) displays the image, specifying parameters and corresponding values that control various aspects of the image display. The following table lists all imshow parameters. Parameter names can be abbreviated, and case does not matter.

Parameter	Value
'DisplayRange'	Two-element vector [LOW HIGH] that controls the display range of an intensity image. See above for more details about how to set [LOW HIGH]. Note: Including the parameter name is optional, except when the image is specified by a filename. The syntax imtool(I,[LOW HIGH]) is equivalent to imtool(I,'DisplayRange',[LOW HIGH]). However, the 'DisplayRange' parameter must be specified when calling imtool with a filename, as in the syntax imtool(filename,'DisplayRange'[LOW HIGH]).
'InitialMagnification'	One of two text strings: 'adaptive' or 'fit' or a numeric scalar value that specifies the initial magnification used to display the image. When set to 'adaptive', the entire image is visible on initial display. If the image is too large to display on the screen, imtool displays the image at the largest magnification that fits on the screen. When set to 'fit', imtool scales the entire image to fit in the window. When set to a numeric value, the value specifies the magnification as a percentage. For example, if you specify 100, the image is displayed at 100% magnification (one screen pixel for each image pixel). By default, the initial magnification parameter is set to the value returned by iptgetpref('ImtoolInitialMagnification').

Class Support

A truecolor image can be uint8, uint16, double, or single. An indexed image can be logical, uint8, double, or single. An intensity image can be logical, uint8, double, single, int16, or uint16. The input image must be nonsparse.

Related Toolbox Preferences

You can use the iptsetpref function to set the following toolbox preference that modifies the behavior of imtool.

 'ImtoolInitialMagnification' controls the initial magnification for image display, unless you override it in a particular call by specifying imtool(...,'InitialMagnification',initial_mag).

For more information about these preferences, see the reference entry for iptsetpref.

Remarks

imshow is the toolbox's fundamental image display function, optimizing figure, axes, and image object property settings for image display. imtool provides all the image display capabilities of imshow but also provides access to several other tools for navigating and exploring images, such as the Pixel Region tool, Image Information tool, and the Adjust Contrast tool. imtool presents an integrated environment for displaying images and performing some common image processing tasks.

Examples

Display an image from a file.

```
imtool('board.tif')
```

Display an indexed image.

```
[X,map] = imread('trees.tif');
imtool(X,map)
```

Display an intensity image.

```
I = imread('cameraman.tif');
imtool(I)
```

Display an intensity image, adjusting the display range.

```
h = imtool(I,[0 80]);
close(h)
```

imtool

See Also

getimage, imageinfo, imcontrast, imdisplayrange, imgetfile, imoverview, impixelinfo, impixelregion, imread, imshow, iptgetpref, ipticondir, iptsetpref, iptwindowalign

Purpose Perform top-hat filtering

Syntax IM2 = imtophat(IM,SE)

IM2 = imtophat(IM, NHOOD)

Description

IM2 = imtophat(IM,SE) performs morphological top-hat filtering on the grayscale or binary input image IM using the structuring element SE, where SE is returned by strel. SE must be a single structuring element object, not an array containing multiple structuring element objects.

IM2 = imtophat(IM,NHOOD), where NHOOD is an array of 0's and 1's that
specifies the size and shape of the structuring element, is the same as
imptophat(IM,strel(NHOOD)).

Class Support

IM can be numeric or logical and must be nonsparse. The output image IM2 has the same class as the input image. If the input is binary (logical), the structuring element must be flat.

Example

You can use top-hat filtering to correct uneven illumination when the background is dark. This example uses top-hat filtering with a disk-shaped structuring element to remove the uneven background illumination from an image.

1 Read an image into the MATLAB workspace.

```
I = imread('rice.png');
imshow(I)
```



imtophat

2 Create the structuring element and perform top-hat filtering of the image.

```
se = strel('disk',12);
J = imtophat(I,se);
figure, imshow(J)
```



3 Use imadjust to improve the visibility of the result.

```
K = imadjust(J);
figure, imshow(K)
```



See Also

imbothat, strel

Purpose

Apply 2-D spatial transformation to image

Syntax

```
B = imtransform(A,TFORM)
B = imtransform(A,TFORM,INTERP)
[B,XDATA,YDATA] = imtransform(...)
[B,XDATA,YDATA] = imtransform(...,param1,val1,param2,val2,...)
```

Description

B = imtransform(A,TFORM) transforms the image A according to the 2-D spatial transformation defined by TFORM, which is a spatial transformation structure (TFORM) as returned by maketform or cp2tform. If ndims(A) > 2, such as for an RGB image, then the same 2-D transformation is automatically applied to all 2-D planes along the higher dimensions.

When you use this syntax, imtransform automatically shifts the origin of your output image to make as much of the transformed image visible as possible. If you are using imtransform to do image registration, this syntax is not likely to give you the results you expect; you might want to set 'XData' and 'YData' explicitly.

B = imtransform(A, TFORM, INTERP) specifies the form of interpolation to use. INTERP can have one of these values. The default value is enclosed in braces ({}).

Value	Description
'bicubic'	Bicubic interpolation
{'bilinear'}	Bilinear interpolation
'nearest'	Nearest-neighbor interpolation

Alternatively, INTERP can be a RESAMPLER structure returned by makeresampler. This option allows more control over how resampling is performed.

[B,XDATA,YDATA] = imtransform(...) returns the location of the output image B in the output X-Y space. XDATA and YDATA are two-element vectors. The elements of XDATA specify the x-coordinates of the first and last columns of B. The elements of YDATA specify the y-coordinates of the first and last rows of B. Normally, imtransform computes XDATA and YDATA automatically so that B

imtransform

contains the entire transformed image A. However, you can override this automatic computation; see below.

[B,XDATA,YDATA] = imtransform(...,param1,val1,param2,val2,...) specifies parameters that control various aspects of the spatial transformation. This table lists all the parameters you can specify. Note that parameter names can be abbreviated and are not case sensitive.

Parameter	Description
'UData' 'VData'	Both of these parameters are two-element real vectors. 'UData' and 'VData' specify the spatial location of the image A in the 2-D input space U-V. The two elements of 'UData' give the <i>u</i> -coordinates (horizontal) of the first and last columns of A, respectively. The two elements of 'VData' give the <i>v</i> -coordinates (vertical) of the first and last rows of A, respectively. The default values for 'UData' and 'VData' are
'XData' 'YData'	[1 size(A,2)] and [1 size(A,1)], respectively. Both of these parameters are two-element real vectors. 'XData' and 'YData' specify the spatial location of the output image B in the 2-D output space X-Y. The two elements of 'XData' give the x-coordinates (horizontal) of the first and last columns of B, respectively. The two elements of 'YData' give the y-coordinates (vertical) of the first and last rows of B, respectively.
	If 'XData' and 'YData' are not specified, imtransform estimates values for them that will completely contain the entire transformed output image.

imtransform

Parameter	Description
'XYScale'	A one- or two-element real vector. The first element of 'XYScale' specifies the width of each output pixel in X-Y space. The second element (if present) specifies the height of each output pixel. If 'XYScale' has only one element, then the same value is used for both width and height. If 'XYScale' is not specified but 'Size' is, then 'XYScale' is computed from 'Size', 'XData', and 'YData'. If neither 'XYScale' nor 'Size' is provided, then the scale of the input pixels is used for 'XYScale'.
'Size'	A two-element vector of nonnegative integers. 'Size' specifies the number of rows and columns of the output image B. For higher dimensions, the size of B is taken directly from the size of A. In other words, size(B,k) equals size(A,k) for k > 2. If 'Size' is not specified, then it is computed from 'XData', 'YData', and 'XYScale'.

imtransform

Parameter	Description
'FillValues'	An array containing one or several fill values. Fill values are used for output pixels when the corresponding transformed location in the input image is completely outside the input image boundaries. If A is 2-D, 'FillValues' must be a scalar. However, if A's dimension is greater than two, then 'FillValues' can be an array whose size satisfies the following constraint: size(fill_values,k) must equal either size(A,k+2) or 1. For example, if A is a uint8 RGB image that is 200-by-200-by-3, then possibilities for 'FillValues' include 0 Fill with black [0;0;0] Fill with black [255;255;255] Fill with white [255;255;255] Fill with white [255;255;0] Fill with yellow
	If A is 4-D with size 200-by-200-by-3-by-10, then 'FillValues' can be a scalar, 1-by-10, 3-by-1, or 3-by-10.

Notes

- When you do not specify the output-space location for B using 'XData' and 'YData', imtransform estimates them automatically using the function findbounds. For some commonly used transformations, such as affine or projective, for which a forward mapping is easily computable, findbounds is fast. For transformations that do not have a forward mapping, such as the polynomial ones computed by cp2tform, findbounds can take significantly longer. If you can specify 'XData' and 'YData' directly for such transformations, imtransform might run noticeably faster.
- The automatic estimate of 'XData' and 'YData' using findbounds is not guaranteed in all cases to completely contain all the pixels of the transformed input image.

- The output values XDATA and YDATA might not exactly equal the input 'XData' and 'YData' parameters. This can happen either because of the need for an integer number of rows and columns, or if you specify values for 'XData', 'YYScale', and 'Size' that are not entirely consistent. In either case, the first element of XDATA and YDATA always equals the first element of 'XData' and 'YData', respectively. Only the second elements of XDATA and YDATA might be different.
- imtransform assumes spatial-coordinate conventions for the transformation TFORM. Specifically, the first dimension of the transformation is the horizontal or *x*-coordinate, and the second dimension is the vertical or *y*-coordinate. Note that this is the reverse of the array subscripting convention in MATLAB.
- TFORM must be a 2-D transformation to be used with imtransform. For arbitrary-dimensional array transformations, see tformarray.

Class Support

The input image A can be of any nonsparse numeric class, real or complex, or it can be of class logical. The class of B is the same as the class of A.

Example

Example 1

Apply a horizontal shear to an intensity image.

```
I = imread('cameraman.tif');
tform = maketform('affine',[1 0 0; .5 1 0; 0 0 1]);
J = imtransform(I,tform);
imshow(I), figure, imshow(J)
```

Example 2

A projective transformation can map a square to a quadrilateral. In this example, set up an input coordinate system so that the input image fills the unit square and then transform the image into the quadrilateral with vertices (0 0), (1 0), (1 1), (0 1) to the quadrilateral with vertices (-4 2), (-8 3), (-3 -5), (6 3). Fill with gray and use bicubic interpolation. Make the output size the same as the input size.

```
'udata', udata,...
'vdata', vdata,...
'size', size(I),...
'fill', 128);
subplot(1,2,1), imshow(udata,vdata,I), axis on
subplot(1,2,2), imshow(xdata,ydata,B), axis on
```

Example 3

Register an aerial photo to an orthophoto.

Read in the aerial photo.

```
unregistered = imread('westconcordaerial.png');
figure, imshow(unregistered)
```

Read in the orthophoto.

```
figure, imshow('westconcordorthophoto.png')
```

Load control points that were previously picked.

```
load westconcordpoints
```

Create a transformation structure for a projective transformation.

```
t_concord = cp2tform(input_points,base_points,'projective');
```

Get the width and height of the orthophoto and perform the transformation.

See Also

checkerboard, cp2tform, imresize, imrotate, maketform, makeresampler, tformarray

Purpose

Display image in the image tool

 $oldsymbol{\mathsf{Note}}$ This function is obsolete and may be removed in future versions. Use imtool instead.

imwrite

Purpose

Write image to graphics file

imwrite is a function in MATLAB. To get help for this function, select **MATLAB Help** from the Help menu and view the online function reference page.

Purpose Convert an indexed image to an intensity image

Syntax I = ind2gray(X,map)

Description I = ind2gray(X, map) converts the image X with colormap map to an intensity

image I. ind2gray removes the hue and saturation information from the input

image while retaining the luminance.

Class Support X can be of class uint8, uint16, single, or double. map is double. I is of the

same class as X.

Example load trees

I = ind2gray(X, map);

imshow(X,map)
figure,imshow(I)





Image Courtesy of Susan Cohen

Algorithm ind2gray converts the colormap to NTSC coordinates using rgb2ntsc, and sets

the hue and saturation components (I and Q) to zero, creating a gray colormap. ind2gray then replaces the indices in the image X with the corresponding

grayscale intensity values in the gray colormap.

See Also gray2ind, imshow, imtool, rgb2ntsc

ind2rgb

Purpose Convert an indexed image to an RGB image

Syntax RGB = ind2rgb(X,map)

Description RGB = ind2rgb(X, map) converts the matrix X and corresponding colormap map

to RGB (truecolor) format.

Class Support X can be of class uint8, uint16, or double. RGB is an m-by-n-by-3 array of class

double.

See Also ind2gray, rgb2ind

Purpose Converts integer values using a lookup table

Syntax B = intlut(A, LUT)

Description B = intlut(A, LUT) converts values in array A based on lookup table LUT and

returns these new values in array B.

For example, if A is a vector whose kth element is equal to alpha, then B(k) is

equal to the LUT value corresponding to alpha, i.e., LUT(alpha+1).

Class Support A can be uint8, uint16, or int16. If A is uint8, LUT must be a uint8 vector with

256 elements. If A is uint 16 or int 16, LUT must be a vector with 65536 elements

that has the same class as A. B has the same size and class as A.

Example A = uint8([1 2 3 4; 5 6 7 8; 9 10 11 12])

LUT = repmat(uint8($[0\ 150\ 200\ 255]$),1,64);

B = intlut(A, LUT)

See Also ind2gray, rgb2ind

ippl

Purpose

Check for presence of the Intel Performance Primitives Library (IPPL)

Syntax

Description

The Intel Performance Primitives Library (IPPL) provides a collection of basic functions used in signal and image processing. The IPPL takes advantage of the parallelism of the Single-Instruction, Multiple-Data (SIMD) instructions that make up the core of the MMX technology and Streaming SIMD Extensions. These instructions are available only on the Intel architecture processors. IPPL is used by some of the Image Processing Toolbox functions to accelerate their execution time.

TF = ippl returns true (1) if IPPL is available and false (0) otherwise.

[TF B] = ippl returns an additional column cell array B. Each row of B contains a string describing a specific IPPL module.

When IPPL is available, the Image Processing Toolbox image arithmetic functions (imabsdiff, imadd, imsubtract, imdivide, immultiply, and imlincomb) and the imfilter function take advantage of it. Toolbox functions that use these functions also benefit.

Notes

IPPL is utilized only for some data types and only under specific conditions. See the help sections of the functions listed above for detailed information on when IPPL is activated.

The IPPL function is likely to change.

See Also

imabsdiff, imadd, imdivide, imfilter, imlincomb, immultiply, imsubtract

iptaddcallback

Purpose

Add function handle to a callback list

Syntax

ID = iptaddcallback(h,callback,func handle)

Description

ID = iptaddcallback(h,callback,func_handle) adds the function handle func_handle to the list of functions to be called when the callback specified by callback executes. callback is a string specifying the name of a callback property of the Handle Graphics object specified by the handle h.

iptaddcallback returns a unique callback identifier, ID, that can be used with iptremovecallback to remove the function from the callback list.

iptaddcallback can be useful when more than one tool want to be notified about the same callback event for a single object.

Note

Callback functions that have already been added to an object using the set command continue to work after calling iptaddcallback. The first time you call iptaddcallback for a given object and callback, the function checks to see if a different callback function is already installed. If a callback is already installed, iptaddcallback replaces that callback function with the iptaddcallback callback processor, and then adds the pre-existing callback function to the iptaddcallback list.

Example

This example creates a figure and registers two callback functions. Whenever MATLAB detects mouse motion over the figure, function handles f1 and f2 are called in the order in which they were added to the list.

```
h = figure;
f1 = @(varargin) disp('Callback 1');
f2 = @(varargin) disp('Callback 2');
iptaddcallback(h, 'WindowButtonMotionFcn', f1);
iptaddcallback(h, 'WindowButtonMotionFcn', f2);
```

See Also

iptremovecallback

iptcheckconn

Purpose Check validity of connectivity argument

Syntax iptcheckconn(CONN,func_name,var_name,arg_pos)

Description

iptcheckconn(CONN,func_name,var_name,arg_pos) checks if CONN is a valid connectivity argument. If it is invalid, the function issues a formatted error message.

A connectivity argument can be one of the following scalar values, 1, 4, 6, 8, 18, or 26. A connectivity argument can also be a 3-by-3-by- ... -by-3 array of 0s and 1s. The central element of a connectivity array must be nonzero and the array must be symmetric about its center.

func_name is a string that specifies the name used in the formatted error message to identify the function checking the connectivity argument.

var_name is a string that specifies the name used in the formatted error message to identify the argument being checked.

arg_pos is a positive integer that indicates the position of the argument being checked in the function argument list.

iptcheckconn converts this number to an ordinal number and includes this information in the formatted error message.

Class Support

 $\ensuremath{\mathsf{CONN}}$ must be of class double or logical and must be real and nonsparse.

Example

To trigger this error message, this example creates a 4-by-4 array and passes it as the connectivity argument.

iptcheckconn(eye(4), 'func_name','var_name',2)

See also

iptnum2ordinal

iptcheckhandle

Purpose

Check validity of handle

Syntax

iptcheckhandle(H,valid_types,func_name,var_name,arg_pos)

Description

iptcheckhandle(H,valid_types,func_name,var_name,arg_pos) checks the validity of the handle H and issues a formatted error message, if the handle is invalid. H must be a handle to a single figure, uipanel, hggroup, axes, or image object.

valid_types is a cell array of strings specifying the set of Handle Graphics object types to which H is expected to belong. For example, if you specify valid_types as {'uipanel','figure'}, H can be either a handle to a uipanel object or a figure object.

func_name is a string that specifies the name used in the formatted error message to identify the function checking the handle.

var_name is a string that specifies the name used in the formatted error message to identify the argument being checked.

arg_pos is a positive integer that indicates the position of the argument being checked in the function argument list. iptcheckhandle converts this number to an ordinal number and includes this information in the formatted error message.


Example

To trigger the error message, create a figure that does not contain an axes and then check for a valid axes handle.

```
fig = figure; % create figure without an axes
iptcheckhandle(fig, {'axes'}, 'my_function', 'my_variable', 2)
```

The following shows the format of the error message and indicates which parts you can customize using iptcheckhandle arguments.

iptcheckhandle



See Also

 $\verb|iptcheckinput|, \verb|iptcheckmap|, \verb|iptchecknargin|, \verb|iptcheckstrs|, \\ \verb|iptnum2ordinal|$

Purpose

Check validity of array and issue error message, if invalid

Syntax

iptcheckinput(A,classes,attributes,func name,var name,arg pos)

Description

iptcheckinput(A, classes, attributes, func_name, var_name, arg_pos) checks the validity of the array A and issues a formatted error message if it is invalid.

classes is a cell array of strings specifying the set of classes to which A is expected to belong. For example, if you specify classes as { 'logical' 'cell'}, A is required to be either a logical array or a cell array. The string 'numeric' is interpreted as an abbreviation for the classes uint8, uint16, uint32, int8, int16, int32, single, and double.

attributes is a cell array of strings specifying the set of attributes that A must satisfy. For example, if attributes is {'real' 'nonempty' 'finite'}, A must be real and nonempty, and it must contain only finite values. The following table lists the supported attributes in alphabetical order.

2d	nonemptyvector	odd	twod
column	nonnan	positive	vector
even	nonnegative	real	
finite	nonsparse	row	
integer	nonzero	scalar	

func_name is a string that specifies the name used in the formatted error message to identify the function checking the input.

var_name is a string that specifies the name used in the formatted error message to identify the argument being checked.

arg_pos is a positive integer that indicates the position of the argument being checked in the function argument list. iptcheckinput converts this number to an ordinal number and includes this information in the formatted error message.

Example


Create a three dimensional array.

$$A = [123; 456];$$

iptcheckinput

```
B = [ 7 8 9; 10 11 12];
C = cat(3,A,B);
iptcheckinput(F,{'numeric'},{'2d'},'func_name','var_name',2)
```

The following shows the format of the error message and indicates which parts you can customize using iptcheckinput arguments.



See Also

iptcheckhandle, iptcheckmap, iptchecknargin, iptcheckstrs, iptnum2ordinal **Purpose**

Check validity of colormap

Syntax

iptcheckmap(map,func name,var name,arg pos)

Description

iptcheckmap(map,func_name,var_name,arg_pos) checks the validity of the MATLAB colormap and issues an error message if it is invalid.

func_name is a string that specifies the name used in the formatted error message to identify the function checking the colormap.

var_name is a string that specifies the name used in the formatted error message to identify the argument being checked.

arg_pos is a positive integer that indicates the position of the argument being checked in the function argument list. iptcheckmap converts this number to an ordinal number and includes this information in the formatted error message.

Example

```
bad_map = ones(10);
iptcheckmap(bad map, 'func name', 'var name',2)
```

The following shows the format of the error message and indicates which parts you can customize using iptcheckmap arguments.



Function FUNC_NAME expected its second input argument, var_name, to be a valid colormap.

Valid colormaps must be nonempty, double, 2-D matrices with 3 columns.

See Also

iptcheckhandle, iptcheckinput, iptchecknargin, iptcheckstrs, iptnum2ordinal

iptchecknargin

Purpose Check number of input arguments

Syntax iptchecknargin(low,high,num inputs,func name)

Description iptchecknargin(low,high,num inputs,func name) checks whether

num_inputs is in the range indicated by low and high. If not, iptchecknargin

issues a formatted error message.

low should be a scalar nonnegative integer.

high should be a scalar nonnegative integer or Inf.

func_name is a string that specifies the name used in the formatted error

message to identify the function checking the handle.

Example Create a function and use iptchecknargin to check that the number of

arguments passed to the function is within the expected range.

function test_function(varargin)
iptchecknargin(1,3,nargin,mfilename);

Trigger the error message by executing the function at the MATLAB command $\,$

line, specifying more the expected number of arguments.

 $test_function(1,2,3,4)$

See Also iptcheckhandle, iptcheckinput, iptcheckmap, iptcheckstrs,

iptnum2ordinal

Purpose

Check validity of option string

Syntax

out=iptcheckstrs(in,valid strs,func name,var name,arg pos)

Description

out=iptcheckstrs(in,valid_strs,func_name,var_name,arg_pos) checks the validity of the option string IN. It returns the matching string in valid_strs in out. iptcheckstrs looks for a case-insensitive, nonambiguous match between in and the strings in valid strs.

valid_strs is a cell array containing strings.

func_name is a string that specifies the name used in the formatted error message to identify the function checking the strings.

var_name is a string that specifies the name used in the formatted error message to identify the argument being checked.

arg_pos is a positive integer that indicates the position of the argument being checked in the function argument list. iptcheckstrs converts this number to an ordinal number and includes this information in the formatted error message.

Example

To trigger this error message, define a cell array of some text strings and pass in another string that isn't in the cell array.

The following shows the format of the error message and indicates which parts you can customize using iptcheckhandle arguments.



Function FUNC_NAME expected its second input argument, var_name to match one of these strings:

option1, option2 **◄** valid_strs

The input, 'option3', did not match any of the valid strings.

iptcheckstrs

See Also

 $ipt check handle, ipt check input, ipt check map, ipt check nargin, \\ipt num 2 ordinal$

iptdemos

Purpose Display index of Image Processing Toolbox demos

Syntax iptdemos

Description iptdemos displays the HTML page that lists all the Image Processing demos.

iptdemos displays the page in the MATLAB Help browser.

iptgetapi

Purpose Get Application Program Interface (API) for a handle

Syntax API = iptgetapi(h)

Description API = iptgetapi(h) returns the API structure associated with handle h if

there is one. Otherwise, iptgetapi returns an empty array.

For more information about handle APIs, see the help for immagbox,

impositionrect, or imscrollpanel.

Example

See Also

immagbox, impositionrect, imscrollpanel

Purpose Return Image Processing Toolbox preference

Syntax prefs = iptgetpref

value = iptgetpref(prefname)

Description

prefs = iptgetpref returns a structure containing all the Image Processing Toolbox preferences with their current values. Each field in the structure has the name of an Image Processing Toolbox preference. See iptsetpref for a list.

value = iptgetpref(prefname) returns the value of the Image Processing Toolbox preference specified by the string prefname. See iptsetpref for a complete list of valid preference names. Preference names are not case

sensitive and can be abbreviated.

Example value = iptgetpref('ImshowAxesVisible')

value =

off

See Also imshow, iptsetpref

ipticondir

Purpose Return name of directories containing IPT and MATLAB icons

Syntax [D1 D2] = ipticondir

Description [D1, D2] = imicondir returns the name of the directories containing the IPT

icons (D1) and the MATLAB icons (D2).

Example [iptdir, MATLABdir] = ipticondir

dir(iptdir)

See Also imtool

iptnum2ordinal

Purpose Convert positive integer to ordinal string

Syntax string = iptnum2ordinal(number)

Description string = iptnum2ordinal(number) converts the positive integer number to

the ordinal text string string.

Example The following example returns the string 'fourth'.

str = iptnum2ordinal(4)

The following example returns the string '23rd'.

str = iptnum2ordinal(23)

iptremovecallback

Purpose

Delete function handle from callback list

Syntax

iptremovecallback(h,callback,ID)

Description

iptremovecallback(h,callback,ID) deletes a callback from the list of callbacks created by imaddcallback for the object with handle h and the associated callback string callback. ID is the identifier of the callback to be deleted. This ID is returned by iptaddcallback when you add the function handle to the callback list.

Example

This example registers three callbacks for a particular figure and then removes one of them.

Register the callbacks and try them interactively.

```
h = figure;
f1 = @(varargin) disp('Callback 1');
f2 = @(varargin) disp('Callback 2');
f3 = @(varargin) disp('Callback 3');
id1 = iptaddcallback(h, 'WindowButtonMotionFcn', f1);
id2 = iptaddcallback(h, 'WindowButtonMotionFcn', f2);
id3 = iptaddcallback(h, 'WindowButtonMotionFcn', f3);
```

Remove one of the callbacks and then move the mouse over the figure again. Whenever MATLAB detects mouse motion over the figure, function handles f1 and f3 are called in that order.

```
iptremovecallback(h, 'WindowButtonMotionFcn', id2);
```

See also

iptaddcallback

iptsetpref

Purpose Set Image Processing Toolbox preferences or display valid values

Syntax iptsetpref(prefname)

iptsetpref(prefname, value)

Description iptsetpref(prefname) displays the valid values for the Image Processing

Toolbox preference specified by prefname.

iptsetpref(prefname, value) sets the Image Processing Toolbox preference specified by the string prefname to the value specified by value. The setting persists until the end of the current MATLAB session, or until you change the setting. (To make the value persist between sessions, put the command in your

startup.m file.)

iptsetpref

This table describes the available preferences. Note that the preference names are case insensitive and can be abbreviated. The default value is enclosed in braces $(\{\})$.

Preference Name	Description	
'ImshowBorder'	Controls whether imshow includes a border around the image in the figure window. Possible values:	
	{'loose'} — Include a border between the image and the edges of the figure window, thus leaving room for axes labels, titles, etc.	
	'tight' — Adjust the figure size so that the image entirely fills the figure.	
	Note: There can still be a border if the image is very small, or if there are other objects besides the image and its axes in the figure.	
'ImshowAxesVisible'	Controls whether imshow displays images with the axes box and tick labels. Possible values:	
	'on' — Include axes box and tick labels.	
	{'off'} — Do not include axes box and tick labels.	

Preference Name	Description
'ImshowInitialMagnification'	Controls the initial magnification of the image displayed by imshow. Possible values:
	Any numeric value — imshow interprets numeric values as a percentage. The default value is 100. One hundred per cent magnification means that there should be one screen pixel for every image pixel.
	'fit' — Scale the image so that it fits into the window in its entirety.
	You can override this preference by specifying the 'InitialMagnification' parameter when you call imshow or by calling the truesize function manually after displaying the image.
'ImtoolInitialMagnification'	Controls the initial magnification of the image displayed by imtool. Possible values:
	{'adaptive'} — Display the entire image. If the image is too large to display on the screen at 100% magnification, display the image at the largest magnification that fits on the screen. This is the default.
	Any numeric value — Specify the magnification as a percentage. One hundred per cent magnification means that there should be one screen pixel for every image pixel
	'fit' — Scale the image so that it fits into the window in its entirety.
	You can override this this preference by specifying the 'InitialMagnification' parameter when you call imtool.

Example

iptsetpref('ImshowBorder','tight')

iptsetpref

See Also

imshow, imtool, iptgetpref, truesize

axis in the MATLAB Function Reference


Purpose Align figure windows

Syntax iptwindowalign(fixed_fig,fixed_fig_edge,... moving_fig,moving_fig_edge)

Description

iptwindowalign(fixed_fig, fixed_fig_edge, moving_fig,... moving_fig_edge) moves the figure, moving_fig, to align it with the figure fixed_fig. moving_fig and fixed_fig are handles to figure objects.

fixed_fig_edge and moving_fig_edge describe the alignment of the figures in relation to their edges and can take any of the following values: 'left', 'right', 'hcenter', 'top', 'bottom', or 'vcenter'. 'hcenter' means center horizontally and 'vcenter' means center vertically. The following figure shows these alignments.



Notes

The two specified locations must be consistent in terms of their direction. For example, you cannot specify 'left' for fixed_fig_edge and 'bottom' for moving_fig_edge.

iptwindowalign

iptwindowalign constrains the position adjustment of moving_fig to keep it entirely visible on the screen.

Examples

Create two figures: fig1 and fig2.

```
fig1 = figure;
fig2 = figure;
```

Move fig2 so its left edge is aligned with the right edge of fig1.

```
iptwindowalign(fig1,'right',fig2,'left');
```

Move fig2 so its top edge is aligned with fig1's bottom edge, and then move it so the two figures are vertically centered.

```
iptwindowalign(fig1, 'bottom', fig2, 'top');
imwindowalign(fig1, 'vcenter', fig2, 'vcenter')pt
```

See Also

imtool

Purpose

Compute inverse Radon transform

Syntax

```
I = iradon(R,theta)
I = iradon(R,theta,interp,filter,frequency_scaling,output_size)
[I,H] = iradon(...)
```

Description

I = iradon(R, theta) reconstructs the image I from projection data in the two-dimensional array R. The columns of R are parallel beam projection data. iradon assumes that the center of rotation is the center point of the projections, which is defined as ceil(size(R,1)/2).

theta describes the angles (in degrees) at which the projections were taken. It can be either a vector containing the angles or a scalar specifying D_theta, the incremental angle between projections. If theta is a vector, it must contain angles with equal spacing between them. If theta is a scalar specifying D_theta, the projections were taken at angles theta = $m*D_theta$, where $m = 0, 1, 2, \ldots, size(R, 2)-1$. If the input is the empty matrix ([]), D_theta defaults to 180/size(R, 2).

iradon uses the filtered back-projection algorithm to perform the inverse Radon transform. The filter is designed directly in the frequency domain and then multiplied by the FFT of the projections. The projections are zero-padded to a power of 2 before filtering to prevent spatial domain aliasing and to speed up the FFT.

I = iradon(P, theta, interp, filter, frequency_scaling, output_size) specifies parameters to use in the inverse Radon transform. You can specify any combination of the last four arguments. iradon uses default values for any of these arguments that you omit.

interp specifies the type of interpolation to use in the back projection. The available options are listed in order of increasing accuracy and computational complexity. The default value is enclosed in braces ({}).

Value	Description
'nearest'	Nearest-neighbor interpolation

Value	Description
{'linear'}	Linear interpolation
'spline'	Spline interpolation

filter specifies the filter to use for frequency domain filtering. filter can be any of the strings that specify standard filters. The default value is enclosed in braces ({}).

Value	Description
{'Ram-Lak'}	Cropped Ram-Lak or ramp filter. The frequency response of this filter is f . Because this filter is sensitive to noise in the projections, one of the filters listed below might be preferable. These filters multiply the Ram-Lak filter by a window that deemphasizes high frequencies.
'Shepp-Logan'	Multiplies the Ram-Lak filter by a sinc function
'Cosine'	Multiplies the Ram-Lak filter by a cosine function
'Hamming'	Multiplies the Ram-Lak filter by a Hamming window
'Hann'	Multiplies the Ram-Lak filter by a Hann window

frequency_scaling is a scalar in the range (0,1] that modifies the filter by rescaling its frequency axis. The default is 1. If frequency_scaling is less than 1, the filter is compressed to fit into the frequency range [0,frequency_scaling], in normalized frequencies; all frequencies above frequency_scaling are set to 0.

output_size is a scalar that specifies the number of rows and columns in the reconstructed image. If output_size is not specified, the size is determined from the length of the projections.

```
n = 2*floor(size(R,1)/(2*sqrt(2)))
```

If you specify output_size, iradon reconstructs a smaller or larger portion of the image but does not change the scaling of the data. If the projections were

calculated with the radon function, the reconstructed image might not be the same size as the original image.

[I,H] = iradon(...) returns the frequency response of the filter in the vector H.


Class Support

R can be double or single. All other numeric input arguments must be of class double. I has the same class as R. H is double.

Example

```
P = phantom(128);
R = radon(P,0:179);
I = iradon(R,0:179, 'nearest', 'Hann');
imshow(P), figure, imshow(I)
```





Algorithm

iradon uses the filtered back projection algorithm to perform the inverse Radon transform. The filter is designed directly in the frequency domain and then multiplied by the FFT of the projections. The projections are zero-padded to a power of 2 before filtering to prevent spatial domain aliasing and to speed up the FFT.

See Also

fan2para, fanbeam, ifanbeam, para2fan, phantom, radon

References

[1] Kak, A. C., and M. Slaney, *Principles of Computerized Tomographic Imaging*, New York, NY, IEEE Press, 1988.

isbw

Purpose Return true for a binary image

Note This function is obsolete and may be removed in future versions. Use

islogical instead.

Syntax flag = isbw(A)

Description flag = isbw(A) returns 1 if A is a binary image and 0 otherwise.

The input image A is considered to be a binary image if it is a nonsparse logical

array.

Class Support The input image A can be any MATLAB array.

See Also isind, isgray, isrgb

isflat

Purpose Return true for flat structuring element

Syntax TF = isflat(SE)

Description TF = isflat(SE) returns true (1) if the structuring element SE is flat;

otherwise it returns false (0). If SE is an array of STREL objects, then TF is the

same size as SE.

Class Support SE is a STREL object. TF is a double-precision value.

See Also strel

isgray

Purpose

Return true for intensity image

Note This function is obsolete and may be removed in future versions.

Syntax

flag = isgray(A)

Description

flag = isgray(A) returns 1 if A is a grayscale intensity image and 0 otherwise. isgray uses these criteria to decide whether A is an intensity image:

- If A is of class double, all values must be in the range [0,1], and the number of dimensions of A must be 2.
- If A is of class uint16 or uint8, the number of dimensions of A must be 2.

Note A four-dimensional array that contains multiple intensity images returns 0, not 1.

Class Support

The input image A can be of class logical, uint8, uint16, or double.

See Also

isbw, isind, isrgb

Purpose

Return true for valid ICC color profile

Syntax

TF = isicc(P)

Description

TF = isicc(P) returns True if structure P is a valid ICC color profile; otherwise False.

isicc checks if P has a complete set of the tags required for an ICC profile. P must contain a Header field, which in turn must contain a Version field and a DeviceClass field. These fields, and others, are used to determine the set of required tags according to the ICC Profile Specification, either Version 2 (ICC.1:2001-04) or Version 4 (ICC.1:2001-12), which are available at www.color.org. The set of required tags is given in Section 6.3 in either version.

Example

Read in a profile and test its validity.

```
P = iccread('sRGB.icm');
TF = isicc(P)
TF =
1
```

Create a MATLAB structure and test its validity.

```
S.name = 'Any Student';
S.score = 83;
S.grade = 'B+'

TF = isicc(S)

TF =
0
```

See Also

applycform, iccread, iccwrite, makecform

isind

Purpose

Return true for an indexed image

Note This function is obsolete and may be removed in future versions.

Syntax

flag = isind(A)

Description

flag = isind(A) returns 1 if A is an indexed image and 0 otherwise.

isind uses these criteria to determine if A is an indexed image:

- If A is of class double, all values in A must be integers greater than or equal to 1, and the number of dimensions of A must be 2.
- If A is of class uint8 or uint16, the number of dimensions of A must be 2.

Note A four-dimensional array that contains multiple indexed images returns 0, not 1.

Class Support

A can be of class logical, uint8, uint16, or double.

See Also

isbw, isgray, isrgb

Purpose

Return true for an RGB image

Note This function is obsolete and may be removed in future versions.

Syntax

flag = isrgb(A)

Description

flag = isrgb(A) returns 1 if A is an RGB truecolor image and 0 otherwise.

isrgb uses these criteria to determine whether A is an RGB image:

- If A is of class double, all values must be in the range [0,1], and A must be m-by-n-by-3.
- If A is of class uint16 or uint8, A must be m-by-n-by-3.

Note A four-dimensional array that contains multiple RGB images returns 0, not 1.

Class Support

A can be of class logical, uint8, uint16, or double.

See Also

isbw, isgray, isind

lab2double

Purpose

Convert $L^*a^*b^*$ data to double

Syntax

labd = lab2double(lab)

Description

labd = lab2double(lab) converts an M-by-3 or M-by-N-by-3 array of $L^*a^*b^*$ color values to class double. The output array labd has the same size as lab.

The Image Processing Toolbox follows the convention that double-precision $L^*a^*b^*$ arrays contain 1976 CIE $L^*a^*b^*$ values. $L^*a^*b^*$ arrays that are uint8 or uint16 follow the convention in the ICC profile specification (ICC.1:2001-4, www.color.org) for representing $L^*a^*b^*$ values as unsigned 8-bit or 16-bit integers. The ICC encoding convention is illustrated by these tables.

Value (L*)	uint8 Value	uint16 Value
0.0	0	0
100.0	255	65280
100.0 + (25500/65280)	None	65535

Value (a* or b*)	uint8 Value	uint16 Value
-128.0	0	0
0.0	128	32768
127.0	255	65280
127.0 + (255/256)	None	65535

Class Support

lab is a uint8, uint16, or double array that must be real and nonsparse. labd is double.

Example

Convert full intensity neutral color (white) from uint8 to double.

```
lab2double(uint8([255 128 128]))
ans =
```

lab2double

100 0 0

See Also

applycform, lab2uint8, lab2uint16, makecform, whitepoint, xyz2double, xyz2uint16

lab2uint16

Purpose Convert $L^*a^*b^*$ data to uint 16

Syntax lab16 = lab2uint16(lab)

Description

lab16 = lab2uint16(lab) converts an M-by-3 or M-by-N-by-3 array of $L^*a^*b^*$ color values to uint16. lab16 has the same size as lab.

The Image Processing Toolbox follows the convention that double-precision $L^*a^*b^*$ arrays contain 1976 CIE $L^*a^*b^*$ values. $L^*a^*b^*$ arrays that are uint8 or uint16 follow the convention in the ICC profile specification (ICC.1:2001-4, www.color.org) for representing $L^*a^*b^*$ values as unsigned 8-bit or 16-bit integers. The ICC encoding convention is illustrated by these tables.

Value (L*)	uint8 Value	uint16 Value
0.0	0	0
100.0	255	65280
100.0 + (25500/65280)	None	65535

Value (a* or b*)	uint8 Value	uint16 Value
-128.0	0	0
0.0	128	32768
127.0	255	65280
127.0 + (255/256)	None	65535

Class Support

lab can be a uint8, uint16, or double array that must be real and nonsparse. lab16 is of class uint16.

Example

Convert full intensity neutral color (white) from double to uint16.

lab2uint16(100 0 0) ans =

65280 32768 32768

lab2uint16

See Also

applycform, lab2double, lab2uint8, makecform, whitepoint, xyz2double, xyz2uint16

lab2uint8

Purpose Convert I

Convert $L^*a^*b^*$ data to uint8

Syntax

lab8 = lab2uint8(lab)

Description

lab8 = lab2uint8(lab) converts an M-by-3 or M-by-N-by-3 array of L*a*b* color values to uint8. lab8 has the same size as lab.

The Image Processing Toolbox follows the convention that double-precision $L^*a^*b^*$ arrays contain 1976 CIE $L^*a^*b^*$ values. $L^*a^*b^*$ arrays that are uint8 or uint16 follow the convention in the ICC profile specification (ICC.1:2001-4, www.color.org) for representing $L^*a^*b^*$ values as unsigned 8-bit or 16-bit integers. The ICC encoding convention is illustrated by these tables.

Value (L*)	uint8 Value	uint16 Value
0.0	0	0
100.0	255	65280
100.0 + (25500/65280)	None	65535

Value (a* or b*)	uint8 Value	uint16 Value
-128.0	0	0
0.0	128	32768
127.0	255	65280
127.0 + (255/256)	None	65535

Class Support

lab is a uint8, uint16, or double array that must be real and nonsparse. lab8 is uint8.

Example

Convert full intensity neutral color (white) from double to uint8.

lab2uint8(100 0 0) ans =

255 128 128

lab2uint8

See Also

applycform, lab2double, lab2uint16, makecform, whitepoint, xyz2double, xyz2uint16

label2rgb

Purpose

Convert a label matrix into an RGB image

Syntax

RGB = label2rgb(L)

RGB = label2rgb(L, map)

RGB = label2rgb(L,map,zerocolor)

RGB = label2rgb(L,map,zerocolor,order)

Description

RGB = label2rgb(L) converts a label matrix L, such as those returned by bwlabel or watershed, into an RGB color image for the purpose of visualizing the labeled regions. The label2rgb function determines the color to assign to each object based on the number of objects in the label matrix and range of colors in the colormap. The label2rgb function picks colors from the entire range.

RGB = label2rgb(L,map) defines the colormap map to be used in the RGB image. map can have any of the following values:

- *n*-by-3 colormap matrix
- String containing the name of a MATLAB colormap function, such as 'jet' or 'gray' (See colormap for a list of supported colormaps.)
- Function handle of a colormap function, such as @jet or @gray

If you do not specify map, the default value is 'jet'.

RGB = label2rgb(L,map,zerocolor) defines the RGB color of the elements labeled 0 (zero) in the input label matrix L. As the value of zerocolor, specify an RGB triple or one of the strings listed in this table.

Value	Color
'b'	Blue
' C '	Cyan
'g'	Green
'k'	Black
' m '	Magenta
'r'	Red

Value Color	
'w'	White
' y '	Yellow

If you do not specify zerocolor, the default value for zero-labeled elements is [1 1 1] (white).


RGB = label2rgb(L,map,zerocolor,order) controls how label2rgb assigns colormap colors to regions in the label matrix. If order is 'noshuffle' (the default), label2rgb assigns colormap colors to label matrix regions in numerical order. If order is 'shuffle', label2rgb assigns colormap colors pseudorandomly.

Class Support

The input label matrix L can have any nonsparse, numeric class. It must contain finite, nonnegative integers. The output of label2rgb is of class uint8.

Example

```
I = imread('rice.png');
figure, imshow(I), title('original image')
BW = im2bw(I, graythresh(I));
L = bwlabel(BW);
RGB = label2rgb(L);
RGB2 = label2rgb(L, 'spring', 'c', 'shuffle');
imshow(RGB), figure, imshow(RGB2)
```



See Also

bwlabel, colormap, ismember, watershed

makecform

Purpose

Create a color transformation structure

Syntax

Description

C = makecform(type) creates the color transformation structure C that defines the color space conversion specified by type. To perform the transformation, pass the color transformation structure as an argument to the applycform function.

The type argument specifies one of the conversions listed in the following table. makecform supports conversions between members of the family of device-independent color spaces defined by the CIE, *Commission Internationale de l'Éclairage* (International Commission on Illumination). In addition, makecform supports conversions to and from the sRGB standard. For a list of the abbreviations used by the Image Processing Toolbox for each color space, see the Remarks section of this reference page.

Туре	Description
'lab2lch'	Convert from $L^*a^*b^*$ to the L^*ch color space.
'lab2srgb' ¹	Convert from $L^*a^*b^*$ to the $srgb$ color space.
'lab2xyz' ¹	Convert from $L^*a^*b^*$ to the XYZ color space.
'lch2lab'	Convert from L^*ch to the $L^*a^*b^*$ color space.
'srgb2lab' ¹	Convert from $srgb$ to the $L^*a^*b^*$ color space.
'srgb2xyz'	Convert from $srgb$ to the XYZ color space.
'upvpl2xyz'	Convert from $u'v'L$ to the XYZ color space.
'uv12xyz'	Convert from uvL to the XYZ color space.

Туре	Description
'xyl2xyz'	Convert from xyY to the XYZ color space.
'xyz2lab' ¹	Convert from XYZ to the $L^*a^*b^*$ color space.
'xyz2srgb'	Convert from XYZ to the $srgb$ color space.
'xyz2upvpl'	Convert from XYZ to the $u'v'L$ color space.
'xyz2uvl'	Convert from XYZ to the uvL color space.
'xyz2xyl'	Convert from XYZ to the xyY color space.

¹ For the 'xyz2lab', 'lab2xyz', 'srgb2lab', and 'lab2srgb' transforms, you can optionally specify the value of the reference illuminant, known as the white point. Use the syntax

C = makecform(type,'WhitePoint', WP)

where WP is a 1-by-3 vector of XYZ values scaled so that Y=1. The default is the CIE illuminant D50 as specified in the International Color Consortium specification ICC.1:2001-04. You can use the whitepoint function to create the WP vector.

C = makecform('icc', src_profile, dest_profile) creates a color transform based on two ICC profiles. src_profile and dest_profile are ICC profile structures returned by iccread.

C = makecform('icc', src_profile, dest_profile,
'SourceRenderingIntent', src_intent, 'DestRenderingIntent',
DEST_INTENT) creates a color transform based on two ICC color profiles,
src_profile and dest_profile, specifying rendering intent arguments for the
source, src_intent, and the destination, dest_intent, profiles.

Rendering intents specify the style of reproduction that should be used when these profiles are combined. For most devices, the range of reproducible colors is much smaller than the range of colors represented by the PCS. Rendering intents define gamut mapping techniques. Possible values for these rendering

makecform

intents are listed below. Each rendering intent has distinct aesthetic and color-accuracy tradeoffs.

Value	Description
'AbsoluteColorimetric'	Maps all out-of-gamut colors to the nearest gamut surface while maintaining the relationship of all in-gamut colors. This absolute rendering contains color data that is relative to a perfectly reflecting diffuser.
'Perceptual' (default)	Employs vendor-specific gamut mapping techniques for optimizing the range of producible colors of a given device. The objective is to provide the most aesthetically pleasing result even though the relationship of the in-gamut colors might not be maintained. This media-relative rendering contains color data that is relative to the device's white point.
'RelativeColorimetric'	Maps all out-of-gamut colors to the nearest gamut surface while maintaining the relationship of all in-gamut colors. This media-relative rendering contains color data that is relative to the device's white point.
'Saturation'	Employs vendor-specific gamut mapping techniques for maximizing the saturation of device colors. This rendering is generally used for simple business graphics such as bar graphs and pie charts. This media-relative rendering contains color data that is relative to the device's white point.

C = makecform('clut', profile, LUTtype) creates the color transformation structure C based on a color lookup table (CLUT) contained in an ICC color profile. profile is an ICC profile structure returned by iccread. LUTtype

specifies which clut in the profile structure is to be used. It can be one of these strings.

LUT Type	Description
'AToB0'	Contains the components of a 16- or 8-bit LUTtag that transforms device colors to PCS colors using the perceptual rendering.
'AToB1'	Contains the components of a 16- or 8-bit LUTtag that transforms device colors to PCS colors using the relative rendering.
'AToB2'	Contains the components of a 16- or 8-bit LUTtag that transforms device colors to PCS colors using the saturation rendering.
'BToA0'	Contains the components of a 16- or 8-bit LUTtag that transforms PCS colors to device colors using the perceptual rendering.
'BToA1'	Contains the components of a 16- or 8-bit LUTtag that transforms PCS colors to device colors using the colorimetric rendering.
'BT0A2'	Contains the components of a 16- or 8-bit LUTtag that transforms PCS colors to device colors using the saturation rendering.
'Gamut'	Contains the components of a 16- or 8-bit LUTtag that determines which PCS colors are out of gamut for a given device.
'PreviewO'	Contains the components of a 16- or 8-bit Preview LUTtag that transforms PCS colors to the PCS colors available for soft proofing using the perceptual rendering.

LUT Type	Description
'Preview1'	Contains the components of a 16- or 8-bit Preview LUTtag that transforms PCS colors to the PCS colors available for soft proofing using the relative colorimetric rendering.
'Preview2'	Contains the components of a 16- or 8-bit Preview LUTtag that transforms PCS colors to the PCS colors available for soft proofing using the saturation rendering.

C = makecform('mattrc', MatTrc, 'Direction', direction) creates the color transformation structure C based on a Matrix/Tone Reproduction Curve (MatTRC) model, contained in an ICC color profile. direction can be either 'forward' or 'inverse' and specifies whether the MatTRC is to be applied in the forward or inverse direction. For more information, see section 6.3.1.2 of the International Color Consortium specification ICC.1:2001-04 (www.color.org).

Remarks

The Image Processing Toolbox uses the following abbreviations to represent color spaces.

Abbreviation	Description
xyz	1931 CIE XYZ tristimulus values (2° observer)
xyl	1931 CIE xyY chromaticity values (2° observer)
uvl	1960 CIE uvL values
upvpl	1976 CIE the $u'v'L$ values
lab	1976 CIE $L^*a^*b^*$ values
lch	Polar transformation of CIE $L^*a^*b^*$ values, where c = chroma and h = hue
srgb	Standard computer monitor RGB values, (IEC 61966-2-1)

```
Example Convert RGB image to L^*a^*b^*, assuming input image is uint8.
```

```
rgb = imread('peppers.png');
cform = makecform('srgb2lab');
lab = applycform(rgb,cform);
```

See Also

applycform, iccread, iccwrite, isicc, lab2double, lab2uint16, lab2uint8, whitepoint, xyz2double, xyz2uint16

makelut

Purpose

Construct a lookup table for use with applylut

Syntax

lut = makelut(fun,n)

Description

lut = makelut(fun,n) returns a lookup table for use with applylut. fun is a function that accepts an *n*-by-*n* matrix of 1's and 0's as input and return a scalar. n can be either 2 or 3. makelut creates lut by passing all possible 2-by-2 or 3-by-3 neighborhoods to fun, one at a time, and constructing either a 16-element vector (for 2-by-2 neighborhoods) or a 512-element vector (for 3-by-3 neighborhoods). The vector consists of the output from fun for each possible neighborhood.

fun must be a function handle.

Class Support

lut is returned as a vector of class double.

Example

In this example, the function returns 1 (true) if the number of 1's in the neighborhood is 2 or greater, and returns 0 (false) otherwise. makelut then uses the function to construct a lookup table for 2-by-2 neighborhoods.

1

makelut

1

See Also applylut

makeresampler

Purpose Create resampling structure

Syntax R = makeresampler(interpolant, padmethod)

DescriptionR = makeresampler(interpolant,padmethod) creates a separable resampler structure for use with tformarray and imtransform.

The interpolant argument specifies the interpolating kernel that the separable resampler uses. In its simplest form, interpolant can have any of the following strings as a value.

Interpolant	Description
'cubic'	Cubic interpolation
'linear'	Linear interpolation
'nearest'	Nearest-neighbor interpolation

If you are using a custom interpolating kernel, you can specify interpolant as a cell array in either of these forms:

To specify the interpolation method independently along each dimension, you can combine both types of interpolant specifications. The number of elements in the cell array must equal the number of transform dimensions. For example, if you specify this value for interpolant

```
{'nearest', 'linear', {2 KERNEL_TABLE}}
```

makeresampler

the resampler uses nearest-neighbor interpolation along the first transform dimension, linear interpolation along the second dimension, and a custom table-based interpolation along the third.

The padmethod argument controls how the resampler interpolates or assigns values to output elements that map close to or outside the edge of the input array. The following table lists all the possible values of padmethod.

Pad Method	Description
'bound'	Assigns values from the fill value array to points that map outside the array and repeats border elements of the array for points that map inside the array (same as 'replicate'). When interpolant is 'nearest', this pad method produces the same results as 'fill'. 'bound' is like 'fill', but avoids mixing fill values and input image values.
'circular'	Pads array with circular repetition of elements within the dimension. Same as padarray.
'fill'	Generates an output array with smooth-looking edges (except when using nearest-neighbor interpolation). For output points that map near the edge of the input array (either inside or outside), it combines input image and fill values. When interpolant is 'nearest', this pad method produces the same results as 'bound'.
'replicate'	Pads array by repeating border elements of array. Same as padarray.
'symmetric'	Pads array with mirror reflections of itself. Same as padarray.

In the case of 'fill', 'replicate', 'circular', or 'symmetric', the resampling performed by tformarray or imtransform occurs in two logical steps:

1 Pad the array A infinitely to fill the entire input transform space.

makeresampler

2 Evaluate the convolution of the padded A with the resampling kernel at the output points specified by the geometric map.

Each nontransform dimension is handled separately. The padding is virtual, (accomplished by remapping array subscripts) for performance and memory efficiency. If you implement a custom resampler, you can implement these behaviors.

Custom Resamplers

The syntaxes described above construct a resampler structure that uses the separable resampler function that ships with the Image Processing Toolbox. It is also possible to create a resampler structure that uses a user-written resampler by using this syntax:

R = makeresampler(PropertyName, PropertyValue,...)

The makeresampler function supports the following properties.

Property	Description
'Type'	Can have the value 'separable' or 'custom' and must always be supplied. If 'Type' is 'separable', the only other properties that can be specified are 'Interpolant' and 'PadMethod', and the result is equivalent to using the makeresampler(interpolant,padmethod) syntax. If 'Type' is 'custom', you must specify the 'NDims' and 'ResampleFcn' properties and, optionally, the 'CustomData' property.
'PadMethod'	See the padmethod argument for more information.
'Interpolant'	See the interpolant argument for more information.
'NDims'	Positive integer indicating the dimensionality the custom resampler can handle. Use a value of Inf to indicate that the custom resampler can handle any dimension. If 'Type' is 'custom', NDims is required.

	Description
'ResampleFcn'	Handle to a function that performs the resampling. The function is called with the following interface.
	<pre>B = resample_fcn(A,M,TDIMS_A,TDIMS_B,FSIZE_A,FSIZE_B,F,R)</pre>
	See the help for tformarray for information about the inputs A, TDIMS_A, TDIMS_B, and F. The argument M is an array that maps the transform subscript space of B to the transform subscript space of A. If A has N transform dimensions (N = length(TDIMS_A)) and B has P transform dimensions (P = length(TDIMS_B)), then $ndims(M) = P + 1$, if N > 1 and P if N == 1, and $size(M,P + 1) = N$.
	The first P dimensions of M correspond to the output transform space, permuted according to the order in which the output transform dimensions are listed in TDIMS_B. (In general TDIMS_A and TDIMS_B need not be sorted in ascending order, although such a limitation might be imposed by specific resamplers.) Thus, the first P elements of size(M) determine the sizes of the transform dimensions of B. The input transform coordinates to which each point is mapped are arrayed across the final dimension of M, following the order given in TDIMS_A. M must be double. FSIZE_A and FSIZE_B are the full sizes of A and B, padded with 1's as necessary to be consistent with TDIMS_A. TDIMS_B, and size(A).
'CustomData'	User-defined.

Stretch an image in the *y*-direction using a separable resampler that applies cubic interpolation in the *y*-direction and nearest-neighbor interpolation in the *x*-direction. (This is equivalent to, but faster than, applying bicubic interpolation.)

```
A = imread('moon.tif');
resamp = makeresampler({'nearest','cubic'},'fill');
stretch = maketform('affine',[1 0; 0 1.3; 0 0]);
B = imtransform(A,stretch,resamp);
```

See Also

imtransform, tformarray

maketform

Purpose

Create geometric transformation structure

Syntax

T = maketform(transformtype,...)

Description

T = maketform(transformtype,...) creates a multidimensional spatial transformation structure (called a TFORM struct) that can be used with the tformfwd, tforminv, fliptform, imtransform, or tformarray functions.

transformtype can be any of the following spatial transformation types. maketform supports a special syntax for each transformation type. See the following sections for information about these syntaxes.

Transform Type	Description
'affine'	Affine transformation in 2-D or N-D
'projective'	Projective transformation in 2-D or N-D
'custom'	User-defined transformation that can be N-D to M-D
'box'	Independent affine transformation (scale and shift) in each dimension
'composite'	Composition of an arbitrary number of more basic transformations

Transform Types

Affine

T = maketform('affine',A) builds a TFORM struct T for an N-dimensional affine transformation. A is a nonsingular real (N+1)-by-(N+1) or (N+1)-by-N matrix. If A is (N+1)-by-(N+1), the last column of A must be [zeros(N,1);1]. Otherwise, A is augmented automatically, such that its last column is [zeros(N,1);1]. The matrix A defines a forward transformation such that tformfwd(U,T), where U is a 1-by-N vector, returns a 1-by-N vector X, such that X = U * A(1:N,1:N) + A(N+1,1:N). T has both forward and inverse transformations.

T = maketform('affine',U,X) builds a TFORM struct T for a two-dimensional affine transformation that maps each row of U to the corresponding row of X.

The U and X arguments are each 3-by-2 and define the corners of input and output triangles. The corners cannot be collinear.

Projective

T = maketform('projective',A) builds a TFORM struct for an N-dimensional projective transformation. A is a nonsingular real (N+1)-by-(N+1) matrix. A (N+1,N+1) cannot be 0. The matrix A defines a forward transformation such that tformfwd(U,T), where U is a 1-by-N vector, returns a 1-by-N vector X, such that X = W(1:N)/W(N+1), where $W = [U \ 1] * A$. The transformation structure T has both forward and inverse transformations.

T = maketform('projective',U,X) builds a TFORM struct T for a two-dimensional projective transformation that maps each row of U to the corresponding row of X. The U and X arguments are each 4-by-2 and define the corners of input and output quadrilaterals. No three corners can be collinear.

Custom

```
T = maketform('custom',NDIMS_IN,NDIMS_OUT,...
FORWARD_FCN,INVERSE_FCN,TDATA) builds a custom TFORM
struct T based on user-provided function handles and parameters. NDIMS_IN
and NDIMS_OUT are the numbers of input and output dimensions. FORWARD_FCN
and INVERSE_FCN are function handles to forward and inverse functions. Those
functions must support the following syntaxes:
```

```
Forward function: X = FORWARD\_FCN(U,T)
Inverse function: U = INVERSE\ FCN(X,T)
```

where U is a P-by-NDIMS_IN matrix whose rows are points in the transformation's input space, and X is a P-by-NDIMS_OUT matrix whose rows are points in the transformation's output space. The TDATA argument can be any MATLAB array and is typically used to store parameters of the custom transformation. It is accessible to FORWARD_FCN and INVERSE_FCN via the tdata field of T. Either FORWARD_FCN or INVERSE_FCN can be empty, although at least INVERSE_FCN must be defined to use T with tformarray or imtransform.

Box

```
T = maketform('box',tsize,LOW,HIGH) or
T = maketform('box',INBOUNDS, OUTBOUNDS) builds an N-dimensional affine
```

TFORM struct T. The tsize argument is an N-element vector of positive integers. LOW and HIGH are also N-element vectors. The transformation maps an input box defined by the opposite corners ones(1,N) and tsize or, alternatively, by corners INBOUNDS(1,:) and INBOUND(2,:) to an output box defined by the opposite corners LOW and HIGH or OUTBOUNDS(1,:) and OUTBOUNDS(2,:). LOW(K) and HIGH(K) must be different unless tsize(K) is 1, in which case the affine scale factor along the Kth dimension is assumed to be 1.0. Similarly, INBOUNDS(1,K) and INBOUNDS(2,K) must be different unless OUTBOUNDS(1,K) and OUTBOUNDS(2,K) are the same, and vice versa. The 'box' TFORM is typically used to register the row and column subscripts of an image or array to some world coordinate system.

Composite

```
T = maketform('composite', T1, T2, ..., TL) or
T = maketform('composite', [T1 T2 ... TL]) builds a TFORM struct T whose forward and inverse functions are the functional compositions of the forward and inverse functions of T1, T2, ..., TL.
```

For example, if L=3, then tformfwd(U,T) is the same as tformfwd(tformfwd(tformfwd(U,T3),T2),T1). The components T1 through TL must be compatible in terms of the numbers of input and output dimensions. T has a defined forward transform function only if all the component transforms have defined forward transform functions. T has a defined inverse transform function only if all the component functions have defined inverse transform functions.

Example

Make and apply an affine transformation.

```
T = maketform('affine',[.5 0 0; .5 2 0; 0 0 1]);
tformfwd([10 20],T)
I = imread('cameraman.tif');
I2 = imtransform(I,T);
imshow(I), figure, imshow(I2)
```

See Also

tformfwd, tforminv, fliptform, imtransform, tformarray

Purpose Convert a matrix to a grayscale intensity image

Syntax I = mat2gray(A,[amin amax])

I = mat2gray(A)

Description I = mat2gray(A, [amin amax]) converts the matrix A to the intensity image I.

The returned matrix I contains values in the range 0.0 (black) to 1.0 (full intensity or white). amin and amax are the values in A that correspond to 0.0 and

1.0 in I.

I = mat2gray(A) sets the values of amin and amax to the minimum and

maximum values in A.


Class Support The input array A can be logical or numeric. The output image I is double.

J = filter2(fspecial('sobel'),I);

K = mat2gray(J);

imshow(I), figure, imshow(K)





See Also gray2ind

mean2

Purpose Compute the mean of the elements of a matrix

Syntax B = mean2(A)

Description B = mean2(A) computes the mean of the values in A.

Class Support The input image A can be numeric or logical. The output image B is a scalar

of class double.

Algorithm mean 2 computes the mean of an array A using mean(A(:)).

See Also std2

mean, std in the MATLAB Function Reference

Purpose

Perform two-dimensional median filtering

Syntax

```
B = medfilt2(A,[m n])
```

B = medfilt2(A)

B = medfilt2(A, 'indexed',...)

Description

Median filtering is a nonlinear operation often used in image processing to reduce "salt and pepper" noise. Median filtering is more effective than convolution when the goal is to simultaneously reduce noise and preserve edges.

B = medfilt2(A, [m n]) performs median filtering of the matrix A in two dimensions. Each output pixel contains the median value in the m-by-n neighborhood around the corresponding pixel in the input image. medfilt2 pads the image with 0's on the edges, so the median values for the points within [m n]/2 of the edges might appear distorted.

B = medfilt2(A) performs median filtering of the matrix A using the default 3-by-3 neighborhood.

B = medfilt2(A, 'indexed',...) processes A as an indexed image, padding with 0's if the class of A is uint8, or 1's if the class of A is double.

Class Support

The input image A can be of class logical, uint8, uint16, or double (unless the 'indexed' syntax is used, in which case A cannot be of class uint16). The output image B is of the same class as A.

Note For information about performance considerations, see ordfilt2.

Remarks

If the input image A is of an integer class, all the output values are returned as integers. If the number of pixels in the neighborhood (i.e., m*n) is even, some of the median values might not be integers. In these cases, the fractional parts are discarded. Logical input is treated similarly.

For example, suppose you call medfilt2 using 2-by-2 neighborhoods, and the input image is a uint8 array that includes this neighborhood.

1 5


4 8

medfilt2 returns an output value of 4 for this neighborhood, although the true median is 4.5.

Example

This example adds salt and pepper noise to an image, then restores the image using medfilt2.

```
I = imread('eight.tif');
J = imnoise(I, 'salt & pepper',0.02);
K = medfilt2(J);
imshow(J), figure, imshow(K)
```





Algorithm

medfilt2 uses ordfilt2 to perform the filtering.

See Also

filter2, ordfilt2, wiener2

Reference

[1] Lim, Jae S., *Two-Dimensional Signal and Image Processing*, Englewood Cliffs, NJ, Prentice Hall, 1990, pp. 469-476.

Purpose

Display multiple image frames as a rectangular montage

Syntax

montage(I)
montage(BW)
montage(X,map)
montage(RGB)
h = montage(...)

Description

montage displays all the frames of a multiframe image array in a single image object, arranging the frames so that they roughly form a square.

montage(I) displays the k frames of the intensity image array I. I is m-by-n-by-1-by-k.

montage(BW) displays the k frames of the binary image array BW. BW is m-by-n-by-1-by-k.

montage(X,map) displays the k frames of the indexed image array X, using the colormap map for all frames. X is m-by-n-by-1-by-k.

montage(RGB) displays the k frames of the truecolor image array RGB. RGB is m-by-n-by-3-by-k.

h = montage(...) returns the handle to the image object.


Class Support

An intensity image can be logical, uint8, uint16, int16, single, or double. An indexed image can be logical, uint8, uint16, single, or double. The map must be double. A truecolor image can be uint8, uint16, single, or double. The output is a handle to the graphics objects produced by this function.

Example

load mri
montage(D,map)

montage



See Also

immovie

Purpose

Perform general sliding-neighborhood operations

Syntax

```
B = nlfilter(A,[m n],fun)
B = nlfilter(A,'indexed',...)
```

Description

B = nlfilter(A, [m n], fun) applies the function fun to each m-by-n sliding block of A. fun is a function that accepts an m-by-n matrix as input and returns a scalar result.

```
c = fun(x)
```

fun must be a function handle.

c is the output value for the center pixel in the m-by-n block x. nlfilter calls fun for each pixel in A. nlfilter zero-pads the m-by-n block at the edges, if necessary.

B = nlfilter(A, 'indexed',...) processes A as an indexed image, padding with 1's if A is of class double and 0's if A is of class uint8.

Class Support

The input image A can be of any class supported by fun. The class of B depends on the class of the output from fun.

Remarks

nlfilter can take a long time to process large images. In some cases, the colfilt function can perform the same operation much faster.

Example

This example produces the same result as calling medfilt2 with a 3-by-3 neighborhood.

```
A = imread('cameraman.tif');
fun = @(x) median(x(:));
B = nlfilter(A,[3 3],fun);
imshow(A), figure, imshow(B)
```

See Also

blkproc, colfilt, function handle

Purpose

Normalized two-dimensional cross-correlation

Syntax

C = normxcorr2(TEMPLATE, A)

Description

C = normxcorr2(TEMPLATE,A) computes the normalized cross-correlation of the matrices TEMPLATE and A. The matrix A must be larger than the matrix TEMPLATE for the normalization to be meaningful. The values of TEMPLATE cannot all be the same. The resulting matrix C contains the correlation coefficients, which can range in value from -1.0 to 1.0.

Class Support

The input matrices can be of class uint8, uint16, or double.

Algorithm

normxcorr2 uses the following general procedure:

- 1 Calculate cross-correlation in the spatial or the frequency domain, depending on size of images.
- **2** Calculate local sums by precomputing running sums. [1]
- **3** Use local sums to normalize the cross-correlation to get correlation coefficients. [2]

Example

```
T = .2*ones(11); % make light gray plus on dark gray background
T(6,3:9) = .6;
T(3:9,6) = .6;
                 % make white plus on black background
BW = T > 0.5:
imshow(BW), title('Binary')
figure, imshow(T), title('Template')
% make new image that offsets template T
T offset = .2*ones(21);
offset = [3 5]; % shift by 3 rows, 5 columns
T offset((1:size(T,1))+offset(1), (1:size(T,2))+offset(2)) = T;
imshow(T offset), title('Offset Template')
% cross-correlate BW and T offset to recover offset
cc = normxcorr2(BW,T offset);
[\max cc, \max] = \max(abs(cc(:)));
[ypeak, xpeak] = ind2sub(size(cc),imax(1));
corr offset = [ (ypeak-size(T,1)) (xpeak-size(T,2)) ];
isequal(corr offset,offset) % 1 means offset was recovered
```

See Also corrcoef

References [1] Lewis, J. P., "Fast Normalized Cross-Correlation," Industrial Light &

Magic,

<http://www.idiom.com/~zilla/Papers/nvisionInterface/nip.html>

[2] Haralick, Robert M., and Linda G. Shapiro, Computer and Robot Vision,

Volume II, Addison-Wesley, 1992, pp. 316-317.

ntsc2rgb

Purpose

Convert NTSC values to RGB color space

Syntax

```
rgbmap = ntsc2rgb(yiqmap)
RGB = ntsc2rgb(YIQ)
```

Description

rgbmap = ntsc2rgb(yiqmap) converts the m-by-3 NTSC (television) color values in yiqmap to RGB color space. If yiqmap is m-by-3 and contains the NTSC luminance (Y) and chrominance (I) and (I) color components as columns, then rgbmap is an m-by-3 matrix that contains the red, green, and blue values equivalent to those colors. Both rgbmap and yiqmap contain intensities in the range 0 to 1.0. The intensity 0 corresponds to the absence of the component, while the intensity 1.0 corresponds to full saturation of the component.

 $\label{eq:RGB} \mbox{{\tt RGB = ntsc2rgb\,(YIQ)}} \ converts \ the \ NTSC \ image \ YIQ \ to \ the \ equivalent \ true color \ image \ RGB.$

ntsc2rgb computes the RGB values from the NTSC components using

$$\begin{bmatrix} R \\ G \\ B \end{bmatrix} = \begin{bmatrix} 1.000 & 0.956 & 0.621 \\ 1.000 & -0.272 & -0.647 \\ 1.000 & -1.106 & 1.703 \end{bmatrix} \begin{bmatrix} Y \\ I \\ Q \end{bmatrix}$$

Class Support

The input image or colormap must be of class double. The output is of class double.

Example

Convert RGB image to NTSC and back.

```
RGB = imread('board.tif');
NTSC = rgb2ntsc(RGB);
RGB2 = ntsc2rgb(NTSC);
```

See Also

rgb2ntsc, rgb2ind, ind2rgb, ind2gray

Purpose

Perform two-dimensional order-statistic filtering

Syntax

B = ordfilt2(A,order,domain)
B = ordfilt2(A,order,domain,S)
B = ordfilt2(...,padopt)

Description

B = ordfilt2(A,order,domain) replaces each element in A by the orderth element in the sorted set of neighbors specified by the nonzero elements in domain.

B = ordfilt2(A,order,domain,S), where S is the same size as domain, uses the values of S corresponding to the nonzero values of domain as additive offsets.

B = ordfilt2(...,padopt) controls how the matrix boundaries are padded. Set padopt to 'zeros' (the default) or 'symmetric'. If padopt is 'zeros', A is padded with 0's at the boundaries. If padopt is 'symmetric', A is symmetrically extended at the boundaries.

Class Support

The class of A can be logical, uint8, uint16, or double. The class of B is the same as the class of A, unless the additive offset form of ordfilt2 is used, in which case the class of B is double.

Remarks

domain is equivalent to the structuring element used for binary image operations. It is a matrix containing only 1's and 0's; the 1's define the neighborhood for the filtering operation.

For example, B = ordfilt2(A,5,ones(3,3)) implements a 3-by-3 median filter; B = ordfilt2(A,1,ones(3,3)) implements a 3-by-3 minimum filter; and B = ordfilt2(A,9,ones(3,3)) implements a 3-by-3 maximum filter.
B = ordfilt2(A,1,[0 1 0; 1 0 1; 0 1 0]) replaces each element in A by the minimum of its north, east, south, and west neighbors.

The syntax that includes S (the matrix of additive offsets) can be used to implement grayscale morphological operations, including grayscale dilation and erosion.

Performance Considerations

When working with large domain matrices that do not contain any zero-valued elements, ordfilt2 can achieve higher performance if A is in an integer data

format (uint8, int8, uint16, int16). The gain in speed is larger for uint8 and int8 than for the 16-bit data types. For 8-bit data formats, the domain matrix must contain seven or more rows. For 16-bit data formats, the domain matrix must contain three or more rows and 520 or more elements.

Example

This examples uses a maximum filter with a [5 5] neighborhood. This is equivalent to imdilate(image, strel('square', 5)).

```
A = imread('snowflakes.png');
B = ordfilt2(A,25,true(5));
figure, imshow(A), figure, imshow(B)
```

See Also

medfilt2

Reference

- [1] Haralick, Robert M., and Linda G. Shapiro, *Computer and Robot Vision*, Volume I, Addison-Wesley, 1992.
- [2] Huang, T.S., G.J.Yang, and G.Y.Tang. "A fast two-dimensional median filtering algorithm.", IEEE transactions on Acoustics, Speech and Signal Processing, Vol ASSP 27, No. 1, February 1979.

Purpose

Convert optical transfer function to point-spread function

Syntax

```
PSF = otf2psf(OTF)
PSF = otf2psf(OTF,OUTSIZE)
```

Description

PSF = otf2psf(OTF) computes the inverse Fast Fourier Transform (IFFT) of the optical transfer function (OTF) array and creates a point-spread function (PSF), centered at the origin. By default, the PSF is the same size as the OTF.

PSF = otf2psf(OTF,OUTSIZE) converts the OTF array into a PSF array, where OUTSIZE specifies the size of the output point-spread function. The size of the output array must not exceed the size of the OTF array in any dimension.

To center the PSF at the origin, otf2psf circularly shifts the values of the output array down (or to the right) until the (1,1) element reaches the central position, then it crops the result to match dimensions specified by OUTSIZE.

Note that this function is used in image convolution/deconvolution when the operations involve the FFT.

Class Support

OTF can be any nonsparse, numeric array. PSF is of class double.

Example

```
PSF = fspecial('gaussian',13,1);
OTF = psf2otf(PSF,[31 31]); % PSF --> OTF
PSF2 = otf2psf(OTF,size(PSF)); % OTF --> PSF2
subplot(1,2,1); surf(abs(OTF)); title('|OTF|');
axis square; axis tight
subplot(1,2,2); surf(PSF2); title('Corresponding PSF');
axis square; axis tight
```

See Also

psf2otf, circshift, padarray

padarray

Purpose

Pad an array

Syntax

B = padarray(A, padsize)

B = padarray(A,padsize,padval)

B = padarray(A,padsize,padval,direction)

Description

B = padarray (A, padsize) pads array A with 0's (zeros). padsize is a vector of positive integers that specifies both the amount of padding to add and the dimension along which to add it. The value of an element in the vector specifies the amount of padding to add. The order of the element in the vector specifies the dimension along which to add the padding.

For example, a padsize value of [2 3] means add 2 elements of padding along the first dimension and 3 elements of padding along the second dimension. By default, paddarray adds padding before the first element and after the last element along the specified dimension.

B = padarray(A,padsize,padval) pads array A where padval specifies the value to use as the pad value. padarray uses the value 0 (zero) as the default. padval can be a scalar that specifies the pad value directly or one of the following text strings that specifies the method padarray uses to determine the values of the elements added as padding.

Value Meaning		
'circular'	Pad with circular repetition of elements within the dimension.	
'replicate'	Pad by repeating border elements of array.	
'symmetric'	Pad array with mirror reflections of itself.	

B = padarray(A,padsize,padval,direction) pads A in the direction specified by the string direction. direction can be one of the following strings. The default value is enclosed in braces ({}).

Value	Meaning		
{'both'}	Pads before the first element and after the last array element along each dimension. This is the default.		
'post'	Pad after the last array element along each dimension.		
'pre'	Pad before the first array element along each dimension.		

Class Support

When padding with a constant value, A can be numeric or logical. When padding using the 'circular', 'replicate', or 'symmetric' methods, A can be of any class. B is of the same class as A.

Example

Example 1

Add three elements of padding to the beginning of a vector. The padding elements, indicated by the gray shading, contain mirror copies of the array elements.

Example 2

Add three elements of padding to the end of the first dimension of the array and two elements of padding to the end of the second dimension. The example uses the value of the last array element as the padding value.

```
A = [1 2; 3 4];
B = padarray(A,[3 2], 'replicate', 'post')
```

padarray

Example 3

Add three elements of padding to the vertical and horizontal dimensions of a three-dimensional array. Use default values for the pad value and direction.

```
A = [ 1 2; 3 4];

B = [ 5 6; 7 8];

C = cat(3,A,B)

C(:,:,1) =

1 2

3 4

C(:,:,2) =

5 6

7 8
```

D = padarray(C,[3 3])
D(:,:,1) ==

0	0	0	0	0	0	0	0
0	0	0	0	0	0	0	0
0	0	0	0	0	0	0	0
0	0	0	1	2	0	0	0
0	0	0	3	4	0	0	0
0	0	0	0	0	0	0	0
0	0	0	0	0	0	0	0
0	0	0	0	0	0	0	0

D(:,:,2) ===								
	0	0	0	0	0	0	0	0
	0	0	0	0	0	0	0	0
	0	0	0	0	0	0	0	0
	0	0	0	5	6	0	0	0
	0	0	0	7	8	0	0	0
	0	0	0	0	0	0	0	0
	0	0	0	0	0	0	0	0
	0	0	0	0	0	0	0	0

See Also circshift, imfilter

para2fan

Purpose

Compute fan-beam projections from parallel-beam tomography data

Syntax

```
F = para2fan(P,D)
```

```
I = para2fan(...,param1,val1,param2,val2,...)
[F,fan positions,fan rotation angles] = fan2para(...)
```

Description

F = para2fan(P,D) computes the fan-beam data (sinogram) F from the parallel-beam data (sinogram) P. Each column of P contains the parallel-beam sensor samples at one rotation angle. D is the distance in pixels from the center of rotation to the center of the sensors.

The sensors are assumed to have a one-pixel spacing. The parallel-beam rotation angles are assumed to be spaced equally to cover [0,180] degrees. The calculated fan-beam rotation angles cover [0,360) with the same spacing as the parallel-beam rotation angles. The calculated fan-beam angles are equally spaced with the spacing set to the smallest angle implied by the sensor spacing.

I = para2fan(...,param1,val1,param2,val2,...) specifies parameters that control various aspects of the para2fan conversion. Parameter names can be abbreviated, and case does not matter. Default values are enclosed in braces like this: {default}. Parameters include

Parameter	Description
'FanCoverage'	String specifying the range through which the beams are rotated.
	Possible values: {'cycle'} or 'minimal'
	See ifanbeam for details.
'FanRotationIncrement'	Positive real scalar specifying the rotation angle increment of the fan-beam projections in degrees.
	If 'FanCoverage' is 'cycle', 'FanRotationIncrement' must be a factor of 360 .
	If 'FanRotationIncrement' is not specified, then it is set to the same spacing as the parallel-beam rotation angles.

Parameter	Description
'FanSensorGeometry'	Text string specifying how sensors are positioned. Possible values: {'arc'} or 'line' See fanbeam for details.
'FanSensorSpacing'	Positive real scalar specifying the spacing of the fan beams. Interpretation of the value depends on the setting of 'FanSensorGeometry':
	If 'FanSensorGeometry' is 'arc', the value defines the angular spacing in degrees. Default value is 1.
	If 'FanSensorGeometry' is 'line', the value defines the linear spacing in pixels.
	If 'FanSensorSpacing' is not specified, the default is the smallest value implied by 'ParallelSensorSpacing' such that
	If 'FanSensorGeometry' is 'arc', 'FanSensorSpacing' is
	180/PI*ASIN(PSPACE/D)
	where PSPACE is the value of 'ParallelSensorSpacing'.
	If 'FanSensorGeometry' is 'line', 'FanSensorSpacing' is
	D*ASIN(PSPACE/D)
'Interpolation'	Text string specifying the type of interpolation used between the parallel-beam and fan-beam data.
	'nearest' — Nearest-neighbor
	{'linear'} — Linear
	'spline' — Piecewise cubic spline
	'pchip' — Piecewise cubic Hermite (PCHIP)
	'cubic' — Same as 'pchip'

para2fan

Parameter	Description	
'ParallelCoverage'	Text string specifying the range of rotation.	
	'cycle' — Parallel data covers 360 degrees	
	{ 'halfcycle'} — Parallel data covers 180 degrees	
'ParallelRotationIncrement'	Positive real scalar specifying the parallel-beam rotation angle increment, measured in degrees. Parallel beam angles are calculated to cover [0,180) degrees with increment PAR_ROT_INC, where PAR_ROT_INC is the value of 'ParallelRotationIncrement'. 180/PAR_ROT_INC must be an integer. If 'ParallelRotationIncrement' is not specified, the increment is assumed to be the same as the increment of the fan-beam rotation angles.	
'ParallelSensorSpacing'	Positive real scalar specifying the spacing of the parallel-beam sensors in pixels. The range of sensor locations is implied by the range of fan angles and is given by [D*sin(min(FAN_ANGLES)),D*sin(max(FAN_ANGLES))] If 'ParallelSensorSpacing' is not specified, the spacing is assumed to be uniform and is set to the minimum spacing implied by the fan angles and sampled over the range implied by the fan angles.	

[F,fan_positions,fan_rotation_angles] = fan2para(...) If 'FanSensorGeometry' is 'arc', fan_positions contains the fan-beam sensor measurement angles. If 'FanSensorGeometry' is 'line', fan_positions contains the fan-beam sensor positions along the line of sensors. fan_rotation_angles contains rotation angles.

Class Support

P and D can be double or single, and must be nonsparse. The other numeric input arguments must be double. The output arguments are double.

Example

Generate parallel-beam projections

```
ph = phantom(128);
theta = 0:180;
```

```
[P,xp] = radon(ph,theta);
imshow(theta,xp,P,[],'n'), axis normal
title('Parallel-Beam Projections')
xlabel('\theta (degrees)')
ylabel('x''')
colormap(hot), colorbar

Convert to fan-beam projections
[F,Fpos,Fangles] = para2fan(P,100);
figure, imshow(Fangles,Fpos,F,[],'n'), axis normal
title('Fan-Beam Projections')
xlabel('\theta (degrees)')
ylabel('Sensor Locations (degrees)')
colormap(hot), colorbar
```

See Also

fan2para, fanbeam, iradon, ifanbeam, phantom, radon

phantom

Purpose

Generate a head phantom image

Syntax

```
P = phantom(def,n)
P = phantom(E,n)
[P,E] = phantom(...)
```

Description

P = phantom(def,n) generates an image of a head phantom that can be used to test the numerical accuracy of radon and iradon or other two-dimensional reconstruction algorithms. P is a grayscale intensity image that consists of one large ellipse (representing the brain) containing several smaller ellipses (representing features in the brain).

def is a string that specifies the type of head phantom to generate. Valid values are

- 'Shepp-Logan' Test image used widely by researchers in tomography
- 'Modified Shepp-Logan' (default) Variant of the Shepp-Logan phantom in which the contrast is improved for better visual perception

n is a scalar that specifies the number of rows and columns in P. If you omit the argument, n defaults to 256.

P = phantom(E,n) generates a user-defined phantom, where each row of the matrix E specifies an ellipse in the image. E has six columns, with each column containing a different parameter for the ellipses. This table describes the columns of the matrix.

Column	Parameter	Meaning
Column 1	A	Additive intensity value of the ellipse
Column 2	a	Length of the horizontal semiaxis of the ellipse
Column 3	b	Length of the vertical semiaxis of the ellipse
Column 4	х0	<i>x</i> -coordinate of the center of the ellipse

Column	Parameter	Meaning
Column 5	y0	y-coordinate of the center of the ellipse
Column 6	phi	Angle (in degrees) between the horizontal semiaxis of the ellipse and the <i>x</i> -axis of the image

For purposes of generating the phantom, the domains for the *x*- and *y*-axes span [-1,1]. Columns 2 through 5 must be specified in terms of this range.

[P,E] = phantom(...) returns the matrix E used to generate the phantom.

Class Support

All inputs and all outputs must be of class double.

Remarks

For any given pixel in the output image, the pixel's value is equal to the sum of the additive intensity values of all ellipses that the pixel is a part of. If a pixel is not part of any ellipse, its value is 0.

The additive intensity value A for an ellipse can be positive or negative; if it is negative, the ellipse will be darker than the surrounding pixels. Note that, depending on the values of A, some pixels can have values outside the range [0,1].

Example

```
P = phantom('Modified Shepp-Logan',200);
imshow(P)
```

phantom



Reference

[1] Jain, Anil K., Fundamentals of $Digital\ Image\ Processing$, Englewood Cliffs, NJ, Prentice Hall, 1989, p. 439.

See Also

radon, iradon

Display information about image pixels

Syntax

pixval on
pixval off
pixval
pixval(fig,option)
pixval(ax,option)
pixval(H,option)

Description

pixval on turns on interactive display of information about image pixels in the current figure. pixval installs a black bar at the bottom of the figure, which displays the (x,y) coordinates for whatever pixel the cursor is currently over and the color information for that pixel. If the image is binary or intensity, the color information is a single intensity value. If the image is indexed or RGB, the color information is an RGB triplet. The values displayed are the actual data values, regardless of the class of the image array, or whether the data is in normal image range.

If you click the image and hold down the mouse button while you move the cursor, pixval also displays the Euclidean distance between the point you clicked and the current cursor location. pixval draws a line between these points to indicate the distance being measured. When you release the mouse button, the line and the distance display disappear.

You can move the display bar by clicking it and dragging it to another place in the figure.

pixval off turns interactive display off in the current figure. You can also turn off the display by clicking the button on the right side of the display bar.

pixval toggles interactive display on or off in the current figure.

pixval(fig,option) applies the pixval command to the figure specified by fig. option is a string containing 'on' or 'off'.

pixval(ax,option) applies the pixval command to the figure that contains the axes ax. option is a string containing 'on' or 'off'.

pixval(H, option) applies the pixval command to the figure that contains the image object H. option is a string containing 'on' or 'off'.

pixval

Example figure, imshow peppers.png

pixval

See Also impixel, improfile

Convert region polygon to region mask

Syntax

```
BW = poly2mask(x,y,m,n)
```

Purpose

BW = poly2mask(x,y,m,n) computes a binary region-of-interest mask BW from a region-of-interest polygon represented by the vectors x and y. The size of BW is m-by-n. Pixels in BW that are inside the polygon (x,y) are set to 1; pixels outside the polygon are set to 0 (zero). The class of BW is logical.

poly2mask closes the polygon automatically if it isn't already closed.

Example

```
x = [63 186 54 190 63];
y = [60 60 209 204 60];
bw = poly2mask(x,y,256,256);
imshow(bw)
hold on
plot(x,y,'b','LineWidth',2)
hold off
```

Create a mask using random points.


```
x = 256*rand(1,4);
y = 256*rand(1,4);
x(end+1) = x(1);
y(end+1) = y(1);
bw = poly2mask(x,y,256,256);
imshow(bw)
hold on
plot(x,y,'b','LineWidth',2)
hold off
```

See Also

roipoly

Algorithm

When creating a region-of-interest mask, poly2mask must determine which pixels are included in the region. This determination can be difficult when pixels on the edge of a region are only partially covered by the border line. The following figure illustrates a triangular region of interest, examining in close-up one of the vertices of the ROI. The figure shows how pixels can be partially covered by the border of a region-of-interest.




Pixels on the Edge of an ROI Are Only Partially Covered by Border

To determine which pixels are in the region, poly2mask uses the following algorithm:

- 1 Divide each pixel (unit square) into a 5-by-5 grid. See Dividing Pixels into a 5-by-5 Subpixel Grid (p. 15-455) for an illustration.
- **2** Adjust the position of the vertices to be on the intersections of the subpixel grid. See Adjusting the Vertices to the Subpixel Grid (p. 15-455) for an illustration.
- **3** Draw a path from each adjusted vertex to the next, following the edges of the subpixel grid. See Drawing a Path Between the Adjusted Vertices (p. 15-456) for an illustration
- **4** Determine which border pixels are inside the polygon using this rule: if a pixel's central subpixel is inside the boundaries defined by the path between adjusted vertices, the pixel is considered inside the polygon. See Determing Which Pixels Are in the Region (p. 15-456) for an illustration


Dividing Pixels into a 5-by-5 Subpixel Grid

The following figure shows the pixel that contains the vertex of the ROI shown previously with this 5-by-5 subpixel grid.




Adjusting the Vertices to the Subpixel Grid

poly2mask adjusts each vertex of the polygon so that the vertex lies on the subpixel grid. Note how poly2mask rounds up x and y coordinates to find the nearest grid corner. This creates a second, modified polygon, slightly smaller, in this case, than the original ROI. A portion is shown in the following figure.



Drawing a Path Between the Adjusted Vertices

poly2mask forms a path from each adjusted vertex to the next, following the edges of the subpixel grid. In the following figure, a portion of this modified polygon is shown by the thick dark lines.




Determing Which Pixels Are in the Region

poly2mask uses the following rule to determine which border pixels are inside the polygon: if the pixel's central subpixel is inside the modified polygon, the pixel is inside the region.

In the following figure, the central subpixels of pixels on the ROI border are shaded a dark gray color. Pixels inside the polygon are shaded a lighter gray. Note that the pixel containing the vertex is not part of the ROI because its center pixel is not inside the modified polygon.

poly2mask



psf2otf

Purpose

Convert point-spread function to optical transfer function

Syntax

```
OTF = psf2otf(PSF)
OTF = psf2otf(PSF,OUTSIZE)
```

Description

OTF = psf2otf(PSF) computes the fast Fourier transform (FFT) of the point-spread function (PSF) array and creates the optical transfer function array, OTF, that is not influenced by the PSF off-centering. By default, the OTF array is the same size as the PSF array.

OTF = psf2otf(PSF,OUTSIZE) converts the PSF array into an OTF array, where OUTSIZE specifies the size of the OTF array. OUTSIZE cannot be smaller than the PSF array size in any dimension.

To ensure that the OTF is not altered because of PSF off-centering, psf2otf postpads the PSF array (down or to the right) with 0's to match dimensions specified in OUTSIZE, then circularly shifts the values of the PSF array up (or to the left) until the central pixel reaches (1,1) position.

Note that this function is used in image convolution/deconvolution when the operations involve the FFT.

Class Support

PSF can be any nonsparse, numeric array. OTF is of class double.

Example

```
PSF = fspecial('gaussian',13,1);
OTF = psf2otf(PSF,[31 31]); % PSF --> OTF
subplot(1,2,1); surf(PSF); title('PSF');
axis square; axis tight
subplot(1,2,2); surf(abs(OTF)); title('Corresponding |OTF|');
axis square; axis tight
```

See Also

otf2psf, circshift, padarray

Perform quadtree decomposition

Syntax

- S = qtdecomp(I)
- S = qtdecomp(I,threshold)
- S = qtdecomp(I,threshold,mindim)
- S = qtdecomp(I,threshold,[mindim maxdim])
- S = qtdecomp(I,fun)

Description

qtdecomp divides a square image into four equal-sized square blocks, and then tests each block to see if it meets some criterion of homogeneity. If a block meets the criterion, it is not divided any further. If it does not meet the criterion, it is subdivided again into four blocks, and the test criterion is applied to those blocks. This process is repeated iteratively until each block meets the criterion. The result can have blocks of several different sizes.

- S = qtdecomp(I) performs a quadtree decomposition on the intensity image I and returns the quadtree structure in the sparse matrix S. If S(k,m) is nonzero, then (k,m) is the upper left corner of a block in the decomposition, and the size of the block is given by S(k,m). By default, qtdecomp splits a block unless all elements in the block are equal.
- S = qtdecomp(I,threshold) splits a block if the maximum value of the block elements minus the minimum value of the block elements is greater than threshold. threshold is specified as a value between 0 and 1, even if I is of class uint8 or uint16. If I is uint8, the threshold value you supply is multiplied by 255 to determine the actual threshold to use; if I is uint16, the threshold value you supply is multiplied by 65535.
- S = qtdecomp(I,threshold,mindim) will not produce blocks smaller than mindim, even if the resulting blocks do not meet the threshold condition.
- S = qtdecomp(I,threshold,[mindim maxdim]) will not produce blocks smaller than mindim or larger than maxdim. Blocks larger than maxdim are split even if they meet the threshold condition. maxdim/mindim must be a power of 2.
- S = qtdecomp(I,fun) uses the function fun to determine whether to split a block. qtdecomp calls fun with all the current blocks of size m-by-m stacked into an m-by-m-by-k array, where k is the number of m-by-m blocks. fun returns a logical k-element vector, whose values are 1 if the corresponding block should

be split, and 0 otherwise. (For example, if k(3) is 0, the third m-by-m block should not be split.) fun must be a function_handle.

Class Support

For the syntaxes that do not include a function, the input image can be of class logical, uint8, uint16, int16, single, or double. For the syntaxes that include a function, the input image can be of any class supported by the function. The output matrix is always of class sparse.

Remarks

qtdecomp is appropriate primarily for square images whose dimensions are a power of 2, such as 128-by-128 or 512-by-512. These images can be divided until the blocks are as small as 1-by-1. If you use qtdecomp with an image whose dimensions are not a power of 2, at some point the blocks cannot be divided further. For example, if an image is 96-by-96, it can be divided into blocks of size 48-by-48, then 24-by-24, 12-by-12, 6-by-6, and finally 3-by-3. No further division beyond 3-by-3 is possible. To process this image, you must set mindim to 3 (or to 3 times a power of 2); if you are using the syntax that includes a function, the function must return 0 at the point when the block cannot be divided further.

Example

View the block representation of quadtree decomposition.

```
I = imread('liftingbody.png');
S = qtdecomp(I,.27);
blocks = repmat(uint8(0),size(S));

for dim = [512 256 128 64 32 16 8 4 2 1];
  numblocks = length(find(S==dim));
  if (numblocks > 0)
```

```
values = repmat(uint8(1),[dim dim numblocks]);
  values(2:dim,2:dim,:) = 0;
  blocks = qtsetblk(blocks,S,dim,values);
  end
end

blocks(end,1:end) = 1;
blocks(1:end,end) = 1;
imshow(I), figure, imshow(blocks,[])
```

The following figure shows the original image and a representation of the quadtree decomposition of the image.




Image Courtesy of NASA

See Also function_handle, qtgetblk, qtsetblk

Get block values in quadtree decomposition

Syntax

```
[vals,r,c] = qtgetblk(I,S,dim)
[vals,idx] = qtgetblk(I,S,dim)
```

Description

[vals,r,c] = qtgetblk(I,S,dim) returns in vals an array containing the dim-by-dim blocks in the quadtree decomposition of I. S is the sparse matrix returned by qtdecomp; it contains the quadtree structure. vals is a dim-by-dim-by-k array, where k is the number of dim-by-dim blocks in the quadtree decomposition; if there are no blocks of the specified size, all outputs are returned as empty matrices. r and c are vectors containing the row and column coordinates of the upper left corners of the blocks.

[vals,idx] = qtgetblk(I,S,dim) returns in idx a vector containing the linear indices of the upper left corners of the blocks.

Class Support

I can be of class logical, uint8, uint16, int16, single, or double. S is of class sparse.

Remarks

The ordering of the blocks in vals matches the columnwise order of the blocks in I. For example, if vals is 4-by-4-by-2, vals(:,:,1) contains the values from the first 4-by-4 block in I, and vals(:,:,2) contains the values from the second 4-by-4 block.

Example

```
I = [1]
                  1
                        1
                              2
                                    3
                                          6
                                                6
                        1
                              4
                                    5
                                                8
                        1
      1
            1
                  1
                            10
                                   15
                                          7
                                                7
      1
                 1
                       1
                                   25
                                          7
                                                7
           1
                            20
     20
          22
                20
                      22
                             1
                                    2
                                          3
                                                4
     20
          22
                22
                      20
                              5
                                    6
                                          7
                                                8
     20
          22
                 20
                      20
                              9
                                   10
                                               12
                                         11
     22
          22
                 20
                      20
                            13
                                   14
                                         15
                                               16];
```

```
S = qtdecomp(I,5);
```

$$[vals,r,c] = qtgetblk(I,S,4)$$

See Also

qtdecomp, qtsetblk

Set block values in quadtree decomposition

Syntax

J = qtsetblk(I,S,dim,vals)

Description

J = qtsetblk(I,S,dim,vals) replaces each dim-by-dim block in the quadtree decomposition of I with the corresponding dim-by-dim block in vals. S is the sparse matrix returned by qtdecomp; it contains the quadtree structure. vals is a dim-by-dim-by-k array, where k is the number of dim-by-dim blocks in the quadtree decomposition.

Class Support

I can be of class logical, uint8, uint16, int16, single, or double. S is of class sparse.

Remarks

The ordering of the blocks in vals must match the columnwise order of the blocks in I. For example, if vals is 4-by-4-by-2, vals(:,:,1) contains the values used to replace the first 4-by-4 block in I, and vals(:,:,2) contains the values for the second 4-by-4 block.

Example

```
I = [1]
                        1
                              2
                                    3
                                          6
                                                6
      1
            1
                        1
                              4
                                    5
                                          6
                                                8
     1
            1
                  1
                        1
                                          7
                                                7
                             10
                                   15
     1
            1
                  1
                        1
                             20
                                   25
                                          7
                                                7
    20
           22
                20
                       22
                              1
                                    2
                                          3
                                                4
    20
           22
                22
                       20
                              5
                                    6
                                          7
                                                8
    20
           22
                20
                       20
                              9
                                   10
                                         11
                                               12
    22
           22
                20
                       20
                             13
                                   14
                                         15
                                               16];
```

```
S = qtdecomp(I,5);
```

```
newvals = cat(3,zeros(4),ones(4));
J = qtsetblk(I,S,4,newvals)
```

See Also

qtdecomp, qtgetblk

Radon transform

Syntax

```
R = radon(I,theta)
[R,xp] = radon(...)
```

Description

R = radon(I, theta) returns the Radon transform R of the intensity image I for the angle theta degrees.

The Radon transform is the projection of the image intensity along a radial line oriented at a specific angle. If theta is a scalar, R is a column vector containing the Radon transform for theta degrees. If theta is a vector, R is a matrix in which each column is the Radon transform for one of the angles in theta. If you omit theta, it defaults to 0:179.

[R,xp] = radon(...) returns a vector xp containing the radial coordinates corresponding to each row of R.

The radial coordinates returned in xp are the values along the x'-axis, which is oriented at theta degrees counterclockwise from the x-axis. The origin of both axes is the center pixel of the image, which is defined as


```
floor((size(I)+1)/2)
```

For example, in a 20-by-30 image, the center pixel is (10,15).

Class Support

I can be of class double, logical, or any integer class. All other inputs and outputs are of class double.

Example



See Also

fan2para, fanbeam, ifanbeam, iradon, para2fan, phantom


References

Bracewell, Ronald N., *Two-Dimensional Imaging*, Englewood Cliffs, NJ, Prentice Hall, 1995, pp. 505-537.


Lim, Jae S., *Two-Dimensional Signal and Image Processing*, Englewood Cliffs, NJ, Prentice Hall, 1990, pp. 42-45.

Algorithm


The Radon transform of an image is the sum of the Radon transforms of each individual pixel, the superposition principle.



The algorithm first divides pixels in the image into four parts and projects each subdivision separately.



Each pixel's contribution is proportionally split into the two nearest bins, according to the distance between the projected location and the bin centers. If the projection hits the center point, the bin on the axes gets the full .25 % weight of the pixel. If the projection hits the border between two bins, the bins share half the .25 %. If the projection falls between a midpoint and a bin border, the pixel



Each pixel's contribution is proportionally split into the two nearest bins, according to the distance between the projected location and the bin centers.

Local range of an image

J = rangefilt(I,NHOOD)

Syntax

```
J = rangefilt(I)
```

Description

J = rangefilt(I) returns the array J, where each output pixel contains the range value (maximum value - minimum value) of the 3-by-3 neighborhood around the corresponding pixel in the input image I. I can have any dimension. The output image J is the same size as the input image I.

J = rangefilt(I,NHOOD) performs range filtering of the input image I where you specify the neighborhood in NHOOD. NHOOD is a multidimensional array of zeros and ones where the nonzero elements specify the neighborhood for the range filtering operation. NHOOD's size must be odd in each dimension.

By default, rangefilt uses the neighborhood true(3). rangefilt determines the center element of the neighborhood by floor((size(NHOOD) + 1)/2). For information about specifying neighborhoods, see Notes.

Class Support

I can be logical or numeric and must be real and nonsparse. NHOOD can be logical or numeric and must contain zeros or ones.

The output image J is the same class as I, except for signed integer data types. The output class for signed data types is the corresponding unsigned integer data type. For example, if the class of I is int8, then the class of J is uint8.

Notes

rangefilt uses the morphological functions imdilate and imerode to determine the maximum and minimum values in the specified neighborhood. Consequently, rangefilt uses the padding behavior of these morphological functions.

In addition, to specify neighborhoods of various shapes, such as a disk, use the strel function to create a structuring element object and then use the getnhood function to extract the neighborhood from the structuring element object.

Examples

(2-D) Identify the two flying objects by measuring the local range.

```
I = imread('liftingbody.png');
J = rangefilt(I);
```

```
imshow(I), figure, imshow(J);
```

(3-D) Quantify land cover changes in an RGB image. The example first converts the image to $L^*a^*b^*$ colorspace to separate intensity information into a single plane of the image, and then calculates the local range in each layer.

```
I = imread('autumn.tif');
cform = makecform('srgb2lab');
LAB = applycform(I, cform);
rLAB = rangefilt(LAB);
imshow(I);
figure, imshow(rLAB(:,:,1),[]);
figure, imshow(rLAB(:,:,2),[]);
figure, imshow(rLAB(:,:,3),[]);
```

See Also

entropyfilt, getnhood, imdilate, imerode, stdfilt, strel

Purpose Reflect structuring element

Syntax SE2 = reflect(SE)

Description

SE2 = reflect(SE) reflects a structuring element through its center. The effect is the same as if you rotated the structuring element's domain 180 degrees around its center (for a 2-D structuring element). If SE is an array of structuring element objects, then reflect(SE) reflects each element of SE, and SE2 has the same size as SE.

Class Support

SE and SE2 are STREL objects.

Example

```
se = strel([0 0 1; 0 0 0; 0 0 0])
se2 = reflect(se)
```

se =

Flat STREL object containing 1 neighbor.

Neighborhood:

0	0	1
0	0	0
0	0	0

se2 =

Flat STREL object containing 1 neighbor.

Neighborhood:

0	0	0
0	0	0
1	0	0

See Also

strel

regionprops

Purpose

Measure properties of image regions

Syntax

STATS = regionprops(L,properties)

Description

STATS = regionprops(L,properties) measures a set of properties for each labeled region in the label matrix L. Positive integer elements of L correspond to different regions. For example, the set of elements of L equal to 1 corresponds to region 1; the set of elements of L equal to 2 corresponds to region 2; and so on. The return value STATS is a structure array of length $\max(L(:))$. The fields of the structure array denote different measurements for each region, as specified by properties.

properties can be a comma-separated list of strings, a cell array containing strings, the single string 'all', or the string 'basic'. This table lists the set of valid property strings. Property strings are case insensitive and can be abbreviated.

'Area'	'EquivDiameter'	'MajorAxisLength'
'BoundingBox'	'EulerNumber'	'MinorAxisLength'
'Centroid'	'Extent'	'Orientation'
'ConvexArea'	'Extrema'	'PixelIdxList'
'ConvexHull'	'FilledArea'	'PixelList'
'ConvexImage'	'FilledImage'	'Solidity'
'Eccentricity'	'Image'	

If properties is the string 'all', then all the preceding measurements are computed. If properties is not specified or if it is the string 'basic', then these measurements are computed: 'Area', 'Centroid', and 'BoundingBox'.

Definitions

'Area' — Scalar; the actual number of pixels in the region. (This value might differ slightly from the value returned by bwarea, which weights different patterns of pixels differently.)

'BoundingBox'— 1-by-ndims(L)*2 vector; the smallest rectangle containing the region. BoundingBox is [ul corner width], where

ul corner is in the form [x y z ...] and specifies the upper left

corner of the bounding box

width is in the form [x_width y_width ...] and specifies

the width of the bounding box along each dimension

'Centroid'— 1-by-ndims (L) vector; the center of mass of the region. Note that the first element of Centroid is the horizontal coordinate (or x-coordinate) of the center of mass, and the second element is the vertical coordinate (or y-coordinate). All other elements of Centroid are in order of dimension.

This figure illustrates the centroid and bounding box. The region consists of the white pixels; the green box is the bounding box, and the red dot is the centroid.



'MajorAxisLength' — Scalar; the length (in pixels) of the major axis of the ellipse that has the same normalized second central moments as the region. This property is supported only for 2-D input label matrices.

'MinorAxisLength' — Scalar; the length (in pixels) of the minor axis of the ellipse that has the same normalized second central moments as the region. This property is supported only for 2-D input label matrices.


'Eccentricity' — Scalar; the eccentricity of the ellipse that has the same second-moments as the region. The eccentricity is the ratio of the distance between the foci of the ellipse and its major axis length. The value is between 0 and 1. (0 and 1 are degenerate cases; an ellipse whose eccentricity is 0 is actually a circle, while an ellipse whose eccentricity is 1 is a line segment.) This property is supported only for 2-D input label matrices.

'Orientation' — Scalar; the angle (in degrees) between the *x*-axis and the major axis of the ellipse that has the same second-moments as the region. This property is supported only for 2-D input label matrices.


regionprops

This figure illustrates the axes and orientation of the ellipse. The left side of the figure shows an image region and its corresponding ellipse. The right side shows the same ellipse, with features indicated graphically; the solid blue lines are the axes, the red dots are the foci, and the orientation is the angle between the horizontal dotted line and the major axis.





'Image' — Binary image (logical) of the same size as the bounding box of the region; the on pixels correspond to the region, and all other pixels are off.



Original Image, Containing a Single Region





Image Returned

'FilledImage' — Binary image (logical) of the same size as the bounding box of the region. The on pixels correspond to the region, with all holes filled in.

'FilledArea' — Scalar; the number of on pixels in FilledImage.








Image Returned

'ConvexHull' — p-by-2 matrix; the smallest convex polygon that can contain the region. Each row of the matrix contains the *x*- and *y*-coordinates of one vertex of the polygon. This property is supported only for 2-D input label matrices.

'ConvexImage' — Binary image (logical); the convex hull, with all pixels within the hull filled in (i.e., set to on). (For pixels that the boundary of the hull passes through, regionprops uses the same logic as roipoly to determine whether the pixel is inside or outside the hull.) The image is the size of the bounding box of the region. This property is supported only for 2-D input label matrices.


'ConvexArea' — Scalar; the number of pixels in 'ConvexImage'. This property is supported only for 2-D input label matrices.

'EulerNumber' - Scalar; equal to the number of objects in the region minus the number of holes in those objects. This property is supported only for 2-D input label matrices.

'Extrema' — 8-by-2 matrix; the extrema points in the region. Each row of the matrix contains the x- and y-coordinates of one of the points. The format of the vector is [top-left top-right right-top right-bottom bottom-right bottom-left left-bottom left-top]. This property is supported only for 2-D input label matrices.

regionprops

This figure illustrates the extrema of two different regions. In the region on the left, each extrema point is distinct; in the region on the right, certain extrema points (e.g., top-left and left-top) are identical.



'EquivDiameter' — Scalar; the diameter of a circle with the same area as the region. Computed as sqrt(4*Area/pi). This property is supported only for 2-D input label matrices.

'Solidity' — Scalar; the proportion of the pixels in the convex hull that are also in the region. Computed as Area/ConvexArea. This property is supported only for 2-D input label matrices.

'Extent' — Scalar; the proportion of the pixels in the bounding box that are also in the region. Computed as the Area divided by the area of the bounding box. This property is supported only for 2-D input label matrices.

'PixelIdxList' — p-element vector containing the linear indices of the pixels in the region.

'PixelList' — p-by-ndims(L) matrix; the actual pixels in the region. Each row of the matrix has the form $[x \ y \ z \ \dots]$ and specifies the coordinates of one pixel in the region.

Class Support

The input label matrix L can have any numeric class.

Remarks

Using the Comma-Separated List Syntax

The comma-separated list syntax for structure arrays is very useful when you work with the output of regionprops. For example, for a field that contains a scalar, you can use this syntax to create a vector containing the value of this field for each region in the image.

For instance, if stats is a structure array with field Area, then the following two expressions are equivalent:

```
stats(1).Area, stats(2).Area, ..., stats(end).Area
and
stats.Area
```

Therefore, you can use these calls to create a vector containing the area of each region in the image.

```
stats = regionprops(L, 'Area');
allArea = [stats.Area];
```

allArea is a vector of the same length as the structure array stats.

Selecting Regions Based on Certain Criteria

The function ismember is useful in conjunction with regionprops for selecting regions based on certain criteria. For example, these commands create a binary image containing only the regions whose area is greater than 80.

```
idx = find([stats.Area] > 80);
BW2 = ismember(L,idx);
```

Performance Considerations

Most of the measurements take very little time to compute. The exceptions are these, which can take significantly longer, depending on the number of regions in L:

- 'ConvexHull'
- 'ConvexImage'
- 'ConvexArea'
- 'FilledImage'

Note that computing certain groups of measurements takes about the same amount of time as computing just one of them because regionprops takes advantage of intermediate computations used in both computations. Therefore, it is fastest to compute all the desired measurements in a single call to regionprops.

Working with Binary Images

You must convert a binary image to a label matrix before calling regionprops.

Two common ways to convert a binary image to a label matrix are by using the bwlabel function,

```
L = bwlabel(BW);
or using the double function,
L = double(BW);
```

Note, however, that these functions produce different but equally valid label matrices from the same binary image.

For example, given the following logical matrix, BW,

bwlabel creates a label matrix containing two contiguous regions labeled by the integer values 1 and 2.

```
mylabel = bwlabel(BW)
mylabel =
     1
     1
          1
                                  0
          0
     0
                      0
                                  0
     0
          0
                0
                      0
                            2
                                  2
                                  2
```

The double function creates a label matrix containing one discontiguous region labeled by the integer value 1.

```
mylabel2 = double(BW)
mylabel2 =
    1     1     0     0     0     0
```

1	1	0	0	0	0
0	0	0	0	0	0
0	0	0	0	1	1
0	0	0	0	1	1

Because each result is legitimately desirable in certain situations, regionprops does not attempt to perform either type of conversion on binary images and instead requires that you convert them using either method.

Example

```
BW = imread('text.png');
L = bwlabel(BW);
stats = regionprops(L, 'all');
stats(23)
ans =
               Area: 90
           Centroid: [69.7556 89.8667]
        BoundingBox: [64.5000 83.5000 11 13]
        SubarrayIdx: {1x2 cell}
   MajorAxisLength: 14.5814
   MinorAxisLength: 11.8963
       Eccentricity: 0.5783
        Orientation: -89.2740
         ConvexHull: [19x2 double]
        ConvexImage: [13x11 logical]
         ConvexArea: 121
              Image: [13x11 logical]
        FilledImage: [13x11 logical]
         FilledArea: 98
        EulerNumber: 0
            Extrema: [8x2 double]
      EquivDiameter: 10.7047
           Solidity: 0.7438
             Extent: 0.6294
       PixelIdxList: [90x1 double]
          PixelList: [90x2 double]
```

See Also

bwlabel, bwlabeln, ismember, watershed

ismember (MATLAB function)

rgb2gray

Purpose

Convert an RGB image or colormap to grayscale

Syntax

```
I = rgb2gray(RGB)
newmap = rgb2gray(map)
```

Description

rgb2gray converts RGB images to grayscale by eliminating the hue and saturation information while retaining the luminance.

I = rgb2gray(RGB) converts the truecolor image RGB to the grayscale intensity image I.

newmap = rgb2gray(map) returns a grayscale colormap equivalent to map.

Class Support

If the input is an RGB image, it can be of class uint8, uint16, single, or double. The output image I is of the same class as the input image. If the input is a colormap, the input and output colormaps are both of class double.

Example

Convert an RGB image to a grayscale image.

```
I = imread('board.tif');
J = rgb2gray(I);
figure, imshow(I), figure, imshow(J);
```

Convert the colormap to a grayscale colormap.

```
[X,map] = imread('trees.tif');
gmap = rgb2gray(map);
figure, imshow(X,map), figure, imshow(X,gmap);
```

Algorithm

rgb2gray converts the RGB values to NTSC coordinates, sets the hue and saturation components to zero, and then converts back to RGB color space.

See Also

ind2gray, ntsc2rgb, rgb2ind, rgb2ntsc

Convert RGB values to hue-saturation-value (HSV) color space

rgb2hsv is a function in MATLAB. To get help for this function, select **MATLAB Help** from the Help menu and view the online function reference pages.

rgb2ind

Purpose

Convert an RGB image to an indexed image

Syntax

```
[X,map] = rgb2ind(RGB,n)
X = rgb2ind(RGB,map)
[X,map] = rgb2ind(RGB,tol)
[...] = rgb2ind(...,dither_option)
```

Description

rgb2ind converts RGB images to indexed images using one of three different methods:

- Uniform quantization
- Minimum variance quantization
- Colormap approximation

For all these methods, rgb2ind also dithers the image unless you specify 'nodither' for dither option.

[X,map] = rgb2ind(RGB,n) converts the RGB image to an indexed image X using minimum variance quantization. map contains at most n colors. n must be less than or equal to 65536.

X = rgb2ind(RGB, map) converts the RGB image to an indexed image X with colormap map by matching colors in RGB with the nearest color in the colormap map. size(map,1) must be less than or equal to 65536.

[X,map] = rgb2ind(RGB,tol) converts the RGB image to an indexed image X using uniform quantization. map contains at most $(floor(1/tol)+1)^3$ colors. tol must be between 0.0 and 1.0.

[...] = rgb2ind(...,dither_option) enables or disables dithering. dither option is a string that can have one of these values:

- 'dither' (default) dithers, if necessary, to achieve better color resolution at the expense of spatial resolution.
- 'nodither' maps each color in the original image to the closest color in the new map. No dithering is performed.

Note The values in the resultant image X are indexes into the colormap map and cannot be used in mathematical processing, such as filtering operations.

Class Support

The input image can be of class uint8, uint16, single, or double. If the length of map is less than or equal to 256, the output image is of class uint8. Otherwise, the output image is of class uint16.

Remarks

If you specify to1, rgb2ind uses uniform quantization to convert the image. This method involves cutting the RGB color cube into smaller cubes of length to1. For example, if you specify a to1 of 0.1, the edges of the cubes are one-tenth the length of the RGB cube. The total number of small cubes is

```
n = (floor(1/tol)+1)^3
```

Each cube represents a single color in the output image. Therefore, the maximum length of the colormap is n. rgb2ind removes any colors that don't appear in the input image, so the actual colormap can be much smaller than n.

If you specify n, rgb2ind uses minimum variance quantization. This method involves cutting the RGB color cube into smaller boxes (not necessarily cubes) of different sizes, depending on how the colors are distributed in the image. If the input image actually uses fewer colors than the number you specify, the output colormap is also smaller.

If you specify map, rgb2ind uses colormap mapping, which involves finding the colors in map that best match the colors in the RGB image.

Example

```
RGB = imread('peppers.png');
[X,map] = rgb2ind(RGB,128);
imshow(X,map)
```

rgb2ind



See Also

cmunique, dither, imapprox, ind2rgb, rgb2gray

Purpose Convert RGB values to NTSC color space

Syntax yiqmap = rgb2ntsc(rgbmap)

YIQ = rgb2ntsc(RGB)

Description yiqmap = rgb2ntsc(rgbmap) converts the m-by-3 RGB values in rgbmap to

NTSC color space. yiqmap is an m-by-3 matrix that contains the NTSC

luminance (Y) and chrominance (I and Q) color components as columns that are

equivalent to the colors in the RGB colormap.

YIQ = rgb2ntsc(RGB) converts the truecolor image RGB to the equivalent NTSC

image YIQ.

 $\textbf{Remarks} \hspace{1cm} \textbf{In the NTSC color space, the luminance is the grayscale signal used to display} \\$

pictures on monochrome (black and white) televisions. The other components $% \left(x\right) =\left(x\right) +\left(x\right)$

carry the hue and saturation information.

rgb2ntsc defines the NTSC components using

 $\begin{bmatrix} Y \\ I \\ Q \end{bmatrix} = \begin{bmatrix} 0.299 & 0.587 & 0.114 \\ 0.596 & -0.274 & -0.322 \\ 0.211 & -0.523 & 0.312 \end{bmatrix} \begin{bmatrix} R \\ G \\ B \end{bmatrix}$

Class Support RGB can be of class uint8, uint16, int16, single, or double. RGBMAP can be

double. The output is double.

See Also ntsc2rgb, rgb2ind, ind2rgb, ind2gray

rgb2ycbcr

Purpose Convert RGB values to YCbCr color space

Syntax ycbcrmap = rgb2ycbcr(rgbmap)

YCBCR = rgb2ycbcr(RGB)

Description ycbcrmap = rgb2ycbcr(rgbmap) converts the RGB values in rgbmap to the

YCbCr color space. ycbcrmap is an m-by-3 matrix that contains the YCbCr luminance (Y) and chrominance (Cb) and (Cr) color components as columns. Each row represents the equivalent color to the corresponding row in the RGB

colormap.

YCBCR = rgb2ycbcr(RGB) converts the truecolor image RGB to the equivalent

image in the YCbCr color space.

Class Support If the input is an RGB image, it can be of class uint8, uint16, or double; the

output image is of the same class as the input image. If the input is a colormap,

the input and output colormaps are both of class double.

See Also ntsc2rgb, rgb2ntsc, ycbcr2rgb

rgbplot

Purpose Plot colormap

rgbplot is a MATLAB function. To get help for this function, select **MATLAB Help** from the Help menu and view the online function reference page.

roicolor

Purpose

Select region of interest, based on color

Syntax

```
BW = roicolor(A,low,high)
BW = roicolor(A,v)
```

Description

roicolor selects a region of interest within an indexed or intensity image and returns a binary image. (You can use the returned image as a mask for masked filtering using roifilt2.)

BW = roicolor(A, low, high) returns a region of interest selected as those pixels that lie within the colormap range [low high].

$$BW = (A \ge low) & (A \le high)$$

BW is a binary image with 0's outside the region of interest and 1's inside.

BW = roicolor(A, v) returns a region of interest selected as those pixels in A that match the values in vector v. BW is a binary image with 1's where the values of A match the values of v.

Class Support

The input image A must be numeric. The output image BW is of class logical.

Example

```
I = imread('rice.png');
BW = roicolor(I,128,255);
imshow(I);
figure, imshow(BW)
```





See Also

roifilt2, roipoly

Smoothly interpolate within an arbitrary image region

Syntax

```
J = roifill(I,c,r)
J = roifill(I)

J = roifill(I,BW)
[J,BW] = roifill(...)

J = roifill(x,y,I,xi,yi)
[x,y,J,BW,xi,yi] = roifill(...)
```

Description

roifill fills in a specified polygon in an intensity image. It smoothly interpolates inward from the pixel values on the boundary of the polygon by solving Laplace's equation. roifill can be used, for example, to erase small objects in an image.

J = roifill(I,c,r) fills in the polygon specified by c and r, which are equal-length vectors containing the row-column coordinates of the pixels on vertices of the polygon. The kth vertex is the pixel (r(k),c(k)).

J = roifill(I) displays the image I on the screen and lets you specify the polygon using the mouse. If you omit I, roifill operates on the image in the current axes. Use normal button clicks to add vertices to the polygon. Pressing **Backspace** or **Delete** removes the previously selected vertex. A shift-click, right-click, or double-click adds a final vertex to the selection and then starts the fill; pressing **Return** finishes the selection without adding a vertex.

J = roifill(I,BW) uses BW (a binary image the same size as I) as a mask. roifill fills in the regions in I corresponding to the nonzero pixels in BW. If there are multiple regions, roifill performs the interpolation on each region independently.

[J,BW] = roifill(...) returns the binary mask used to determine which pixels in I get filled. BW is a binary image the same size as I with 1's for pixels corresponding to the interpolated region of I and 0's elsewhere.

J = roifill(x,y,I,xi,yi) uses the vectors x and y to establish a nondefault spatial coordinate system. xi and yi are equal-length vectors that specify polygon vertices as locations in this coordinate system.

[x,y,J,BW,xi,yi] = roifill(...) returns the XData and YData in x and y, the output image in J, the mask image in BW, and the polygon coordinates in xi and yi. xi and yi are empty if the roifill(I,BW) form is used.

If roifill is called with no output arguments, the resulting image is displayed in a new figure.

Class Support

The input image I can of class uint8, uint16, int16, single, or double. The input binary mask BW can be any numeric class or logical. The output binary mask BW is always logical. The output image J is of the same class as I. All other inputs and outputs are of class double.

Example

```
I = imread('eight.tif');
c = [222 272 300 270 221 194];
r = [21 21 75 121 121 75];
J = roifill(I,c,r);
imshow(I)
figure, imshow(J)
```





See Also

roifilt2, roipoly

Filter a region of interest in an image

Syntax

```
J = roifilt2(h,I,BW)
J = roifilt2(I,BW,fun)
```

Description

J = roifilt2(h,I,BW) filters the data in I with the two-dimensional linear filter h. BW is a binary image the same size as I that is used as a mask for filtering. roifilt2 returns an image that consists of filtered values for pixels in locations where BW contains 1's, and unfiltered values for pixels in locations where BW contains 0's. For this syntax, roifilt2 calls filter2 to implement the filter.

J = roifilt2(I,BW,fun) processes the data in I using the function fun. The result J contains computed values for pixels in locations where BW contains 1's, and the actual values in I for pixels in locations where BW contains 0's.

fun must be a function handle.

Class Support

For the syntax that includes a filter h, the input image can be logical or numeric, and the output array J has the same class as the input image. For the syntax that includes a function, I can be of any class supported by fun, and the class of J depends on the class of the output from fun.

Example

This example continues the roipoly example.

```
I = imread('eight.tif');
c = [222 272 300 270 221 194];
r = [21 21 75 121 121 75];
BW = roipoly(I,c,r);
h = fspecial('unsharp');
J = roifilt2(h,I,BW);
imshow(J), figure, imshow(J)
```

roifilt2



See Also

imfilter, filter2, function_handle, roipoly

Select a polygonal region of interest

Syntax

```
BW = roipoly(I,c,r)
BW = roipoly(I)

BW = roipoly(x,y,I,xi,yi)
[BW,xi,yi] = roipoly(...)
[x,y,BW,xi,yi] = roipoly(...)
```

Description

Use roipoly to select a polygonal region of interest within an image. roipoly returns a binary image that you can use as a mask for masked filtering.

BW = roipoly(I,c,r) returns the region of interest selected by the polygon described by vectors c and r. BW is a binary image the same size as I with 0's outside the region of interest and 1's inside.

BW = roipoly(I) displays the image I on the screen and lets you specify the polygon using the mouse. If you omit I, roipoly operates on the image in the current axes. Use normal button clicks to add vertices to the polygon. Pressing **Backspace** or **Delete** removes the previously selected vertex. A shift-click, right-click, or double-click adds a final vertex to the selection and then starts the fill; pressing **Return** finishes the selection without adding a vertex.

BW = roipoly(x,y,I,xi,yi) uses the vectors x and y to establish a nondefault spatial coordinate system. xi and yi are equal-length vectors that specify polygon vertices as locations in this coordinate system.

[BW,xi,yi] = roipoly(...) returns the polygon coordinates in xi and yi. Note that roipoly always produces a closed polygon. If the points specified describe a closed polygon (i.e., if the last pair of coordinates is identical to the first pair), the length of xi and yi is equal to the number of points specified. If the points specified do not describe a closed polygon, roipoly adds a final point having the same coordinates as the first point. (In this case the length of xi and yi is one greater than the number of points specified.)

[x,y,BW,xi,yi] = roipoly(...) returns the XData and YData in x and y, the mask image in BW, and the polygon coordinates in xi and yi.

If roipoly is called with no output arguments, the resulting image is displayed in a new figure.

roipoly

Class Support

The input image I can be of class uint8, uint16, int16, single, or double. The output image BW is of class logical. All other inputs and outputs are of class double.

Remarks

For any of the roipoly syntaxes, you can replace the input image I with two arguments, m and n, that specify the row and column dimensions of an arbitrary image. For example, these commands create a 100-by-200 binary mask.

```
c = [112 112 79 79];
r = [37 66 66 37];
BW = roipoly(100,200,c,r);
```

If you specify m and n with an interactive form of roipoly, an m-by-n black image is displayed, and you use the mouse to specify a polygon within this image.

Example

```
I = imread('eight.tif');
c = [222 272 300 270 221 194];
r = [21 21 75 121 121 75];
BW = roipoly(I,c,r);
imshow(I)
figure, imshow(BW)
```





See Also

roifilt2, roicolor, roifill, poly2mask

Purpose Compute the standard deviation of the elements of a matrix

Syntax b = std2(A)

Description b = std2(A) computes the standard deviation of the values in A.

Class Support A can be numeric or logical. B is a scalar of class double.

Algorithm std2 computes the standard deviation of the array A using std(A(:)).

See Also corr2, mean2

std, mean in the MATLAB Function Reference

stdfilt

Purpose

Local standard deviation of an image

Syntax

```
J = stdfilt(I)
J = stdfilt(I,NHOOD)
```

Description

J = stdfilt(I) returns the array J, where each output pixel contains the standard deviation of the 3-by-3 neighborhood around the corresponding pixel in the input image I. I can have any dimension. The output image J is the same size as the input image I.

For pixels on the borders of I, stdfilt uses symmetric padding. In symmetric padding, the values of padding pixels are a mirror reflection of the border pixels in I.

J = stdfilt(I,NHOOD) calculates the local standard deviation of the input image I, where you specify the neighborhood in NHOOD. NHOOD is a multidimensional array of zeros and ones where the nonzero elements specify the neighbors. NHOOD's size must be odd in each dimension.

By default, stdfilt uses the neighborhood ones(3). stdfilt determines the center element of the neighborhood by floor((size(NHOOD) + 1)/2).

Class Support

I can be logical or numeric and must be real and nonsparse. NHOOD can be logical or numeric and must contain zeros and/or ones. J is of class double.

Notes

To specify neighborhoods of various shapes, such as a disk, use the strel function to create a structuring element object and then use the getnhood function to extract the neighborhood from the structuring element object.

Example

```
I = imread('circuit.tif');
J = stdfilt(I);
imshow(I);
figure, imshow(J,[]);
```

See also

entropyfilt, getnhood, rangefilt, std2, strel

Create morphological structuring element

Syntax

SE = strel(shape,parameters)


Description

SE = strel(shape, parameters) creates a structuring element, SE, of the type specified by shape. This table lists all the supported shapes. Depending on shape, strel can take additional parameters. See the syntax descriptions that follow for details about creating each type of structuring element.

Flat Structuring Elements	
'arbitrary'	'pair'
'diamond'	'periodicline'
'disk'	'rectangle'
'line'	'square'
'octagon'	

Nonflat Structuring Elements	
'arbitrary'	'ball'

SE = strel('arbitrary', NHOOD) creates a flat structuring element where NHOOD specifies the neighborhood. NHOOD is a matrix containing 1's and 0's; the location of the 1's defines the neighborhood for the morphological operation. The center (or origin) of NHOOD is its center element, given by floor((size(NHOOD)+1)/2). You can omit the 'arbitrary' string and just use strel(NHOOD).




SE = strel('arbitrary', NHOOD, HEIGHT) creates a nonflat structuring element, where NHOOD specifies the neighborhood. HEIGHT is a matrix the same size as NHOOD containing the height values associated with each nonzero element of NHOOD. The HEIGHT matrix must be real and finite valued. You can omit the 'arbitrary' string and just use strel(NHOOD, HEIGHT).

SE = strel('ball',R,H,N) creates a nonflat, ball-shaped structuring element (actually an ellipsoid) whose radius in the X-Y plane is R and whose height is H. Note that R must be a nonnegative integer, H must be a real scalar, and N must be an even nonnegative integer. When N is greater than 0, the ball-shaped structuring element is approximated by a sequence of N nonflat, line-shaped structuring elements. When N equals 0, no approximation is used, and the structuring element members consist of all pixels whose centers are no greater than R away from the origin. The corresponding height values are determined from the formula of the ellipsoid specified by R and H. If N is not specified, the default value is 8.

Note Morphological operations run much faster when the structuring element uses approximations (N > 0) than when it does not (N = 0).


SE = strel('diamond',R) creates a flat, diamond-shaped structuring element, where R specifies the distance from the structuring element origin to the points of the diamond. R must be a nonnegative integer scalar.



SE = strel('disk',R,N) creates a flat, disk-shaped structuring element, where R specifies the radius. R must be a nonnegative integer. N must be 0, 4, 6, or 8. When N is greater than 0, the disk-shaped structuring element is approximated by a sequence of N periodic-line structuring elements. When N


equals 0, no approximation is used, and the structuring element members consist of all pixels whose centers are no greater than R away from the origin. If N is not specified, the default value is 4.

Note Morphological operations run much faster when the structuring element uses approximations (N > 0) than when it does not (N = 0). However, structuring elements that do not use approximations (N = 0) are not suitable for computing granulometries. Sometimes it is necessary for strel to use two extra line structuring elements in the approximation, in which case the number of decomposed structuring elements used is N + 2.




SE = strel('line', LEN, DEG) creates a flat, linear structuring element, where LEN specifies the length, and DEG specifies the angle (in degrees) of the line, as measured in a counterclockwise direction from the horizontal axis. LEN is


approximately the distance between the centers of the structuring element members at opposite ends of the line.




SE = strel('octagon',R) creates a flat, octagonal structuring element, where R specifies the distance from the structuring element origin to the sides of the octagon, as measured along the horizontal and vertical axes. R must be a nonnegative multiple of 3.




SE = strel('pair', OFFSET) creates a flat structuring element containing two members. One member is located at the origin. The second member's location is specified by the vector OFFSET. OFFSET must be a two-element vector of integers.




SE = strel('periodicline',P,V) creates a flat structuring element containing 2*P+1 members. V is a two-element vector containing integer-valued row and column offsets. One structuring element member is located at the origin. The other members are located at 1*V, -1*V, 2*V, -2*V, ..., P*V, -P*V.



SE = strel('rectangle', MN) creates a flat, rectangle-shaped structuring element, where MN specifies the size. MN must be a two-element vector of nonnegative integers. The first element of MN is the number of rows in the structuring element neighborhood; the second element is the number of columns.



SE = strel('square',W) creates a square structuring element whose width is W pixels. W must be a nonnegative integer scalar.



Notes

For all shapes except 'arbitrary', structuring elements are constructed using a family of techniques known collectively as *structuring element decomposition*. The principle is that dilation by some large structuring elements can be computed faster by dilation with a sequence of smaller structuring elements. For example, dilation by an 11-by-11 square structuring element can be accomplished by dilating first with a 1-by-11 structuring element and then

with an 11-by-1 structuring element. This results in a theoretical performance improvement of a factor of 5.5, although in practice the actual performance improvement is somewhat less. Structuring element decompositions used for the 'disk' and 'ball' shapes are approximations; all other decompositions are exact.

Methods

This table lists the methods supported by the STREL object.

getheight	Get height of structuring element
getneighbors	Get structuring element neighbor locations and heights
getnhood	Get structuring element neighborhood
getsequence	Extract sequence of decomposed structuring elements
isflat	Return true for flat structuring element
reflect	Reflect structuring element
translate	Translate structuring element

Example

Algorithm

The method used to decompose diamond-shaped structuring elements is known as "logarithmic decomposition" [1].

The method used to decompose disk structuring elements is based on the technique called "radial decomposition using periodic lines" [2], [3]. For details, see the MakeDiskStrel subfunction in toolbox/images/@strel/strel.m.

The method used to decompose ball structuring elements is the technique called "radial decomposition of sphere" [2].

See Also

imdilate, imerode

References

- [1] van den Boomgard, Rein, and Richard van Balen, "Methods for Fast Morphological Image Transforms Using Bitmapped Images," *Computer Vision, Graphics, and Image Processing: Graphical Models and Image Processing*, Vol. 54, No. 3, May 1992, pp. 252-254.
- [2] Adams, Rolf, "Radial Decomposition of Discs and Spheres," Computer Vision, Graphics, and Image Processing: Graphical Models and Image Processing, Vol. 55, No. 5, September 1993, pp. 325-332.
- [3] Jones, Ronald, and Pierre Soille, "Periodic lines: Definition, cascades, and application to granulometrie," *Pattern Recognition Letters*, Vol. 17, 1996, pp. 1057-1063.

stretchlim

Purpose

Find limits to contrast stretch an image

Syntax

```
LOW_HIGH = stretchlim(I,TOL)
LOW HIGH = stretchlim(RGB,TOL)
```

Description

LOW_HIGH = stretchlim(I,TOL) returns a pair of intensities that can be used by imadjust to increase the contrast of an image.

TOL = [LOW_FRACT HIGH_FRACT] specifies the fraction of the image to saturate at low and high intensities.

If TOL is a scalar, LOW_FRACT = TOL, and HIGH_FRACT = 1 - LOW_FRACT, which saturates equal fractions at low and high intensities.

If you omit the argument, TOL defaults to [0.01 0.99], saturating 2%.

```
If TOL = 0, LOW HIGH = [min(I(:)) max(I(:))].
```

LOW_HIGH = stretchlim(RGB,TOL) returns a 2-by-3 matrix of intensity pairs to saturate each plane of the RGB image. TOL specifies the same fractions of saturation for each plane.

Class Support

The input image can be of class uint8, uint16, int16, double, or single. The output intensities returned, LOW_HIGH, are of class double and have values between 0 and 1.

Example

```
I = imread('pout.tif');
J = imadjust(I,stretchlim(I),[]);
imshow(I), figure, imshow(J)
```

stretchlim





See Also

brighten, histeq, imadjust

subimage

Purpose

Display multiple images in the single figure

Syntax

```
subimage(X,map)
subimage(I)
subimage(BW)
subimage(RGB)
subimage(x,y,...)
h = subimage(...)
```

Description

You can use subimage in conjunction with subplot to create figures with multiple images, even if the images have different colormaps. subimage works by converting images to true color for display purposes, thus avoiding colormap conflicts.

subimage(X, map) displays the indexed image X with colormap map in the current axes.

subimage(I) displays the intensity image I in the current axes.

subimage (BW) displays the binary image BW in the current axes.

 $\operatorname{subimage}(\operatorname{RGB})$ displays the truecolor image RGB in the current axes.

subimage(x,y...) displays an image using a nondefault spatial coordinate system.

h = subimage(...) returns a handle to an image object.

Class Support

The input image can be of class logical, uint8, uint16, or double.

Example

```
load trees
[X2,map2] = imread('forest.tif');
subplot(1,2,1), subimage(X,map)
subplot(1,2,2), subimage(X2,map2)
```

See Also

imshow

subplot in the MATLAB Function Reference

Spatial transformation of a multidimensional array

Syntax

B = tformarray(A,T,R,TDIMS A,TDIMS B,TSIZE B,TMAP B,F)

Description

B = tformarray(A,T,R,TDIMS_A,TDIMS_B,TSIZE_B,TMAP_B,F) applies a spatial transformation to array A to produce array B. The tformarray function is like imtransform, but is intended for problems involving higher-dimensioned arrays or mixed input/output dimensionality, or requiring greater user control or customization. (Anything that can be accomplished with imtransform can be accomplished with a combination of maketform, makeresampler, findbounds, and tformarray; but for many tasks involving 2-D images, imtransform is simpler.)

This table provides a brief description of all the input arguments. See the following section for more detail about each argument. (Click an argument in the table to move to the appropriate section.)

Argument	Description
A	Input array or image
Т	Spatial transformation structure, called a TFORM, typically created with maketform
R	Resampler structure, typically created with makeresampler
TDIMS_A	Row vector listing the input transform dimensions
TDIMS_B	Row vector listing the output transform dimensions
TSIZE_B	Output array size in the transform dimensions
TMAP_B	Array of point locations in output space; can be used as an alternative way to specify a spatial transformation
F	Array of fill values

A can be any nonsparse numeric array, and can be real or complex.

tformarray

T is a TFORM structure that defines a particular spatial transformation. For each location in the output transform subscript space (as defined by TDIMS_B and TSIZE_B), tformarray uses T and the function tforminv to compute the corresponding location in the input transform subscript space (as defined by TDIMS_A and size(A)).

If T is empty, tformarray operates as a direct resampling function, applying the resampler defined in R to compute values at each transform space location defined in TMAP_B (if TMAP_B is nonempty), or at each location in the output transform subscript grid.

R is a structure that defines how to interpolate values of the input array at specified locations. R is usually created with makeresampler, which allows fine control over how to interpolate along each dimension, as well as what input array values to use when interpolating close to the edge of the array.

TDIMS_A and TDIMS_B indicate which dimensions of the input and output arrays are involved in the spatial transformation. Each element must be unique, and must be a positive integer. The entries need not be listed in increasing order, but the order matters. It specifies the precise correspondence between dimensions of arrays A and B and the input and output spaces of the transformer T. length(TDIMS_A) must equal T.ndims_in, and LENGTH(TDIMS_B) must equal T.ndims_out.

For example, if T is a 2-D transformation, TDIMS_A = [2 1], and TDIMS_B = [1 2], then the column dimension and row dimension of A correspond to the first and second transformation input-space dimensions, respectively. The row and column dimensions of B correspond to the first and second output-space dimensions, respectively.

TSIZE_B specifies the size of the array B along the output-space transform dimensions. Note that the size of B along nontransform dimensions is taken directly from the size of A along those dimensions. If, for example, T is a 2-D transformation, size(A) = [480 640 3 10], TDIMS_B is [2 1], and TSIZE_B is [300 200], then size(B) is [200 300 3].

TMAP_B is an optional array that provides an alternative way of specifying the correspondence between the position of elements of B and the location in output transform space. TMAP_B can be used, for example, to compute the result of an image warp at a set of arbitrary locations in output space. If TMAP_B is not empty, then the size of TMAP_B takes the form

```
[D1 D2 D3 ... DN L]
```

where N equals length(TDIMS_B). The vector [D1 D2 ... DN] is used in place of TSIZE_B. If TMAP_B is not empty, then TSIZE_B should be [].

The value of L depends on whether or not T is empty. If T is not empty, then L is T.ndims_out, and each L-dimension point in TMAP_B is transformed to an input-space location using T. If T is empty, then L is length (TDIMS_A), and each L-dimensional point in TMAP_B is used directly as a location in input space.

F is a double-precision array containing fill values. The fill values in F can be used in three situations:

- When a separable resampler is created with makeresampler and its padmethod is set to either 'fill' or 'bound'.
- When a custom resampler is used that supports the 'fill' or 'bound' pad methods (with behavior that is specific to the customization).
- When the map from the transform dimensions of B to the transform dimensions of A is deliberately undefined for some points. Such points are encoded in the input transform space by NaNs in either TMAP_B or in the output of TFORMINV.

In the first two cases, fill values are used to compute values for output locations that map outside or near the edges of the input array. Fill values are copied into B when output locations map well outside the input array. See makeresampler for more information about 'fill' and 'bound'.

F can be a scalar (including NaN), in which case its value is replicated across all the nontransform dimensions. F can also be a nonscalar, whose size depends on size(A) in the nontransform dimensions. Specifically, if K is the Jth nontransform dimension of A, then size(F,J) must be either size(A,K) or 1. As a convenience to the user, tformarray replicates F across any dimensions with unit size such that after the replication size(F,J) equals size(A,K).

For example, suppose A represents 10 RGB images and has size 200-by-200-by-3-by-10, T is a 2-D transformation, and TDIMS_A and TDIMS_B are both [1 2]. In other words, tformarray will apply the same 2-D transform to each color plane of each of the 10 RGB images. In this situation you have several options for F:

tformarray

- F can be a scalar, in which case the same fill value is used for each color plane of all 10 images.
- F can be a 3-by-1 vector, [R G B] '. Then R, G, and B are used as the fill values for the corresponding color planes of each of the 10 images. This can be interpreted as specifying an RGB fill color, with the same color used for all 10 images.
- F can be a 1-by-10 vector. This can be interpreted as specifying a different fill value for each of 10 images, with that fill value being used for all three color planes.
- F can be a 3-by-10 matrix, which can be interpreted as supplying a different RGB fill color for each of the 10 images.

Class Support

A can be any nonsparse numeric array, and can be real or complex. It can also be of class logical.

Example

Create a 2-by-2 checkerboard image where each square is 20 pixels wide, then transform it with a projective transformation. Use a pad method of 'circular' when creating a resampler, so that the output appears to be a perspective view of an infinite checkerboard. Swap the output dimensions. Specify a 100-by-100 output image. Leave TMAP_B empty, since TSIZE_B is specified. Leave the fill value empty, since it won't be needed.

See Also

findbounds, imtransform, makeresampler, maketform

Apply forward spatial transformation

Syntax

```
[X,Y] = tformfwd(T,U,V)
[X1,X2,X3,...] = tformfwd(T,U1,U2,U3,...)
X = tformfwd(T,U)
[X1,X2,X3,...] = tformfwd(T,U)
X = tformfwd(T,U1,U2,U3,...)
```

Description

[X,Y] = tformfwd(T,U,V) applies the 2D-to-2D spatial transformation defined in T to coordinate arrays U and V, mapping the point $[U(k) \ V(k)]$ to the point $[X(k) \ Y(k)]$.

T is a TFORM struct created with maketform, fliptform, or cp2tform. Both T.ndims_in and T.ndims_out must equal 2. U and V are typically column vectors matching in length. In general, U and V can have any dimensionality, but must have the same size. In any case, X and Y will have the same size as U and V.

[X1,X2,X3,...] = tformfwd(T,U1,U2,U3,...) applies the ndims_in-to-ndims_out spatial transformation defined in TFORM structure T to the coordinate arrays U1,U2,...,UNDIMS_IN (where NDIMS_IN = T.ndims_in and NDIMS_OUT = T.ndims_out). The number of output arguments must equal NDIMS_OUT. The transformation maps the point

```
[U1(k) U2(k) ... UNDIMS_IN(k)]
```

to the point

```
[X1(k) X2(k) ... XNDIMS OUT(k)].
```

U1, U2, U3, ... can have any dimensionality, but must be the same size.

 $X1, X2, X3, \ldots$ must have this size also.

X = tformfwd(T,U) applies the ndims_in-to-ndims_out spatial transformation defined in TFORM structure T to each row of U, where U is an M-by-NDIMS_IN matrix. It maps the point U(k,:) to the point X(k,:). X is an M-by-NDIMS_OUT matrix.

X = tformfwd(T,U), where U is an (N+1)-dimensional array, maps the point U(k1,k2,...,kN,:) to the point X(k1,k2,...,kN,:). size (U,N+1) must equal

```
NDIMS_IN. X is an (N+1)-dimensional array, with size(X,I) equal to size(U,I) for I = 1, ..., N and size(X,N+1) equal to NDIMS_OUT.
```

[X1,X2,X3,...] = tformfwd(T,U) maps an (N+1)-dimensional array to NDIMS OUT equally sized N-dimensional arrays.

X = tformfwd(T,U1,U2,U3,...) maps NDIMS_IN N-dimensional arrays to one (N+1)-dimensional array.

Note

X = tformfwd(U,T) is an older form of the two-argument syntax that remains supported for backward compatibility.

Example

Create an affine transformation that maps the triangle with vertices (0,0), (6,3), (-2,5) to the triangle with vertices (-1,-1), (0,-10), (4,4).

```
u = [ 0  6  -2]';
v = [ 0  3  5]';
x = [-1  0  4]';
y = [-1 -10  4]';
tform = maketform('affine',[u v],[x y]);
```

Validate the mapping by applying tformfwd. Results should equal [x, y]

```
[xm, ym] = tformfwd(tform, u, v)
```

See Also

cp2tform, fliptform, maketform, tforminv

Apply inverse spatial transformation

Syntax

U = tforminv(X,T)

Description

[U,V] = tforminv(T,X,Y) applies the 2D-to-2D inverse transformation defined in TFORM structure T to coordinate arrays X and Y, mapping the point $[X(k) \ Y(k)]$ to the point $[U(k) \ V(k)]$. Both T.ndims_in and T.ndims_out must equal 2. X and Y are typically column vectors matching in length. In general, X and Y can have any dimensionality, but must have the same size. In any case, U and V will have the same size as X and Y.

[U1,U2,U3,...] = tforminv(T,X1,X2,X3,...) applies the NDIMS_OUT-to-NDIMS_IN inverse transformation defined in TFORM structure T to the coordinate arrays X1,X2,...,XNDIMS_OUT (where NDIMS_IN = T.ndims_in and NDIMS_OUT = T.ndims_out). The number of output arguments must equal NDIMS IN. The transformation maps the point

```
[X1(k) X2(k) ... XNDIMS_OUT(k)]
```

to the point

```
[U1(k) U2(k) \dots UNDIMS_IN(k)].
```

 $X1, X2, X3, \ldots$ can have any dimensionality, but must be the same size.

U1, U2, U3, ... have this size also.

U = tforminv(T,X), where X is an (N+1)-dimensional array, maps the point X(k1,k2,...,kN,:) to the point U(k1,k2,...,kN,:). size (X,N+1) must equal NDIMS_OUT. U is an (N+1)-dimensional array, with size (U,I) equal to size (X,I) for I = 1,...,N and size (U,N+1) equal to NDIMS_IN.

[U1,U2,U3,...] = tforminv(T,X) maps an (N+1)-dimensional array to NDIMS_IN equally-sized N-dimensional arrays.

U = tforminv(T,X1,X2,X3,...) maps NDIMS_OUT N-dimensional arrays to one (N+1)-dimensional array.

Note

U = tforminv(X,T) is an older form of the two-argument syntax that remains supported for backward compatibility.

Example

Create an affine transformation that maps the triangle with vertices (0,0), (6,3), (-2,5) to the triangle with vertices (-1,-1), (0,-10), (4,4).

```
u = [ 0  6  -2]';
v = [ 0  3  5]';
x = [-1  0  4]';
y = [-1 -10  4]';
tform = maketform('affine',[u v],[x y]);
```

Validate the mapping by applying tforminv. Results should equal [u, v].

```
[um, vm] = tforminv(tform, x, y)
```

See Also

cp2tform, tforminv, maketform, fliptform

Purpose Translate structuring element

Syntax SE2 = translate(SE,V)

Description SE2 = reflect(SE,V) translates a structuring element SE in N-D space. V is

an N-element vector containing the offsets of the desired translation in each

dimension.

Class Support SE and SE2 are STREL objects; V is a vector of double-precision values.

Dilating with a translated version of strel(1) is a way to translate the input image in space. This example translates the cameraman.tif image down and to the right by 25 pixels.

I = imread('cameraman.tif');
se = translate(strel(1), [25 25]);

J = imdilate(I,se);
imshow(I), title('Original')

figure, imshow(J), title('Translated');



See Also strel, reflect

truesize

Purpose Adjust display size of an image

Syntax truesize(fig,[mrows mcols])

truesize(fig)

Description truesize(fig,[mrows ncols]) adjusts the display size of an image. fig

is a figure containing a single image or a single image with a colorbar. [mrows ncols] is a 1-by-2 vector that specifies the requested screen area in

pixels that the image should occupy.

truesize(fig) uses the image height and width for [mrows ncols]. This results in the display's having one screen pixel for each image pixel.

If you omit the figure argument, truesize works on the current figure.

Remarks If the 'TruesizeWarning' toolbox preference is 'on', truesize displays a

warning if the image is too large to fit on the screen. (The entire image is still displayed, but at less than true size.) If 'TruesizeWarning' is 'off', truesize does not display the warning. Note that this preference applies even when you

call truesize indirectly, such as through imshow.

See Also imshow, iptsetpref, iptgetpref

Convert data to unsigned 16-bit integers

uint16 is a MATLAB built-in function. To get help for this function, select **MATLAB Help** from the Help menu and view the online function reference page.

uint8

Purpose

Convert data to unsigned 8-bit integers

uint8 is a MATLAB built-in function. To get help for this function, select **MATLAB Help** from the Help menu and view the online function reference page.

Compute new values of A based on lookup table LUT

Note uintlut is an obsolete version of intlut and may be removed in a future version of the toolbox.

Syntax

B = uintlut(A,LUT)

Purpose

B = uintlut(A,LUT) creates an array B containing new values of A based on the lookup table LUT. For example, if A is a vector whose kth element is equal to alpha, then B(k) is equal to the LUT value corresponding to alpha, that is, LUT(alpha+1).

Class Support

A must be uint8 or uint16. If A is uint8, then LUT must be a uint8 vector with 256 elements. If A is uint16, then LUT must be a uint16 vector with 65536 elements. B has the same size and class as A.

Example

```
A = uint8([1 2 3 4; 5 6 7 8;9 10 11 12]);
LUT = repmat(uint8([0 150 200 255]),1,64);
B = uintlut(A,LUT);
imshow(A), figure, imshow(B);
```

See Also

impixel, improfile

Display an image as a texture-mapped surface

Syntax

```
warp(X,map)
warp(I,n)
warp(BW)
warp(RGB)
warp(z,...)
warp(x,y,z,...)
h = warp(...)
```

Description

warp(X,map) displays the indexed image X with colormap map as a texture map on a simple rectangular surface.

warp(I,n) displays the intensity image I with grayscale colormap of length n as a texture map on a simple rectangular surface.

warp(BW) displays the binary image BW as a texture map on a simple rectangular surface.

warp(RGB) displays the RGB image in the array RGB as a texture map on a simple rectangular surface.

warp(z,...) displays the image on the surface z.

warp(x,y,z...) displays the image on the surface (x,y,z).

h = warp(...) returns a handle to a texture-mapped surface.

Class Support

The input image can be of class logical, uint8, uint16, or double.


Remarks

Texture-mapped surfaces are generally rendered more slowly than images.

Example

This example texture maps an image of a test pattern onto a cylinder.

```
[x,y,z] = cylinder;
I = imread('testpat1.png');
warp(x,y,z,I);
```



See Also imshow

image, imagesc, surf in the MATLAB Function Reference

watershed

Purpose

Find image watershed regions

Syntax

L = watershed(A)

L = watershed(A,CONN)

Description

L = watershed(A) computes a label matrix identifying the watershed regions of the input matrix A, which can have any dimension. The elements of L are integer values greater than or equal to 0. The elements labeled 0 do not belong to a unique watershed region. These are called *watershed pixels*. The elements labeled 1 belong to the first watershed region, the elements labeled 2 belong to the second watershed region, and so on.

By default, watershed uses 8-connected neighborhoods for 2-D inputs and 26-connected neighborhoods for 3-D inputs. For higher dimensions, watershed uses the connectivity given by conndef (ndims(A), 'maximal').

L = watershed(A,CONN) specifies the connectivity to be used in the watershed computation. CONN can have any of the following scalar values.

Value	Meaning	
Two-dimensional connectivities		
4	4-connected neighborhood	
8	8-connected neighborhood	
Three-dimensional connectivities		
6	6-connected neighborhood	
18	18-connected neighborhood	
26	26-connected neighborhood	

Connectivity can be defined in a more general way for any dimension by using for CONN a 3-by-3-by- ...-by-3 matrix of 0's and 1's. The 1-valued elements define neighborhood locations relative to the center element of CONN. Note that CONN must be symmetric about its center element.

Class Support

A can be a numeric or logical array of any dimension, and it must be nonsparse. The output array L is of class double.

Example 2-D Example

1 Make a binary image containing two overlapping circular objects.

```
center1 = -10;
center2 = -center1;
dist = sqrt(2*(2*center1)^2);
radius = dist/2 * 1.4;
lims = [floor(center1-1.2*radius) ceil(center2+1.2*radius)];
[x,y] = meshgrid(lims(1):lims(2));
bw1 = sqrt((x-center1).^2 + (y-center1).^2) <= radius;
bw2 = sqrt((x-center2).^2 + (y-center2).^2) <= radius;
bw = bw1 | bw2;
figure, imshow(bw,'InitialMagnification','fit'), title('bw')</pre>
```

2 Compute the distance transform of the complement of the binary image.

```
D = bwdist(~bw);
figure, imshow(D,[],'InitialMagnification','fit')
title('Distance transform of ~bw')
```

3 Complement the distance transform, and force pixels that don't belong to the objects to be at -Inf.

```
D = -D;
D(~bw) = -Inf;
```

4 Compute the watershed transform and display it as an indexed image.

```
L = watershed(D);
rgb = label2rgb(L,'jet',[.5 .5 .5]);
figure, imshow(rgb,'InitialMagnification','fit')
title('Watershed transform of D')
```

3-D Example

1 Make a 3-D binary image containing two overlapping spheres.

```
center1 = -10;
center2 = -center1;
dist = sqrt(3*(2*center1)^2);
radius = dist/2 * 1.4;
```

2 Compute the distance transform.

```
D = bwdist(~bw);
figure, isosurface(x,y,z,D,radius/2), axis equal
title('Isosurface of distance transform')
xlabel x, ylabel y, zlabel z
xlim(lims), ylim(lims), zlim(lims)
view(3), camlight, lighting gouraud
```

3 Complement the distance transform, force nonobject pixels to be -Inf, and then compute the watershed transform.

```
D = -D;
D(~bw) = -Inf;
L = watershed(D);
figure, isosurface(x,y,z,L==2,0.5), axis equal
title('Segmented object')
xlabel x, ylabel y, zlabel z
xlim(lims), ylim(lims), zlim(lims)
view(3), camlight, lighting gouraud
figure, isosurface(x,y,z,L==3,0.5), axis equal
title('Segmented object')
xlabel x, ylabel y, zlabel z
xlim(lims), ylim(lims), zlim(lims)
view(3), camlight, lighting gouraud
```

Algorithm

watershed uses a variation of the Vincent and Soille algorithm [1]. For details of the variation, see toolbox/images/images/private/watershed vs.h.

See Also

bwlabel, bwlabeln, bwdist, regionprops

watershed

Reference

[1] Vincent, Luc, and Pierre Soille, "Watersheds in Digital Spaces: An Efficient Algorithm Based on Immersion Simulations," *IEEE Transactions of Pattern Analysis and Machine Intelligence*, Vol. 13, No. 6, June 1991, pp. 583-598.

whitepoint

Purpose

Return XYZ values of standard illuminants

Syntax

```
xyz = whitepoint
```

xyz = whitepoint(string)

Description

xyz = whitepoint(string) returns xyz, a three-element row vector of XYZ values scaled so that Y = 1. string specifies the white reference illuminant. The following table lists all the possible values for string. The default value is enclosed in braces ($\{\}$).

Value	Description
'a'	CIE standard illuminant A
' C '	CIE standard illuminant C
'd50'	CIE standard illuminant D50
' d55 '	CIE standard illuminant D55
' d65 '	CIE standard illuminant D65
{'icc'}	ICC standard profile connection space illuminant; a 16-bit fractional approximation of D50

xyz = whitepoint is the same as xyz = whitepoint('icc').

Class Support

string is a character array. xyz is of class double.

Example

This example returns the XYZ color space representation of the default white reference illuminant 'icc'.

```
wp_icc = whitepoint
wp_icc =
    0.9642    1.0000    0.8249
```

Perform two-dimensional adaptive noise-removal filtering

Syntax

Description

wiener2 lowpass-filters an intensity image that has been degraded by constant power additive noise. wiener2 uses a pixelwise adaptive Wiener method based on statistics estimated from a local neighborhood of each pixel.

J = wiener2(I,[m n],noise) filters the image I using pixelwise adaptive Wiener filtering, using neighborhoods of size m-by-n to estimate the local image mean and standard deviation. If you omit the [m n] argument, m and n default to 3. The additive noise (Gaussian white noise) power is assumed to be noise.

[J,noise] = wiener2(I,[m n]) also estimates the additive noise power before doing the filtering. wiener2 returns this estimate in noise.

Class Support

The input image I is a two-dimensional image of class uint8, uint16, int16, single, or double. The output image J is of the same size and class as I.

Example

For an example, see "Using Adaptive Filtering" on page 10-52.

Algorithm

wiener2 estimates the local mean and variance around each pixel,

$$\begin{split} \mu &= \frac{1}{NM} \sum_{n_1,\, n_2 \in \, \eta} \alpha(n_1,n_2) \\ \sigma^2 &= \frac{1}{NM} \sum_{n_1,\, n_2 \in \, \eta} \alpha^2(n_1,n_2) - \mu^2 \end{split}$$

where η is the *N*-by-*M* local neighborhood of each pixel in the image A. wiener2 then creates a pixelwise Wiener filter using these estimates,

$$b(n_1, n_2) = \mu + \frac{\sigma^2 - v^2}{\sigma^2} (a(n_1, n_2) - \mu)$$

where v^2 is the noise variance. If the noise variance is not given, wiener2 uses the average of all the local estimated variances.

wiener2

See Also filter2, medfilt2

Reference [1] Lim, Jae S., Two-Dimensional Signal and Image Processing, Englewood

Cliffs, NJ, Prentice Hall, 1990, pp. 536-540.

Convert color data from XYZ representation to double

Syntax

xyzd = xyz2double(XYZ)

Description

xyxd = xyz2double(XYZ) converts an M-by-3 or M-by-N-by-3 array of XYZ color values to double. xyzd has the same size as XYZ.

The Image Processing Toolbox follows the convention that double-precision XYZ arrays contain 1931 CIE XYZ values. XYZ arrays that are uint16 follow the convention in the ICC profile specification (ICC.1:2001-4, www.color.org) for representing XYZ values as unsigned 16-bit integers. There is no standard representation of XYZ values as unsigned 8-bit integers. The ICC encoding convention is illustrated by this table.

Value (X, Y, or Z)	uint16 Value
0.0	0
1.0	32768
1.0 + (32767/32768)	65535

Class Support

xyz is a uint16 or double array that must be real and nonsparse. xyzd is of class double.

Example

Convert uint16-encoded XYZ values to double.

```
xyz2double(uint16([100 32768 65535]))
ans =
```

3.0518e-003 1.0000e+000 2.0000e+000

See Also

applycform, lab2double, lab2uint16, lab2uint8, makecform, whitepoint, xyz2uint16

xyz2uint16

Purpose

Convert color data from XYZ representation to uint16

Syntax

xyz16 = xyz2uint16(xyz)

Description

xyz16 = xyz2uint16(xyz) converts an M-by-3 or M-by-N-by-3 array of *XYZ* color values to uint16. xyz16 has the same size as xyz.

The Image Processing Toolbox follows the convention that double-precision XYZ arrays contain 1931 CIE XYZ values. XYZ arrays that are uint16 follow the convention in the ICC profile specification (ICC.1:2001-4, www.color.org) for representing XYZ values as unsigned 16-bit integers. There is no standard representation of XYZ values as unsigned 8-bit integers. The ICC encoding convention is illustrated by this table.

Value (X, Y, or Z)	uint16 Value
0.0	0
1.0	32768
1.0 + (32767/32768)	65535

Class Support

xyz is a uint16 or double array that must be real and nonsparse. xyz16 is uint8.

Example

Convert XYZ values to uint16 encoding.

```
xyz2uint16([0.1 0.5 1.0])
ans =
```

3277 16384 32768

See Also

 ${\it applycform, lab2double, lab2uint16, lab2uint8, makecform, whitepoint, } \\ {\it xyz2double}$

Purpose Convert YCbCr values to RGB color space

Syntax rgbmap = ycbcr2rgb(ycbcrmap)

RGB = ycbcr2rgb(YCBCR)

Description rgbmap = ycbcr2rgb(ycbcrmap) converts the YCbCr values in the colormap

ycbcrmap to the RGB color space. If ycbcrmap is m-by-3 and contains the YCbCr luminance (Y) and chrominance (Cb) and (Cr) color values as columns, then rgbmap is returned as an m-by-3 matrix that contains the red, green, and blue

values equivalent to those colors.

RGB = ycbcr2rgb(YCBCR) converts the YCbCr image YCBCR to the equivalent

truecolor image RGB.

Class Support If the input is a YCbCr image, it can be of class uint8, uint16, or double; the

output image is of the same class as the input image. If the input is a colormap,

the input and output colormaps are both of class double.

Example Convert image from RGB space to YCbCr space and back.

rgb = imread('board.tif');
ycbcr = rgb2ycbcr(rgb);
rgb2 = ycbcr2rgb(ycbcr);

See Also ntsc2rgb, rgb2ntsc, rgb2ycbcr

zoom

Purpose

Zoom in and out on an image

zoom is a MATLAB function. To get help for this function, select **MATLAB Help** from the Help menu and view the online function reference page.

Index

A	averaging filter
adapthisteq 14-17	creating 14-150
example 9-28	example 6-7
adaptive filters 9-37	
definition 9-2	
two-dimensional adaptive noise filtering	В
14-429	background
affine transformations	of a binary image 8-2
definition 5-12	of an intensity image 1-11
using imtransform 4-11	bestblk $14\text{-}23$
aliasing	bicubic interpolation 4-3
definition 4-2, 4-7	bilinear interpolation 4-3
alpha channel 12-4	binary images 2-9
analyzing images	applying a lookup table 14-21
edge detection 14-126	calculating the Euler number 8-43
intensity profiles 14-268	changing the display colors of 3-28
pixel values 14-265	constructing lookup tables 14-328
quadtree decomposition 14-365	definition 2-2
antialiasing 4-7	displaying 3-28
definition 4-2	feature measurement 8-40
applycform 14-20	finding area 14-28
applylut 14-21	flood fill operation 8-26
example 8-45	image area 8-42
modifying text in an image 8-44	labeling connected components 14-46
approximation	labeling connected components labeling 8-40
definition 12-2	lookup table operations 8-44
in indexed images 12-12	morphological operations 8-4
of an image background 1-11	object selection 14-61
of colors 12-7	packing 8-3
area	perimeter determination 8-17
of binary images 8-42	selecting objects in 8-42
of image regions 9-11	using neighborhood operations 14-21
arrays	binary masks
storing images 2-4	creating 10-3

definition 10-2 blkproc 14-24bit depth specifying overlap 13-10 1-bit images 2-18 using 13-9 screen bit depth 12-3 block processing 13-2 blind deconvolution algorithm block size 14-23 used for deblurring 11-16 column processing 13-11 distinct blocks 13-8 padding borders in block processing 13-5 sliding neighborhoods 13-4 using nlfilter 14-343 border padding definition 13-2 in block processing 13-5 border replication in image processing 6-12 boundary padding See border padding boundary ringing in image deblurring 11-23 boundary tracing 9-13 bounding box finding for a region 9-11 brightness adjustment 9-23 bwarea 14-28 using 8-42 bwareaopen 14-30 bwboundaries 14-32 bwdist 14-36 using 8-37 bweuler 14-42bwhitmiss 14-44 bwlabel 14-46 bwlabeln 14-49 bwmorph 14-52 skeletonization example 8-17 bwpack 14-57

bwperim 14-59

bwselect 14-61	quantization performed by rgb2ind 14-386
bwtraceboundary 14-63	reducing number of colors 12-6
using 9-15	color approximation
bwulterode 14-66	definition 3-2
bwunpack 14-68	performed by rgb2ind 14-386
	color cube
	a description of 12-7
C	quantization of 12-8
camera read-out noise 11-12	color planes 12-9, 12-25
Canny edge detector 14-127	of an HSV image 12-25
using the edge function 9-12	of an RGB image 2-10
center of mass	color reduction 12-6
calculating for region 9-11	color spaces
center pixel	converting among 12-15
calculating 13-4	converting between 14-346, 14-387
definition 13-2	data encodings 12-18
checkerboard 14-69	device-independent color spaces 12-16
chrominance	HSV 12-23
in CIE color spaces 12-16	NTSC 12-22, 14-346, 14-387
in NTSC color space 12-22	YCbCr 12-23
in YCbCr color space 12-23	YIQ 12-22
CIE color spaces 12-15	colorbar 3-32
CIELAB color space 12-15	colorcube 12-12
class support 2-13	colormap mapping 12-11
See also data types	colormaps
closing 14-52	brightening 14-27
morphology 8-14	creating a colormap using colorcube 12-12
cmpermute 14-71	darkening 14-27
cmunique 14-72	rearranging colors in 14-71
col2im 14-74	removing duplicate entries in 14-72
colfilt 14-75	column processing 14-75
example 13-12, 13-14	definition 13-2
using 13-11	in neighborhood operations 13-11
color	reshaping columns into blocks 14-74
approximation 12-7	composite transformations 4-11
dithering 12-13	-
quantization 12-7	

conformal transformations 5-12	control points
conndef 14-78	appearance of 5-26
connected components	prediction 5-24
definition 8-2	saving 5-29
labeling 8-40	selecting 5-14
using bwlabel 14-46	specifying 5-22
connectivity	conv2 2-4
definition 8-2	compared to imfilter 6-14
overview 8-23	conversions between image types 2-13
specifying custom 8-25	convmtx2 14-81
constant component	convn
See zero-frequency component	compared to imfilter 6-14
contour plots	used with images 2-4
text labels 9-9	convolution
contours	convolution matrix 14-81
definition 9-2	definition 6-4
contrast adjustment	Fourier transform and 7-12
decreasing contrast 9-23	two-dimensional 6-4
increasing contrast 9-21	with imfilter 6-9
specifying limits automatically 9-24	convolution kernel
contrast stretching	definition 6-4
with decorrelation stretching 9-32	coordinate systems
See also contrast adjustment	pixel coordinates 2-31
contrast-limited adaptive histogram equalization	spatial coordinates 2-32
(CLAHE) 9-28	corr2 14-83
Control Point Selection Tool	calculating summary statistics 9-11
appearance of control point symbols 5-26	correlation
changing view of images 5-17	definition 6-6
saving a session 5-30	Fourier transform 7-13
saving control points 5-29	with imfilter 6-9
specifying control points 5-22	correlation coefficient 14-83
starting 5-15	correlation kernel
using 5-14	definition 6-6
using point prediction 5-24	cp2tform 14-84
	using 5-12

cpcorr 14-93	decomposition of structuring elements
example 5-31	example 8-9
cpselect 14-95	getting sequence 14-174
using 5-7	deconvblind $14 ext{-}102$
cpstruct2pairs 14-97	example 11-16
cropping an image 4-10	deconvlucy 14-105
cross-correlation	example 11-11
improving control point selection 5-31	deconvreg 14-108
	example 11-9
	deconvwnr 14-110
D	example 11-7
damping	decorrelation stretching 9-29
for noise reduction 11-12	See also contrast adjustment
data types	decorrstretch 14-112
8-bit integers (uint8) 2-5	detail rectangle
converting between 2-19	in Control Point Selection Tool 5-16
double-precision (double) 2-19	DICOM files
double-precision (double) 2-5	reading and writing 2-22
in image filtering 6-7	DICOM unique identifier
summary of image types and numeric classes	generating 2-28
2-13	dicomdict 14-113
DC component	dicominfo 14-114
See zero-frequency component	dicomread 14-115
dct2 14-98	dicomuid 14-118
equations 7-17	dicomwrite 14-119
dctmtx 14-101	Digital Imaging and Communications in
using 7-18	Medicine
deblurring	See DICOM files
avoiding boundary ringing 11-23	dilation 8-4
conceptual model 11-3	grayscale 14-347
overview 11-3	discrete cosine transform 7-17
overview of functions 11-6	image compression 7-19
use of frequency domain 11-22	transform matrix 7-18, 14-101
using the blind deconvolution algorithm 11-16	discrete Fourier transform 7-8
using the Lucy-Richardson algorithm 11-11	discrete transform
with regularized filter 11-9	definition 7-2
with the Wiener filter 11-7	

display depth 12-3	E
See screen color resolution	edge 14-126
display techniques	example 9-13
displaying images at true size 14-418	edge detection 9-12
multiple images 14-407	Canny method 9-12
displaying images	example 9-13
adding a colorbar 3-32	methods 14-126
at true size 3-19	Sobel method 9-12
binary 3-28	edges
binary images with different colors 3-28	definition 9-2
comparison of functions 3-3	edgetaper 14-131
directly from disk 3-18	avoiding boundary ringing 11-23
indexed images 3-25	8-bit image files
initial size 3-19	creating 2-19
intensity images 3-26	reading 2-16
multiple images in the same figure window	enhancing images
3-20	decorrelation stretching 9-29
texture mapping 3-36	intensity adjustment 9-22
toolbox preferences for 3-38	noise removal 9-34
unconventional ranges of data 3-26	erosion 8-4
using imshow 3-18	grayscale 14-347
using the Image Viewer 3-4, 3-5	Euclidean distance 9-3, 14-361
distance	Euler number
between pixels 9-3	calculating 8-43
Euclidean 9-3	
distance transform 8-37	
distinct block operations 13-8	F
definition 13-2	fan2para 14-132
overlap 13-9	fanbeam 14-136
zero padding 13-8	using 7-36
dither 14-123	fan-beam projection data
dithering 12-13	arc geometry 7-37
example 12-13	computing 7-36
	line geometry 7-38
	reconstructing image from 7-39

fast Fourier transform 7-8	filters
zero padding 7-10	adaptive 9-37, 14-429
See also Fourier transform	averaging 14-150
feature measurement 1-19	binary masks 10-6
area 9-11	computing frequency response 7-11
binary images 8-40	designing 6-17
bounding box 9-11	finite impulse response (FIR) 6-17
center of mass 9-11	frequency response 6-23
fft 7-8	imfilter 6-7
fft2 7-8	Infinite Impulse Response (IIR) 6-18
example 7-9	Laplacian of Gaussian 14-150
using 7-11	linear 6-4
fftn 2-4, 7-8	median 9-34, 14-339
fftshift	multidimensional 6-13
example 6-18	order-statistic 14-347
using 7-11	predefined types 14-150
files	Prewitt 14-150
displaying images from disk 3-18	Sobel 14-150
filling a region 10-9	unsharp 14-150
definition 10-2	unsharp masking 6-15
filling holes in images 8-28	findbounds 14-142
filter design 6-17	FIR filters 6-17
frequency sampling method 6-19, 14-147	transforming from one-dimensional to
frequency transformation method 6-18,	two-dimensional 6-18
14-155	flat-field correction 11-12
windowing method 6-20, 14-158, 14-162	fliptform 14-143
filter2	flood-fill operation 8-26
compared to imfilter 6-14	foreground
example 3-27, 9-36	of a binary image 8-2
filtering	4-bit image files 2-18
a region 10-6	Fourier transform 7-3
masked filtering 10-6	applications of the Fourier transform 7-11
regions 10-2	centering the zero-frequency coefficient 7-11
	computing frequency response 7-11
	convolution and 7-12
	correlation 7-13

DFT coefficients 7-9	fwind2 14-162
examples of transform on simple shapes 7-7	example 6-20
fast convolution with 7-12	-
for performing correlation 7-13	
frequency domain 7-3	G
increasing resolution 7-10	gamma correction 9-24
padding before computation 7-10	Gaussian convolution kernel
two-dimensional 7-3	frequency response of 7-12
zero-frequency component 7-3	Gaussian filter 14-150
freqspace 6-22	Gaussian noise 9-37
example 6-19	adding 14-260
frequency domain 7-3	geocoded images 5-6
definition 7-2	geometric operations
frequency response	cropping 4-10
computing 6-23, 7-11, 14-145	definition 4-2
desired response matrix 6-22	interpolation 4-3
frequency sampling method (filter design) 6-19	resizing 4-5
using fsamp2 14-147	georegistered images 5-6
frequency transformation method (filter design)	getheight 14-166
6-18	getimage 14-167
using ftrans2 14-155	example 3-18
freqz	getline 14-169
example 6-18	getneighbors 14-170
freqz2 14-145	getnhood 14-171
computing frequency response of linear filters	getpts 14-172
7-11	getrect 14-173
example 6-20	getsequence 14-174
fsamp2 14-147	graphics card 12-4
example 6-19	graphics file formats
fspecial 14-150	converting from one format to another 2-21
creating predefined filters 6-15	writing data 2-17
ftrans2 14-155	gray2ind $14 ext{-}175$
example 6-18	grayscale images
function functions	See intensity images
using 13-9	grayscale morphological operations 14-347
fwind1 14-158	grayslice 14-176
example 6-21	

graythresh 14-177	im2java2d 14-197
thresholding image values 1-15	im2uint16 14-198
	im2uint8 14-199
	imabsdiff 14-200
Н	imadd $14\text{-}202$
histeq 14-178	imadjust 14-204
example 9-27	brightening example 9-23
increase contrast example 9-26, 9-29	example 9-22
histogram equalization 9-26, 14-178	gamma correction and 9-24
histograms 9-9	gamma correction example 9-25
definition 9-2	increase contrast example 9-22
holes	setting limits automatically 9-24
filling 8-26	image analysis
tracing boundaries 9-13	contour plots 9-8
HSV color space 12-23	edge detection 9-12
color planes of 12-25	histograms 9-9
hsv2rgb 12-23	intensity profiles 9-5
hue	overview 9-12
in HSV color space 12-23	pixel values 9-3
in NTSC color space 12-22	quadtree decomposition 9-19
	summary statistics 9-11
	image area (binary images) 14-28
<u> </u>	image arithmetic
ICC profiles	combining functions 2-30
processing 12-19	overview 2-29
iccread 14-182	truncation rules 2-29
idct2 14-185	image editing 10-9
ifanbeam 14-186	image filtering
using 7-39	data types 6-7
ifft 7-8	unsharp masking 6-15
ifft2 7-8	with imfilter 6-7
ifftn 7-8	Image Information tool
IIR filters 6-18	in Image Viewer 3-7
im2bw 14-191	using 3-16
im2col 14-193	-
im2double $14\text{-}195$	
example 13-14	

image profiles	Image Viewer
definition 9-2	closing 3-4
image properties	compared to imshow 3-3
definition 9-2	controlling initial magnification 3-5
set by imshow 3-23	exploring images 3-9
image registration	extended example 1-10
fine-tuning point placement 5-31	managing memory usage 3-16
overview 5-4	opening 3-4
procedure 5-4	overview 3-4
selecting control points 5-14	overview of tools 3-6
specifying control point pairs 5-22	panning images 3-11
types of transformations 5-12	specifying image magnification 3-12
using control point prediction 5-24	starting 3-4
image rotation 4-8	using the Pixel Region tool 3-13
image transformations	viewing multiple images 3-5
affine 5-12	zoom tools 3-11
custom 4-11	images
local weighted mean 5-13	analyzing 9-3
piecewise linear 5-13	arithmetic operations 2-29
polynomial 5-13	causes of blurring 11-3
projective 5-13	creating movies 14-257
supported by cp2tform 5-12	data types 2-5, 2-19
types of 5-12	displaying multiple images 3-19, 14-407
using imtransform 4-11	displaying multiple images in the same figure
image types 2-6	window 3-20
binary 2-9	feature measurement 1-19
converting 2-13	filling holes in 8-28
indexed 2-6	finding image minima and maxima 8-29
intensity 2-8	getting data from axes 14-167
interpolation and 4-4	how MATLAB stores 2-4
multiframe images 2-12	image types 2-6
overview 2-2	improving contrast 1-14
RGB 2-9	reducing number of colors 12-6
supported by the toolbox 2-6	registering 5-4
See also indexed, intensity, binary, RGB,	restoring blurred images 11-3
multiframe	returning information about 2-20

statistical analysis of 1-20	imlincomb $14\text{-}254$
storage classes 2-5	example 2-30
using imshow 3-18	immovie $14\text{-}257$
viewing as a surface plot 1-12	example 3-35
imapprox 14-207	immultiply $14\text{-}258$
example 12-12	imnoise 14-260
imbothat 14-209	example 9-37
imclearborder 14-211	salt & pepper example 9-35
imclose 14-214	imopen $14\text{-}263$
using 8-14	using 8-14
imcomplement 14-216	impixel $14\text{-}265$
imcontour 14-218	example 9-4
example 9-9	improfile 14-268
imcrop 14-220	example 9-7
example 4-10	grayscale example 9-5
imdilate 14-223	imread $2\text{-}16$
imdivide 14-227	example for multiframe image 2-17
imerode $14\text{-}229$	imreconstruct 14-272
closure example 8-15	example 8-20
imextendedmax 14-232	imregionalmax $14\text{-}274$
example 8-31	imregionalmin $14 ext{-}276$
imextendedmin 14-234	imresize 14-278
imfill 14-236	using 4-5
example 8-28	imrotate 14-280
imfilter 14-240	example 4-8
compared to other filtering functions 6-14	using 4-8
convolution option 6-9	imshow $14\text{-}282$
correlation option 6-9	compared to Image Viewer 3-3
padding options 6-10	displaying images 3-18
using 6-7	displaying unconventional range data 3-27
imfinfo $2\text{-}20$	example for binary images 3-28
example 2-18	example for intensity images 3-26
imhist 14-244	example for RGB images 3-30
example 9-10, 9-21, 9-22	preferences for 3-38
imhmax 14-246	specifying number of gray levels 3-26
imhmin $14\text{-}248$	truesize option 3-19
imimposemin 14-250	used with indexed images 3-25

imsubtract 14-284	interpolation 4-3
imtophat 14-286	bicubic 4-3
imtransform 14-288	bilinear 4-3
using 4-11	default 4-4
imview 14-294	definition 4-2
compared to imshow 3-3	intensity profiles 9-5
displaying unconventional range data 3-27	nearest-neighbor 4-3
overview 3-4	of binary images 4-4
used with indexed images 3-25	of indexed images 4-4
imwrite	of RGB images 4-4
example 2-18	tradeoffs between methods 4-3
ind2gray 14-299	within a region of interest 10-9
ind2rgb 14-300	inverse Radon transform 7-29
indexed images 2-6	example 7-34
converting from intensity 14-175	filtered backprojection algorithm 7-31
converting from RGB 14-385	inverse transform
definition 2-2	definition 7-2
reducing number of colors in 12-6, 12-12	ippl 14-301
infinite impulse response (IIR) filter 6-18	iptdemos $14 ext{-}302$
inline 13-9	iptgetpref 3-39, 14-303
Intel Performance Primitives Library 14-301	iptsetpref 14-304
intensity adjustment 9-22	iradon 7-29, $14 ext{-}306$
gamma correction 9-24	example 7-29
histogram equalization 9-26	isbw 14-309
specifying limits automatically 9-24	isflat 14-310
See also contrast adjustment	isgray 14-311
intensity images 2-8	isind $14\text{-}312$
converting from matrices 14-337	isrgb 14-313
converting from RGB 14-383	
converting to indexed 14-175	
definition 2-2	J
displaying 3-26	java.opts file
flood-fill operation 8-26	managing memory usage 3-16
number of gray levels displayed 3-26	JPEG compression
intensity profiles 9-5, 14-268	discrete cosine transform and 7-19

L	M
lab2double 14-314	magnification
lab2uint16 14-316	specifying in Image Viewer 3-5
lab2uint8 14-318	magnifying
label matrix	See resizing images
creating 8-40	makecform $14\text{-}322$
viewing as pseudocolor image 1-18, 8-41	makelut 14-328
label2rgb 14-320	example 8-44
labeling	makeresampler 14-330
connected components 8-40	maketform 14-334
levels of contours 9-9	marker image
Laplacian of Gaussian edge detector 14-127	creating 8-34
Laplacian of Gaussian filter 14-150	definition 8-19
line detection 7-27	mask image
line segment	definition 8-19
pixel values along 9-5	masked filtering 10-6
linear conformal transformations 5-12	definition 10-2
linear filtering 6-4, 13-5	mat2gray 14-337
convolution 6-4	matrices
filter design 6-17	converting to intensity images 14-337
FIR filters 6-17	storing images in 2-4
IIR filters 6-18	maxima
noise removal and 9-34	finding in images 8-29
local weighted mean transformations 5-13	imposing 8-33
lookup tables	suppressing 8-31
constructing 14-328	McClellan transform 14-155
using 8-44	mean2 9-11, 14-338
Lucy-Richardson algorithm	medfilt2 14-339
used for deblurring 11-11	example 9-36
luminance	using 9-35
in NTSC color space 12-22	median filtering 9-34, 14-339
in YCbCr color space 12-23	minima
	finding in images 8-29
	imposing 8-33
	suppressing 8-31

minimum variance quantization 12-9	N
moiré patterns 4-7	nearest-neighbor interpolation 4-3
montage 14-341	neighborhood operations
example 3-33, 3-34	definition 13-2
morphological operations 8-4	neighborhoods
closing 14-52	binary image operations 14-21
diagonal fill 14-53	definition 8-2
dilation 8-4	neighborhood operations 13-2
erosion 8-4	nlfilter 13-6, 14-343
grayscale 14-347	example 13-6
opening 8-14	noise
overview 8-1	adding to an image 14-260
predefined operations 8-16	definition 9-2
shrinking objects 14-54	noise amplification
skeletonization 8-17	reducing 11-12
morphological reconstruction	noise removal 9-34
finding peaks and valleys 8-29	adaptive filtering (Weiner) and 9-37
overview 8-19	Gaussian noise 9-37
morphology	grain noise 9-34
definition 8-2	linear filtering and 9-34
See also morphological reconstruction	median filter and 9-35
movies	salt and pepper noise 9-35
creating from images 3-35, 14-257	nonlinear filtering 13-5
playing 3-35	normalized cross-correlation 5-31
multidimensional filters 6-13	normxcorr2 14-344
multiframe images	NTSC color space 12-22, 14-346, 14-387
about 2-12	ntsc2rgb 12-22, 14-346
definition 2-2	
displaying 14-341	
limitations 2-12	0
multilevel thresholding 14-176	object selection 14-61
	objects
	tracing boundaries 9-13
	observed image
	in image registration 5-14
	1-bit image files 2-18

opening	piecewise linear transformations 5-13
morphology 8-14	Pixel Region tool
optical transfer function (OTF)	in Image Viewer 3-6
definition 11-2	specifying region size 3-15
order-statistic filtering 14-347	using 3-13
ordfilt2 14-347	pixel values 14-265, 14-361
orthonormal matrix 7-19	along a line segment 9-5
orthophoto	returning using a mouse 9-3
defined 5-6	using the Pixel Region tool 3-13
orthorectified image 5-6	pixels
OTF	correcting for bad pixels 11-12
See optical transfer function	defining connectivity 8-23
otf2psf 14-349	definition 2-4
use of 11-22	displaying coordinates of 9-3
outliers 9-35	Euclidean distance between 9-3
overlap	returning coordinates of 9-4
in block operations 13-2	selecting 9-3
in distinct block operations 13-8	pixval 14-361
Overview window	using 9-3
in Image Viewer 3-6	PNG
using 3-9	writing as 16-bit 2-18
	point mapping
	for image registration 5-4
P	point spread function (PSF)
packed binary image	definition 11-2
definition 8-3	importance of in deblurring 11-4
padarray 14-350	Poisson noise
padding borders	adding 14-260
in block processing 13-5	poly2mask 14-363
options with imfilter 6-10	polygon
panning images	pixels inside 10-3
using the Image Viewer 3-11	selecting a polygonal region of interest 10-3
para2fan 14-354	polynomial transformations 5-13
parallel beam projections 7-30	predicting control point locations
perimeter determination	in image registration 5-24
in binary images 8-17	
phantom 7-32, 14-358	

preferences	R
Image Processing Toolbox display preferences	radon $14 ext{-}372$
3-38	example 7-24
ImshowAxesVisible 3-38	Radon transform
ImshowBorder 3-38	center pixel 7-23
ImshowTruesize 3-38	description of 7-21
TrueSizeWarning 3-39	example 7-32
Prewitt edge detector 14-127	inverse Radon transform 7-29
Prewitt filter 14-150	line detection example 7-27
profiles	of the Shepp-Logan Head phantom 7-33
reading ICC color profiles 12-19	relationship to Hough transform 7-27
projections	rank filtering 9-35
parallel beam 7-30	See also order-statistic filtering
projective transformations 4-11, 5-13	read-out noise
PSF	correcting 11-12
See point spread function	real orthonormal matrix 7-19
psf2otf 14-364	reconstruction
use of 11-22	morphological 8-19
	reference image
	in image registration 5-14
Q	reflect 14-374
qtdecomp 14-365	region labeling 8-40
example 9-19	region of interest
qtgetblk 14-369	based on color or intensity 10-5
qtsetblk 14-371	binary masks 10-3
quadtree decomposition 9-19, 14-365	definition 10-2
definition 9-2	filling 10-9
getting block values 14-369	filtering 10-6
setting block values 14-371	polygonal 10-3
quantization 12-7	selecting 10-3
minimum variance 12-9	using arbitrary binary masks 10-4
performed by rgb2ind 14-386	region property measurement 9-11
tradeoffs between using minimum variance	regional maxima
and uniform quantization methods	definition 8-3, 8-29
12-11	imposing 8-33
	suppressing 8-31

regional minima	specifying a colormap to use 12-11
definition 8-3, 8-29	uniform quantization example 12-9
imposing 8-33	used in dithering 12-13
suppressing 8-31	using 12-7
regionprops 14-375	rgb2ntsc 14-387
using 1-19, 9-11	example 12-22
registering an image 5-4	rgb2ycbcr 14-388
regularized filter	example 12-23
used for deblurring 11-9	Richardson-Lucy algorithm
replication	See Lucy-Richardson
to avoid border effect 6-12	ringing
resizing images 4-5	in image deblurring 11-23
antialiasing 4-7	Roberts edge detector 14-127
resolution	roicolor 10-5, 14-390
screen color resolution 12-3	roifill 14-391
See also bit depth 12-3	example 10-9
RGB color cube	roifilt2 14-393
description of 12-7	contrast example 10-6
quantization of 12-8	inline example 10-7
RGB images 2-9	roipoly 14-395
converting to indexed 14-385	example 10-3
converting to intensity 14-383	rotation
definition 2-3	of images 4-8
displaying 3-30	
measuring the intensities of each color plane	
9-6	S
reducing number of colors 12-6	salt and pepper noise 9-35
rgb2gray 14-383	adding 14-260
rgb2hsv 12-23	sampling
converting RGB to HSV color space 12-24	handling undersampled images 11-13
example 12-25	saturation
rgb2ind $14\text{-}385$	in HSV color space 12-23
colormap mapping example 12-12	in NTSC color space 12-22
example 12-12, 12-13	screen bit depth 12-3
in minimum variance quantization 12-9	definition 12-2
minimum variance quantization example	screen color resolution 12-3
12-10	definition 12-2

ScreenDepth 12-3	determining composition 14-225
Shepp-Logan head phantom 7-32	subimage 3-22, 14-407
shrinking	subplot 3-21
See resizing images	subtraction
Signal Processing Toolbox	of one image from another 1-13
hamming function 6-21	$sum2 ext{-}4$
16-bit image files	surf
creating 2-19	viewing images 1-12
reading 2-16	
skeletonization 8-17	
sliding neighborhood operations 13-4	T
center pixel in 13-4	template matching 7-13
padding in 13-5	texture mapping 3-36
Sobel edge detector 14-126	tformarray $14\text{-}409$
Sobel filter 14-150	tformfwd $14\text{-}413$
spatial coordinates 2-32	tforminv $14\text{-}415$
spatial domain	thresholding
definition 7-2	to create a binary image 1-15
speckle noise	to create indexed image from intensity image
adding 14-260	14-176
statistical properties	tomography 7-29
mean 14-338	tracing boundaries 9-13
of image objects 1-20	transformation matrix 6-18
standard deviation 14-397	transforms 7-1
std2 9-11, 14-397	definition 7-2
storage classes	discrete cosine 7-17, 14-98
converting between 2-20	discrete Fourier transform 7-8
of images 2-3	Fourier 7-3
strel 14-398	inverse Radon 7-29
stretchlim 14-405	Radon 7-21
adjusting image contrast 1-14	two-dimensional Fourier transform 7-3
using 9-24	translate 14-417
structuring elements 8-7	transparency 12-4
creating 8-8	truesize 14-418
decomposition of 8-9	used with imshow 3-19
decomposition sequence 14-174	truncation rules
definition 8-3	for image arithmetic operators 2-29

24-bit image files 2-9 xyz2double 14-431 xyz2uint16 14-432 U Υ uint16 storing images in 2-16 YCbCr color space 12-23 ycbcr2rgb 14-433 uint8 storing images in 2-16 using 12-23 uintlut 14-421YIQ color space 12-22 undersampling correcting 11-13 uniform quantization See quantization unsharp filter 14-150 unsharp masking 6-15 W warp 14-422example 3-36 using 3-36 watershed 14-424weight array in deblurring 11-12 whitepoint 14-428Wiener filter deblurring with 11-7 wiener2 14-429adaptive filtering 9-37 using 9-37 windowing method (filter design) 6-20, 14-158, 14-162 X

X-ray absorption tomography 7-29

XYZ color space 12-15

Z

zero padding 7-13
and the fast Fourier transform 7-10
image boundaries 6-10
zero-cross edge detector 14-127
zero-frequency component 7-3
zooming
Control Point Selection Tool 5-19
with Image Viewer 3-11